Account info guides

Category: Account management

These articles describe how to manage account access.

About profile and security settings

/en/guides/about-profile-and-security-settings

IMPORTANT

This guide only applies to customers with Fastly accounts or with Signal Sciences accounts that are linked to Fastly accounts. If you only have a Signal Sciences account, check out our information about the My profile menu instead.

You can manage your Fastly accounts, your personal profile information, and the security settings on your account, all in the same location.


Before you begin

Be sure you know how to access the web interface controls before learning about the details you'll encounter here.

About profile and security settings

Your account profile and security settings appear on a new tab, outside of the Fastly control panel, when you select **Profile & security** from the user quick links menu or go to **Account** >

Profile and security.



From here, you can:

- manage your profile information and do things like change your profile name
- change or reset an account password
- manage two-factor authentication

> **TIP**
>
> If you use both the Fastly and Next-Gen WAF control panels, you can switch between them by clicking one of the links that appears above the your profile and security settings.

What's next

Dig deeper into details about all areas of the web interface before you move on to working with services.

---

* * *

About the Account pages

/en/guides/about-the-account-pages

Use the Account pages in the Fastly control panel to review and manage (depending on the roles and permissions you've been assigned) various aspects of your company's account, as well as your personal account access and its appearance.

Before you begin

Be sure you know how to access the web interface controls before learning about each of the pages you'll encounter there.

About the Account controls

From the **Account** controls, you can access:

- the **Company settings** page where you can control details that identify your company (e.g., the owner and various company contacts), as well as the location to enable a login IP allowlist, enable company-wide account options (e.g., two-factor authentication), and cancel your account.
- a **User management** page where you can control user invitations and configure their roles.
- an **API tokens** menu where you can view details about and manage API tokens associated with your account.
- an **Audit log** page where you can monitor events related to your account, users, and services.
- the **Single sign-on** page where you can manage user authentication by enabling single sign-on (SSO).
- a **Billing** menu where you can review metrics related to your use of products and features enabled on your account, as well as control how you are charged for them.
- a **Your accounts** page where you can view details about the accounts to which you have access, if you've been invited as a member to more than one.

- a **Profile and security** link that takes you to where you can manage the personal information and security settings used when you log in to an account.

What's next

Dig deeper into details about all areas of the web interface before you move on to working with services.

---

* * *

📄	**About the Sustainability dashboard**
🔗	/en/guides/about-the-sustainability-dashboard

IMPORTANT

This information is part of a beta release. For additional details, read our product and feature lifecycle descriptions.

Located in the account area of the Fastly control panel, the Sustainability dashboard provides data visualizations for Fastly's carbon emission and data center energy consumption to anyone assigned the role of billing or superuser on your account. To calculate your sustainability and usage data, we measure the energy requirements of running Fastly services from both renewable and non-renewable sources and the carbon intensity of the energy grids serving Fastly data centers hosting those services in the regions where you have generated usage.

Before you begin

Be sure you know how to access the web interface controls before learning about the details you'll encounter here.

Limitations and considerations

When viewing the Sustainability dashboard page, keep the following things in mind:

- The sustainability data provided here is Fastly's Confidential Information as per your agreement with Fastly. You may include Fastly sustainability data as part of an

aggregate carbon footprint report that does not disclose the Fastly sustainability data as a standalone number or identify Fastly in any form.

- The sustainability data includes Scope 1 and 2 carbon emissions as defined under the Greenhouse Gas Protocol.
- Data on this dashboard is subject to estimations and measurement uncertainties due to the limitations inherent in the nature of such data and the methods of calculation. Our estimates may be affected by these inherent measurement uncertainties and could vary if we employ different measurement techniques in the future.

About the controls

A series of controls appears to the right of the page name. These controls allow you to refine the displayed metrics. Specifically:

- the **Location** menu allows you to select the country where the metrics are drawn from.
- the **Date** menu allows you to change the timeframe over which metrics will be displayed.
- the **Export** menu allows you to create a PRD of the metrics or to export the metrics to a CSV file.

About the metrics

The Sustainability dashboard displays the following metrics:

- **Total Power:** sum of renewable and non-renewable power consumed by Fastly infrastructure.
- **Renewable Power:** amount of renewable power consumed by Fastly infrastructure.
- **Non-renewable Power:** amount of non-renewable power consumed by Fastly infrastructure.
- **Carbon:** amount of carbon emissions produced by Fastly infrastructure.
- **Bandwidth:** total number of bytes delivered.

What's next

Dig deeper into details about all areas of the web interface before you move on to working with services.

---

* * *

📄	**Account lockouts**
🔗	/en/guides/account-lockouts

Why is my account locked?

For security reasons, Fastly limits the number of times someone can try logging in to an account. We don't want to give people unlimited attempts at guessing your password, so we stop them from trying after a limited number of failed attempts to sign in. You can change your password at any time when you're logged in to your account.

I am not using two-factor authentication. How can I access my account?

Once locked, you will not be able to sign in to your account, even with the correct password. To unlock your account because you exceeded the number of guesses you were allowed, you can either:

- reset the password yourself.
- ask a superuser associated with your account to send you a password reset email.

I am using two-factor authentication. How can I access my account?

I don't have my mobile device.

If you do not have access to your mobile device, you can complete the login process using one of your recovery codes. These were the recovery codes you saved in a secured location outside of your Fastly account when two-factor authentication was first enabled. You can continue to use your recovery codes until your device is once again accessible. Recovery

codes can only be used once, however, so remember to regenerate a new set to avoid running out before you recover your mobile device.

If you don't believe you will be able to recover your lost mobile device and you still have at least two recovery codes left, you can log in with one recovery code and disable two-factor authentication with a second code. Once two-factor authentication is disabled, you can re-enable it with a new mobile device at a later time and regenerate a new set of codes.

I don't have my mobile device and I don't have my recovery codes.

If you don't have your mobile device and didn't save any recovery codes, have another user at your company with the superuser role follow the steps to reset a user's two-factor authentication. If you don't know who a superuser is at your company, contact support.

I don't have my phone, I didn't save my recovery codes, and I am the only superuser for the account.

Contact Customer Support. We will verify that you are associated with the company by phone. We will use the contact information located on the company website or under the Fastly account tab. Upon verification, we will send you a recovery code and reset your password.

Was my account compromised?

If a user's account appears to be hacked or phished, we may proactively reset the passwords for the affected accounts to revoke access to the hacker. In these cases, we send an email to the account's real owner (you) with additional information on how to reset the password. If you received one of these emails, follow the instructions in the email.

If you think your account has been hacked or phished, contact Customer Support immediately.

How is a locked account different from a blocked account?

Fastly allows you to restrict who can access your Fastly account based on the IP address of the person attempting to log in. This means that even with the correct login name and password, access to your Fastly account may be blocked if the IP doesn't match your company's list of allowed addresses.

If your company enables this optional IP allowlisting, they must keep the list of restricted IP addresses up to date. Only users with the role of superuser can make changes to the IP

allowlist settings (your account owner is always a superuser), and your account owner must have a valid telephone number on file to do so.

If your IP addresses change after allowlisting is enabled and you forget to update your allowlist configuration, you will be locked out of your account. You will need to contact support to request that a Customer Support representative contact your account's owner via telephone during Fastly's regular business hours. To protect your account's security, we will not unlock your account based on an email request alone.


---

* * *

Changing company profile details

/en/guides/changing-company-profile-details

Fastly allows you change most of the details about your company after your account has been created, including the company name and address, the company's listed account owner, and any of the contacts you've created for specific company communications.



NOTE

Customer IDs are automatically generated upon account creation and cannot be edited.

Who can view and change company profile details

Users assigned the role of engineer can view company profile details. You must be the account owner or be assigned the role of superuser to change company profile details.

Changing an account's company settings

Fastly allows you to change an account's company settings like company name, owner, and company address at any time after your account has been created.

1. Log in to the Fastly control panel and select **Account** from the navigation sidebar.
2. In the **Company name** field of the **Company settings** area, replace the current company name with the new one. This is the company name that will be displayed on your monthly invoice.
3. From the **Owner** menu, select a new company owner from the available names.
4. In the **Address (optional)** field, replace the existing company address with the new one.
5. To define the specific range of IP addresses authorized to access your account, follow the instructions for enabling or disabling an IP allowlist.
6. Click **Update Company**.

Creating company contacts

We allow you to set up a variety of company contacts to help Fastly route conversations and requests to the correct humans in your organization. To create a new company contact:

1. Log in to the Fastly control panel and select **Account** from the navigation sidebar.
2. In the **Company contacts** area, click **Add contact**.
3. From the **Select contact type** menu, select the type of company contact to create:
    - **Primary:** Select this option to specify who Fastly should contact when account renewals and decisions (e.g., new product adoption) must be discussed with someone in your organization.
    - **Technical:** Select this option to specify who Fastly should contact when product changes (e.g., retirements and deprecations) must be communicated to someone

in your organization who can make changes to your services.

- **Security:** Select this option to specify who Fastly should contact when security-related vulnerabilities or incidents must be communicated to someone in your organization.
- **Emergency:** Select this option to specify who Fastly should contact when urgent, high-severity issues must be communicated to someone in your organization.
- **Billing:** Select this option to specify who Fastly should contact when sending out invoices to someone in your organization or for confirmation of cost-based training that will be billed at the account level.
- **Third-Party Reports:** Select this option to specify who Fastly should contact when compliance-related issues (e.g., DMCA, GDPR) need to be addressed by someone in your organization.

4. From the **Name** menu, select the name of the human contact to specify for this contact type.

> TIP
>
> Some contacts for your organization may not have nor require Fastly accounts and, thus, can't be selected from the controls. You can enter contact information manually by instead clicking **Enter contact manually** to enable manual entry of information in all Company contacts fields.

5. *(Optional)* In the **Phone number** field, enter a telephone number at which to contact the selected user.
6. Click **Add**. The contact's information appears.

> IMPORTANT
>
> Company contact information can only be added or removed, not edited. Once you've added at least one company contact of a particular type, you cannot remove that contact until you've added another of the same type to replace it. To update a contact's information, remove their entry via the **Remove** link and re-add them to the company contacts list instead. Contacts are automatically removed from the system if the assigned contact is deleted as an account user.

* * *

Enabling an IP allowlist for account logins through the web interface

/en/guides/enabling-an-ip-allowlist-for-account-logins-through-the-web-interface

Fastly allows you to define the range of IP addresses authorized on your Fastly account from which users are able to login to the Fastly control panel. It can restrict access to most of Fastly's API endpoints.

Limitations and considerations

An account owner telephone number is required in case of account lockouts. During setup, Fastly checks your current IP address against the list you provide to ensure you don't lock yourself out of your account. If your IP addresses change at a later date (for example, because you move offices) and you forget to update your allowlist configuration, you will be locked out of your account.

WARNING

If you are locked out of your account, you will need to contact support and request that a Customer Support representative contact your account's owner via telephone during Fastly's regular business hours. To protect your account's security, ***we will not unlock your account based on an email request alone***.


Several API endpoints are exempt from allowlisting. By design, some API endpoints such as historical stats or real-time analytics do not enforce customer IP allowlist checks. For endpoints that support that functionality, if an IP address outside of an allowlist is used to make an API request, the API will respond with a 403 Forbidden error that includes an appropriate error message. For more information about this functionality, contact support.

Enabling an IP allowlist for account logins through the control panel

> **NOTE**
>
> Only superusers have the ability to access this feature.

To restrict logins to the Fastly web interface based on a specific list or range of IP addresses, follow these steps.

1. Log in to the Fastly control panel and select **Account** from the navigation sidebar.
2. In the **Login IP allowlist** field of the **Company settings** area, replace `0.0.0.0/0` (the default IP range indicating no allowlisting) with the IP addresses for which control panel access to your account should be restricted.



   You can include single or multiple IP addresses or IP ranges (separated by commas) as follows:

   - a single IPv4 address (e.g., replace the default with `192.168.0.1`)
   - an IPv4 CIDR range (e.g., replace the default with `192.168.0.0/24`, `192.168.0.1/32`)
   - an IPv4 Wildcard range (e.g., replace the default with `192.168.0.*`, `192.168.*.1`, `192.168.*.*`)

3. Click **Update Company**.

Disabling an IP allowlist for account logins through the control panel

To disable IP allowlisting on your Fastly account and allow control panel access to any IP range, follow these steps.

1. Log in to the Fastly control panel and select **Account** from the navigation sidebar.

2. In the **Login IP allowlist** field of the **Company settings** area, enter `0.0.0.0/0` (the default IP range indicating no allowlisting).

3. Click **Update Company**.

---

* * *

📄	**Logging in and using Fastly**
🔗	/en/guides/logging-in-and-using-fastly

> **IMPORTANT**
>
> This guide only applies to customers with Fastly accounts or with Signal Sciences accounts linked to Fastly accounts.

The Fastly control panel allows you to use a web browser to log in from anywhere. If you have trouble logging in, refer to our guide on troubleshooting your login.

Before you begin

Keep in mind the following:

- **Keep password managers up to date.** Most password managers associate entries in their databases according to specific website domains. If you've stored your username and password combination there for either your Fastly or Signal Sciences accounts, your password manager won't have any way of knowing when you've added or updated information. You must always manually enter and update the information in your password manager yourself.
- **Single sign-on (SSO) is enforced per your organization's settings.** If your organization has single sign-on (SSO) enabled (for Fastly accounts or Signal Sciences accounts), you will be prompted to authenticate with SSO or will be automatically signed-in if you're already authenticated. This includes your login for other Fastly assets linked to your Fastly account (for example, your Support portal login).
- **Fastly Support portal access uses the same account.** You can log in to the Fastly Support portal using the same credentials as your Fastly account.

- **Two-factor authentication is enforced per you or your organization's settings.** If you or your organization has enabled two-factor authentication for Fastly accounts or Signal Sciences accounts, you'll need to enter a code generated by an authenticator app as part of the login process.


Logging in to your account with your email and password


1. Navigate to the appropriate login page for your account, either https://manage.fastly.com/ or https://dashboard.signalsciences.net/.
2. In the **Email** field, enter the email address associated with your account.
3. Click **Continue**.
4. In the **Password** field, enter the password associated with the email address you entered.
5. Click **Log in**.
6. *(Optional)* If your account has two-factor authentication enabled then, in the **Authentication code** field, enter the code generated by the authenticator app on your mobile device.
7. Click **Complete login**.

Switching between application control panels

Regardless of which account you log in to first, you can switch between the Fastly and Next-Gen WAF control panels a couple of different ways.


The switcher menu appears as nine squares in a three-by-three grid at the top of the browser:





Clicking the switcher menu ⠿ with the Fastly control panel active will open the Next-Gen WAF control panel in a new browser tab. Likewise, clicking the switcher menu ⠿ with the Next-Gen WAF control panel active will open the Fastly control panel in a new browser tab.

You can also switch between control panels by clicking one of the control panel links that appears above the your profile and security settings:



Logging out of your account

To log out of your account, do one of the following:

- To log out of your Fastly account, select **Sign out** from the **user quick links menu**.
- To log out of your Signal Sciences account, select **Sign out** from the **My Profile menu**.

* * *

Managing two-factor authentication

/en/guides/managing-two-factor-authentication

IMPORTANT

This guide only applies to customers with Fastly accounts or with Signal Sciences accounts linked to Fastly accounts. If you only have a Signal Sciences account, check out our guide to enabling and disabling two-factor authentication instead.

Fastly supports two-factor authentication, a two-step verification system, for logging in to the control panel and other linked Fastly assets (e.g., the Fastly support portal). In a two-factor authentication security process, users provide two means of identifying themselves to the system, typically by providing the system with something they know (for example, their login ID and password combination) and something they have (such as an authentication code).

Before you begin

You'll need to enter an authentication code regularly. Once two-factor authentication has been enabled for your Fastly account, an authentication code will be requested upon login at least every 14 days for each computer and browser you use to access the Fastly control panel or a linked Fastly asset.

A mobile device is required. Using this security feature with a Fastly account requires a mobile device capable of scanning a barcode or QR code using a downloadable authenticator application. We recommend the following:

- For Android, iOS, and Blackberry: Google Authenticator
- For Android and iOS: Duo Mobile
- For Windows Phone: Authenticator

There are special requirements for using this feature with API tokens generated for the Fastly control panel. Check out the API token documentation for more information.


Managing two-factor authentication as a user

Depending on whether or not your organization has enabled company-wide two-factor authentication, you may be able to enable and disable two-factor authentication for your personal account. We also have instructions for recovering access to your account if you lose your mobile device.


Enabling two-factor authentication

Follow these steps to enable two-factor authentication for your account.

1. Log in to the Fastly control panel.
2. Go to **Account** > **Profile & security**.
3. Click **Two-factor authentication**.



4. Click **Continue** and then reauthenticate your login credentials.



5. Launch the authenticator application installed on your mobile device and scan the QR code on the setup page. A time-based authentication code appears on your mobile

device. If a browser link appears, click it to save the code. When you do, the words `Secret saved` appear briefly.

6. In the **One-time code** field in the setup page, enter the time-based authentication code displayed by your mobile device.

> IMPORTANT
>
> **Google Authenticator Users:** A common time syncing issue may cause your authenticator codes to fail. You can correct this using Google's instructions.

7. In the **Device name** field, enter a name to help you identify your device and then click **Continue**.
8. Click **Finish setup**. Two-factor authentication will be enabled for the next time you log in.
9. Generate recovery codes for your account in case of emergency.

Once you enable two-factor authentication for your account, any other open sessions in other browser windows will require reauthentication in those windows using an authentication code generated by the authenticator application installed on your mobile device (in addition to your email and password). Future logins will also require an authentication code. By default, the system requires you to authenticate your login using an authentication code at least every two weeks for each computer and browser you use to access the Fastly control panel or linked Fastly asset.

Generating recovery codes

If you're ever unable to access your mobile device, recovery codes can be used to log in when your account has two-factor authentication enabled. Each of these recovery codes can only be used once, but you can regenerate a new set at any time and any previously generated codes that are still unused will be invalidated.

To generate recovery codes, follow these steps.

1. Log in to the Fastly control panel.
2. Go to **Account** > **Profile & security**.
3. Click **Two-factor authentication**.
4. Click **Generate recovery codes**.
5. Click **Download recovery codes** and then save them in a secure location.

> **IMPORTANT**
>
> Be sure to store a copy of your recovery codes in a safe place in the same order they appear on the screen. You'll need to use them in the displayed order if you lose access to your mobile device and need to use a recovery code in place of the authentication application to access your account.

6. Click **I've saved my recovery codes**.

Disabling two-factor authentication

Once two-factor authentication is enabled for your account, you can disable it at any time by following these steps.

> **IMPORTANT**
>
> If your organization has enabled company-wide two-factor authentication, you cannot disable two-factor authentication for your account.

1. Log in to the Fastly control panel.
2. Go to **Account** > **Profile & security**.
3. Click **Two-factor authentication**.
4. Click **Disable two-factor authentication**.
5. In the **Your authentication code** field, enter the time-based authentication code displayed in the authenticator application on your mobile device, then click **Disable**.

> **NOTE**
>
> If you have lost your mobile device, you can enter a recovery code in the **Authentication Code** field. For more information, check out the section on what to do if you lose your mobile device. If your organization has enabled company-wide two-factor authentication, you can also contact a superuser in your organization and ask them to reset it for you.

What to do if you lose your mobile device

If you lose your mobile device after enabling two-factor authentication, use a recovery code to log in to your Fastly account.

WARNING

You must use the recovery codes for your account in the order they were supplied to you. If you don't, an invalid recovery code error will appear and you'll be asked to enter the next valid code in your list.

You can continue to use recovery codes to log in until you get your mobile device back. Recovery codes can only be used once, however, so remember to regenerate a new list of codes as needed to avoid running out before you recover your mobile device.

If you do not believe you will be able to recover your lost mobile device and you still have at least two recovery codes left, you can log in with one recovery code and disable two-factor authentication with a second code. Once two-factor authentication is disabled, you can re-enable it with a new mobile device at a later time and regenerate a new set of codes.

Locked out of your account? Check out our article on what you can do about it.

Managing two-factor authentication as a superuser


Organizations can enable two-factor authentication users one at a time or all at once for all of their users. When the company-wide two-factor authentication feature is enabled, all users within the organization are required to use two-factor authentication to log in to the Fastly control panel, and they cannot disable two-factor authentication for their accounts.

IMPORTANT

Two-factor authentication enforcement (2FA enforcement) at the company level can only be enabled for Fastly accounts or Fastly accounts with linked Signal Sciences accounts. Customers with only Signal Sciences accounts cannot enforce 2FA at the company level.

Enabling two-factor authentication for a single user

If you are assigned the superuser role for your organization, you can view who has two-factor authentication enabled the User management settings for your Account. Users with this feature enabled have 2FA displayed next to their names.



To disable two-factor authentication for any user within your organization, select **Disable 2FA** from the menu that appears when you click the gear next to that user's name.

Resetting a user's two-factor authentication

If company-wide two-factor authentication is enabled, and a user within the organization gets locked out of their account or needs to enable a new device, an account superuser can reset their two-factor authentication. To reset a user's two-factor authentication, follow the steps below.

1. Log in to the Fastly control panel.
2. Go to **Account** > **User management**.
3. In the **Users** area, click the gear next to a user and then select **Reset 2FA**. A warning message appears.
4. Click **Reset**. The user will need to set up two-factor authentication for their account the next time they log in.

Disabling two-factor authentication for a single user's account

If company-wide two-factor authentication is enabled, a superuser can disable two-factor authentication for a single user's account. This is typically done for user accounts being used for scripts and session authentication. To disable two-factor authentication for a single user's account, follow the steps below.

1. Log in to the Fastly control panel.
2. Go to **Account** > **User management**.

3. In the **Users** area, click the gear ⚙ next to a user and then select **Ignore 2FA**. A warning message appears.


4. Click **Ignore**. Two-factor authentication will no longer be required for the selected user.

Enabling company-wide two-factor authentication

Users assigned the superuser role can enable this feature on the Account page. To enable company-wide two-factor authentication for all users within your organization, follow the steps below.

1. Log in to the Fastly control panel and select **Account** from the navigation sidebar.

2. In the **Customer options** area, select **Enabled** from the **Company-wide two-factor authentication** controls.



3. Click **Update Customer Options**. A warning message appears stating that login sessions from non-2FA users in your company will immediately expire.


4. Click **Continue**. Two-factor authentication becomes required for all users in your company. Anyone currently logged in and not previously using 2FA on their account will be logged out of the Fastly control panel. Anyone who has not already enabled two-factor authentication for their account will be prompted to do so the next time they log in to the Fastly control panel.

Disabling company-wide two-factor authentication

A superuser can disable company-wide two-factor authentication. Once this feature is disabled, existing users within the organization will be able to manage their own two-factor

authentication settings, and new users will not be required to set up two-factor authentication to log in to the Fastly control panel. To disable company-wide two-factor authentication, follow the steps below:

1. Log in to the Fastly control panel and select **Account** from the navigation sidebar.
2. In the **Customer options** area, select **Disabled** from the **Company-wide two-factor authentication** controls.



3. Click **Update Customer Options**. A warning message appears.
4. Click **Continue**. Company-wide two-factor authentication becomes disabled.

---

* * *

Monitoring account activity with the audit log

/en/guides/monitoring-account-activity-with-the-audit-log

The audit log keeps track of events related to your Fastly account, users, and services. You can use the audit log to determine which changes were made and by whom. For example, you can use the audit log to review:

- when API tokens were created

- who logged in to your account via the control panel
- what types of changes may have been made to your service configuration settings and by whom (e.g., a user assigned to your account, a Fastly user acting on your behalf)
- when users make changes to their account security settings
- when superusers purchase additional products and features for your account via the control panel

You can use the Fastly control panel and API to view the audit log.


> **TIP**
>
> For information on monitoring events related to a service, check out our guide on the event log. For information on monitoring the data that passes through Fastly, check out our guide on Fastly's real-time log streaming features.

Accessing the audit log via the Fastly control panel

You must be assigned the role of superuser to view the audit log. You can filter audit log events by event type, token ID, service ID, user ID, and date directly in the Fastly control panel.

Follow these instructions to access the audit log for your account:

1. Log in to the Fastly control panel.
2. Go to **Account** > **Audit log**.



NOTE

As of June 22, 2021, audit log data is retained for a period of one year (365 days).

Accessing the audit log via the Fastly API

The `/events` API endpoint can be used to retrieve the audit log for a Fastly account. For example, you could make the following API call in a terminal application to retrieve a filtered view of all recent audit log events:

```
$ curl -g -H "Fastly-Key: FASTLY_API_TOKEN" "https://api.fastly.com/er
```

The response will look like this:


```
{
  "data": [
      {
          "attributes": {
              "admin": false,
              "created_at": "2016-06-06T20:05:10Z",
              "customer_id": "x4xCwxxJxGCx123Rx5xTx",
              "description": "Version 2 was activated",
              "event_type": "version.activate",
              "ip": "127.0.0.0",
              "metadata": {
                  "version_number": 2
              },
              "service_id": "SU1Z0isxPaozGVKXdv0eY",
              "user_id": "x9KzsrACXZv8tPwlEDsKb6"
          },
          "id": "5IH1QmNSV1Qi7jXc4oIZlZc",
          "type": "event"
      }
  ],
  "links": {
    "last": "https://api.fastly.com/events?filter[customer_id]=x
  }
}
```

```
24  }
```

Check out the Fastly API documentation for more information.

---

* * *

Reviewing service activity with the event log

/en/guides/reviewing-service-activity-with-the-event-log


Event logs keep track of events related to a service. With the appropriate user role and permissions you can use event logs to determine which service-level changes were made and by whom. For example, you can use them to see who activated the most recent version of a service and view recent service configuration setting changes.

> **TIP**
>
> For information on monitoring Fastly account activity, check out our guide on the audit log. For information on monitoring the data that passes through Fastly, read our guide on Fastly's real-time log streaming features.

Follow these instructions to access the event logs for a service:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.

The last 20 service-related events are displayed near the bottom of the page, in the Event log area.



NOTE

As of June 22, 2021, event log data is retained for a period of one year (365 days).

* * *

Troubleshooting your login

/en/guides/troubleshooting-your-login

This guide describes what to do if you're having trouble logging in to https://manage.fastly.com/ or the Fastly Support portal.

I can't log in

If you're having trouble logging in to the Fastly control panel or the Fastly support portal, check if any of the following are true:

- **There are outages or scheduled maintenance.** Check the Fastly status page to make sure there are no outages or scheduled maintenance currently affecting Fastly systems and your login capabilities.
- **Your email and password are incorrect.** Make sure you're using the correct email for your account, especially if you have multiple accounts. If you've forgotten your password, learn how to reset it.
- **You're logging in at the wrong URL.** If you have a Fastly account or both Fastly and Signal Sciences accounts, use https://manage.fastly.com/ to log in. If you only have a Signal Sciences account use https://dashboard.signalsciences.net/ to log in. You can log in to the Fastly support portal from the Fastly control panel or use https://support.fastly.com.
- **Your account may be locked.** For security reasons, Fastly limits the number of times someone can try logging in to an account. Refer to Account lockouts for more information.

I don't see the features or data I'm looking for in the control panel

Information that appears in the Fastly web interface depends on several things, including the access you've been granted. If you don't have access to what you're looking for or can't see something you're expecting to see, check if any of the following are true:

- **Your account ID has incorrect permissions assigned to it.** The user role and permissions assigned to your account ID for your Fastly app access or your Next-Gen

WAF access affect what you can do in the web interface. Check with a superuser on your account if your access appears to be incorrect.

- **Your login session has timed out.** Once logged in to your account, your session can potentially remain active for up to 12 hours without requiring reauthentication. This depends on the session timeout settings for your Signal Sciences corp and whether or not SSO is enabled for either your Signal Sciences account or Fastly account. By design, session timeouts cannot exceed 12 hours. All users will be logged out automatically after 3 hours of inactivity.

- **You're signed in to a different account or control panel.** If you have both Fastly and Signal Sciences accounts you may need to switch application control panels to see the correct information. Likewise, if you have multiple Fastly accounts, make sure you sign in using the account that has the data you're looking for.

- **You're accessing a different Fastly service.** Every service tied to your Fastly account contains a unique ID that can help you determine if you're looking at the right information. Our guide on services provides more information that can help you switch services or search for the correct one.

- **You're looking at a different site in your Signal Sciences corp.** Be sure you're looking at the right site within your corp. Our web interface controls can help you select different sites from the corp navigation bar.

- **The product or feature isn't enabled for your account.** Some Fastly products and features (e.g., Image Optimizer) may be disabled by default but can be enabled directly in the web interface by anyone with the appropriate roles and permissions. If you can't access a product or feature you think you should have, check with a superuser on your account to make sure your permissions are properly set. If you still can't access a product or feature, contact support for assistance or contact sales@fastly.com to start a conversation about which features may be best for your account.

I don't see past support requests in the Support portal

When you create a Fastly account, your Support portal account gets created automatically.

If you don't see the support tickets you're expecting to see once you log in, especially for past support requests, it's likely that your Fastly account email address is different from the email address associated with your Support portal account. This might happen because:

- you changed your Fastly account email address but not your Support portal address

- you created a Support portal account with a different email address than your Fastly account
- you have more than one Support portal account and aren't logged into the correct one

Contact Fastly Support and provide us with your Fastly account and Support portal email addresses. We'll have your past support requests moved to the new email address and can even merge separate Support portal accounts after verifying your credentials.

I still can't log in or use Fastly the way I expect

If you continue to have issues logging in or using Fastly, contact Fastly Support.

---

* * *

📄	**Using API tokens**
🔗	/en/guides/using-api-tokens

API tokens are unique security credentials that allow human users and automated systems to prove their identity to Fastly, thereby indicating they can be trusted to access restricted resources and perform specific, restricted operations via the Fastly API.

Token types

There are two types of API tokens: user tokens and automation tokens.

User tokens

User tokens provide security credentials for API activities initiated by human users. They are associated with a specific human and are only active for the lifetime of their account. They are sometimes referred to as "personal tokens" or "personal API tokens."

Keep in mind the following things about user tokens:

- They can be created by any user and they only apply to the user that created them. This can't be updated.

- They carry the same permissions and scopes as the user who would be performing account-based actions via the API. For example, if you are a billing user, then your token will only allow you to perform the capabilities of the billing role.
- They must be deleted (revoked) before you can delete the account of the user who created them.

Automation tokens

Automation tokens provide security credentials for non-human clients (e.g., continuous integration and build systems) that need to conduct automated API activities like integration tests and routinely scripted tasks.

Keep in mind the following:

- They can only be created by users with the role of superuser and must use sudo mode to do so.
- They cannot be created via API if an account has force SSO or multi-factor authentication enabled.
- They can remain active indefinitely because they are not tied to a human user.
- They do not trigger or apply to Next-Gen WAF features and scopes.

Token scopes

You can limit the capabilities of API tokens by specifying the scope of their service-related activities. Specifically, you can allow or limit API tokens as follows:

- **Global API access (`global`)** allows the token full control over a service with access to all API endpoints, including purging.
- **Purge full cache (`purge_all`)** allows the token purging ability for an entire service via a `purge_all` API request.
- **Purge select content (`purge_select`)** allows the token purging ability via Surrogate-Key and URL but does not include the ability to purge all cache.
- **Read-only access (`global:read`)** allows the token read-only access to account information, configuration, and stats.

General limitations and best practices

When managing and using API tokens, keep in mind the following limitations:

- **API tokens can only be created, viewed, and deleted.** They cannot be edited or updated.
- **Each user is limited to 100 active API tokens.** Deleted and expired tokens don't count against the limit.
- **Unused tokens do not last forever.** API tokens that remain unused for two years are automatically deleted even if they have been set to never expire.
- **The event log only shows API token activity appropriate to your user role.** If you've been assigned the `user` role, you can only see events from your own actions. If you've been assigned the `engineer` role, you can see all events related to your own actions plus all the actions on services to which you've been granted access.

When creating API tokens, also keep the following best practices in mind:

- **Keep it secret. Keep it safe.** When you generate a new token, you should store it in a protected place like a password manager to keep it secret and safe. For security reasons, you will only be able to copy tokens once, at the time of creation. You won't be able to retrieve token strings later.
- **Consider implementing minimal privileges.** Limiting a token's service access, controlling its scope, and setting an expiration date restricts that credential's access can minimize the risk of damage if security credentials are somehow compromised. For more information, review the principle of least privilege.

Creating API tokens

To create API tokens, follow these steps.

Creating user tokens


> **IMPORTANT**
>
> Be sure you're creating tokens for the right account. If you've been invited as a user on multiple accounts, you'll need to switch to the appropriate account first.

To create user tokens, follow these steps:

1. Log in to the Fastly control panel.
2. Go to **Account** > **API tokens** > **Personal tokens**.

3. Click **Create token**.

4. When prompted, enter your password to re-authenticate your permissions.



5. Fill out the **Create a Token** fields as follows:

   - In the **Name** field, enter a descriptive name for the token that indicates how or where it will be used.

- *(Optional)* When visible, leave the **Type** option set to **User token**. These controls only appear when you've been assigned the role of superuser.
- From the **Scope** options, select one or more checkboxes to limit the token's access to a specific scope. Only the Scope options applicable to the chosen role will be selectable. Our guide to configuring user roles and permissions provides more information.
- From the **Access** options, select either all services or limit the token's access to a specific service or group of services by selecting them from the **Search or select service** menu.
- From the **Expiration** options, set the token expiration timeframe. By default the control panel will set the expiration date to 90 days from the date on which you create it. You can, however, set a token to never expire or you can select a specific date on which it expires.

> TIP
>
> After a token expires, using it for any request will return an HTTP 401 response.

6. Click **Create Token** to create the new token. A new token and its creation notification appears. This is the credential you'll use to authenticate via the Fastly API. You may use the same token for multiple applications.
7. Click the clipboard to copy the API token string so you can store it in a safe, secret location.

> WARNING
>
> This is the only time your API token string will be visible. Be sure to immediately copy it and store it in a safe location. It will never be visible again.

8. Click **Okay**.

Creating automation tokens

> NOTE
>
> Only superusers have the ability to create automation tokens.


To create automation tokens, follow these steps:

1. Log in to the Fastly control panel.

2. Go to **Account** > **API tokens** > **Personal tokens**.

3. Click **Create token**.

4. When prompted, enter your password to re-authenticate your permissions.



5. Fill out the **Create a Token** fields as follows:

    - In the **Name** field, enter a descriptive name for the token that indicates how or where it will be used.

- From the **Type** options, select `Automation token`.
- From the **Role** options, select the user role that will assign the appropriate access permissions to the API token. Available options are `Engineer`, `User`, and `Billing`. Our guide to configuring user roles and permissions provides more information.
- *(Optional)* Select **TLS management** to grant the token the ability to modify TLS configurations across all services, including TLS certificates and domains.
- From the **Scope** options, select one or more checkboxes to limit the token's access to a specific scope. Only the Scope options applicable to the selected role will be selectable. Our guide to configuring user roles and permissions provides more information.
- From the **Access** options, select either all services or limit the token's access to a specific service or group of services by selecting them from the **Search or select service** menu.
- From the **Expiration** options, set the token expiration timeframe. By default the control panel will set the expiration date to 90 days from the date on which you create it. You can, however, set a token to never expire or you can select a specific date on which it expires.

> TIP
>
> After a token expires, using it for any request will return an HTTP 401 response.

6. Click **Create Token** to create the new token. A new token and its creation notification appears. This is the credential you'll use to authenticate via the Fastly API. You may use the same token for multiple applications.
7. Click the clipboard to copy the API token string so you can store it in a safe, secret location.

> WARNING
>
> This is the only time your API token string will be visible. Be sure to immediately copy it and store it in a safe location. It will never be visible again.

8. Click **Okay**.


Viewing API tokens

To view API tokens, follow these steps.

Viewing user tokens

To view your personal user tokens, follow these steps:


1. Log in to the Fastly control panel.
2. Go to **Account** > **API tokens** > **Personal tokens**. The API tokens page appears with a list of your personal tokens.



Viewing account tokens

If you've been assigned the role of superuser, view account tokens using these steps:

1. Log in to the Fastly control panel.
2. Go to **Account** > **API tokens** > **Account tokens**. The Account Tokens page appears with a list of tokens associated with your organization's Fastly account.



Deleting API tokens

> **WARNING**
>
> Deleting an API token will break any integration actively using that credential.

To delete user or automation tokens, follow these steps.

Deleting user tokens

To delete a user token you've created, follow these steps:

1. Log in to the Fastly control panel.
2. Go to **Account** > **API tokens** > **Personal tokens**.
3. Find the token you want to delete and click the trash .
4. Click **Delete** to permanently delete the user token.


Deleting account tokens

To delete an account token or to revoke (and thereby delete) another user's token as a superuser, follow the steps:

1. Log in to the Fastly control panel.
2. Go to **Account** > **API tokens** > **Account tokens**.
3. Find the token you want to delete and click the trash .
4. Click **Delete** to permanently delete the token.

Legacy API credentials

If you created a Fastly account before May 15th, 2017, you may have used an API key (or multiple API keys) to authenticate API requests. This account-level credential was migrated to an API token with a `global` scope and access to all of your services. It was assigned to a newly created, synthetic user with the name `Global API Token`.



---

* * *

Category: Billing

These articles describe Fastly's billing and payment plans and how to make adjustments to your billing information.

	About the Billing menu
🔗	/en/guides/about-the-billing-menu

To access billing-related detail for your account, go to **Account** > **Billing**. This menu provides options that allow you to review and manage things related to the charges associated with products and features enabled for your account.

Before you begin

Be sure you know how to access the web interface controls before learning about each of the pages you'll encounter there.

Prerequisites

All users can see the Billing menu and the items within it, but you'll only be able to view the data on linked pages if you've been assigned the role of billing or superuser. All other user roles may see an error message indicating you're not authorized to view the information.

About the Billing menu

From the Billing menu, you can access:

- the **billing Overview** page where you can gain insight on past bills and usage related to bill-related metrics for your account broken down by product and region over key, monthly timeframes.
- the **Plan usage** page where you can view your account plans and usage details.
- the **Trials** page where you can view details about product or feature trials.
- the **Invoices** page where you can view a complete history of the monthly bills for your Fastly account and their payment statuses, which you can use to review your specific account charges that are active or can be started.
- the **Billing information** page where you can upgrade to a paid account from a trial account. Once on a paid account, you can view and edit your credit card information and update your billing address for your account, if you have the appropriate permissions to do so.

> NOTE
>
> Billing plan information is only available for Delivery customers.

What's next

Dig deeper into details about all areas of the web interface before you move on to working with services.

---

* * *

	About the Billing overview page
🔗	/en/guides/about-the-billing-overview-page

The Billing overview page allows you to view general billing information and bill-related metrics for your account broken down by product and region over key, monthly timeframes. When your user role allows, you access the Billing overview page by selecting **Billing** from the user quick links menu.

Before you begin

Be sure you know how to access the web interface controls before learning about the information you'll encounter here.


About the Billing overview page

This page provides high-level details about:

- the **Current plan** associated with your account, with links that allow you to view plan usage
- your most recent **Invoices**, with links to details about your bill for a specific month
- any **Purchased products** that have been added to your account
- **Billing metrics** in the form of graphs that show variable charges on your bill over time

About Purchased products

This page includes a card listing the products purchased for your account via the Fastly control panel and the date on which they were purchased. If you have not purchased products this way, you will not see this card.



You can view the usage information related to your purchased products by clicking **Usage**. In the **Options** menu, you can find out more information about the product by clicking the **Go to** link for the product or **Documentation**. You can also click **Cancel** to start the cancellation process for any product you've purchased through the Fastly control panel.

About Billing metrics

A series of graphs appear that provide insights into what you're being charged for by Fastly and how that amount applies to the various products you've purchased and the regions in which traffic to your services operates.

These graphs include:

- the **Total bill** graph, which displays the total US dollar amount that Fastly has billed your account over a specific time period
- the **Full-Site Delivery bill** graph, which displays the total US dollar amount your account has been billed for the Fastly Full-Site Delivery portion of your account's bill over a specific time period
- the **Compute bill** graph, which displays the total US dollar amount your account has been billed for Compute platform operations over a specific time period

- the **Bandwidth** graph, which displays the total bandwidth in gigabytes that has been processed for your account over a specific time period
- the **Requests** graph, which displays the total number of requests processed for your account over a specific time period
- the **Other services & products** graph, which displays the total US dollar amount that Fastly has billed your account for all Fastly products and services, not including Full-Site Delivery and Compute, over a specific time period
- the **Regional bills** graph, which displays how much you were billed for Fastly products and services within each geographical region of the world, excluding non-regional offerings, over a specific time period

When reviewing the metrics displayed on the billing graphs, keep the following things in mind:


- **Data doesn't appear in real time.** Unlike the metrics displayed in the Observability page graphs, data for billing metrics does not appear in real-time nor for time periods shorter than one month.
- **Dollar amounts shown are for US dollars.** For any graph displaying monetary amounts, these amounts appear in US dollars only.

Working with the Billing metrics graphs


You can interact with and control the Billing metrics graphs as follows.

Limiting data to specific geographic regions or products

By default any graph that displays metrics for regional offerings displays data for all regions. You can change these to display data for specific regions by selecting a specific region from the **Region** menu near the top of each graph.




Likewise, the **Regional bills** graph displays metrics for all products you currently pay for. You can change this to display data for a specific offering by selecting it from the **Product** menu near the top of the graph.



Changing displayed time periods


By default all graphs display billing data for the past six months. You can change this by selecting a new time frame from the month control at the top of the page to a maximum of 24 months.



Printing and exporting billing data

You can print a report of your billing data by selecting **Print** from the **Export** menu at the top of the page. This will launch the printing controls for your browser and allow you to send the report to a printer or create a PDF version of the data for the time period you've selected.

You can create an exportable version of your billing data by selecting **Export to CSV** from the **Export** menu at the top of the page. This will automatically download a CSV-formatted text file to a local directory.



What's next

Dig deeper into details about all areas of the web interface before you move on to working with services.

* * *

About the charges on your bill

/en/guides/about-the-charges-on-your-bill

We bill you as specified in your applicable ordering document. Unless otherwise specified, we will bill you monthly according to that month's use of Fastly's services.

> **NOTE**
>
> Billing limits for this product may be different if you've purchased a packaged offering or are using a product or feature trial.

About the monthly minimum charges

We bill a minimum of $50 per month so we can fully support all of our customers. This is the minimum price you'll pay in any month once you've completed your testing trials.

For example, say that you're done testing Fastly's services and you've begun to push production-level traffic through Fastly. If most of your site's traffic for the current month is in North America and Europe and your site uses 10GB of traffic over 10 million requests, the combined bandwidth and request charges would be $8.70 for the month. Because this amount falls below the $50 monthly minimum (you'll see this appear as a "commit shortfall" on your bill), we would charge you $50 for that month, not $8.70.

Bandwidth and request prices for some billing regions are slightly higher. If most of your site's traffic were in these other regions instead, then at the above traffic levels your bandwidth and request usage charges would still fall below the monthly minimum and we would charge you $50 for that month.

When we charge you for Fastly services

Fastly typically bills in arrears, not in advance, meaning that we bill you for services after you've used them, not before. For example, if you sign up for and start using Fastly services in January, the bill you receive in February reflects January's charges and services, your March bill reflects February's charges and services, and so forth.

How account cancellation affects your bill

If you ever cancel your account, you'll be billed for any outstanding charges accrued through the day you canceled, or at least the monthly minimum, whichever amount is greater.

Estimating your month-to-date bill

You can estimate your month-to-date (MTD) bill via the control panel or via the API.

Via the control panel

To view an estimated report of account usage for the current partial month, use any standard web browser to log in to your Fastly account and navigate to:

https://manage.fastly.com/billing/month-to-date

> NOTE
>
> A small number of billing plans cannot be calculated month-to-date and only include an end-of-month generated invoice. If you have one of these billing plans, the control panel will clearly tell you that you can't see the report due to your account's status.

Via the API

As part of our API, an endpoint exists to generate a report of your usage for the current partial month (known as month-to-date, or MTD). Full details of this endpoint's output format can be found in our Invoices API documentation.

---

* * *

	About the Plan usage page
🔗	/en/guides/about-the-plan-usage-page

The Plan usage page allows you to view your account usage metrics broken down by product and region over key, monthly timeframes, up to the last 24 months. These metrics provide insights into the monthly usage of things your account's billing is based on (for example, Image Optimizer requests or Concierge TLS). Use the information here to help you estimate your bill and plan for the future. To access the Plan usage page, go to **Account** > **Billing** > **Plan usage**.

Before you begin

Be sure you know how to access the web interface controls before learning about the information you'll encounter here.

About the Plan usage page

When your user role allows you access to this page, you'll find:

- a **Summary** area where you can view global, monthly usage-based metrics for your accounts.
- a **Usage** area where you can view a graph of your monthly trends for each of the usage-based metrics related to your accounts. Select a different metric using the menu above the graph. Hover the cursor over a specific date in the graph to display the specific metrics for that day.
- a **Service usage** area where you can view simple, monthly usage metrics on a per-service basis. Use the search box to search by service name or ID.
- a **Regional usage** area where you can view usage metrics within each geographical region of the world for past months and the current month to date. Expand or collapse a region by clicking on its name or use the controls to the right of the area's title to expand or collapse and hide all regions at once.

About the plan usage metrics data

When reviewing the metrics displayed on the Plan usage page, keep the following things in mind:

- **Per-service usage metrics appear only for the account you're logged in to.** To view per-service metrics for a child account, log in to that account.
- **Data doesn't appear in real time.** Unlike the metrics displayed in the Observability page graphs, data for plan usage metrics does not appear in real-time. Usage-based metrics are updated daily. The date and time of the last update appears at the top of the page.
- **Plan usage data is exportable.** You can create an exportable version of your plan usage data for each month by clicking the data export link at the top of the page.

What's next

Dig deeper into details about all areas of the web interface before you move on to working with services.

---

* * *

📄	**About the Trials page**
🔗	/en/guides/about-the-trials-page

The Trials page allows you to view details about product or feature trials that are active or can be started. The Trials page also provides access to usage metrics for trials you have started. To access the Trials page, go to **Account** > **Billing** > **Trials**.

Before you begin

Keep in mind the following limitations about trials:

- Only users assigned the billing or superuser role can access the Trials page.
- Only superusers can start trials or upgrade to full access of the product or feature once a trial period has ended.

About the Trials page

When your user role allows you access to this page, a list of cards for product lines with available trials appears. Clicking **Details** within any product line allows you to view the following details:

- whether or not an available trial is enabled or has been purchased for your account
- the date on which a specific trial started and its expiration date
- the name of the user who started the trial (that name will appear as "Fastly" if the trial was started by an internal Fastly admin and "Deleted user" if the trial was started by a user that has since been deleted from your account)
- access to summarized usage details for the trial
- a link to relevant documentation for the product or feature

TIP

Use the search bar to filter the page for specific trials.

Starting a trial

You can start trials for an entire product line or for any feature within that product line at any time:

- **Starting trials for entire product lines**. From any product line card, click **Start trial** to the right of the product line's name and then confirm that you want to start all trials for the entire product line.
- **Starting trials for specific features**. On any product line card, click **Details** underneath the product line name to expose the features available and then click **Start trial** to the right of the feature you want to trial.

Once a trial is enabled, you can immediately begin configuring it for use with your account or on your services. Keep in mind, however, that each specific trial can only be started once per account. Once the trial is over, you can upgrade your account to retain full access to the product or feature by clicking **Purchase**.

Monitoring trial usage

Once a trial has been started, click **Usage** to view usage metrics about your trial period. You can view these usage metrics even after the trial has expired.

* * *

	Account types
🔗	/en/guides/account-types

Fastly offers a variety of account types, which we detail below.

Trial accounts

We provide several ways to give Fastly a try before you purchase anything. Use a trial account to get hands-on experience exploring the capabilities of our platforms.

- **Delivery services development trials.** We offer a development trial that allows you to test our delivery services by simply signing up. We allow you to test up to $50 of traffic per month for free to ensure everything fits your requirements. You can pay as you go from there by switching to a paid account directly in the web interface. Keep in mind that some add-on options (bringing your own TLS certificates, for example) require you to switch your account to a paid account before that functionality becomes available to you.

- **Compute services development trials.** We offer a trial of Compute that allows you to gain experience working with Fastly's serverless edge platform. We allow you to test up to $50 of Compute charges. Once you've signed up for a Fastly account, start your trial by navigating to the Compute tab in the web interface and then following the on-screen prompts. Use the trial to test how serverless application concepts created in your non-production environment can be deployed to the Fastly Edge.

Keep in mind the limitations that apply to all trials:

- Trial accounts are not designed for use with production traffic or workloads.

- Trial accounts do not include customer support for Compute issues, nor are the service availability SLAs applicable. Only paid accounts include this support and the associated SLAs.

- Specific resource allocation limitations apply during your Compute trial. Compute has a lower resource allocation that can only be increased or removed if you upgrade to a paid account, at which point normal limitations and constraints apply. Contact sales@fastly.com for more information.

TIP

Already have an account but looking to start a trial for a specific product or feature? Check out the Trials page for details.

Paid accounts

You can sign up for a paid Fastly account via our control panel or by contacting us at sales@fastly.com.

Signing up for a paid account online

You can use Fastly's delivery services on a month-to-month basis across our global regions. Start by signing up for a trial, explore a bit, and then, when you're ready to start pushing production traffic our way, upgrade your account directly in the control panel.

Once you switch to a paid account, the developer account trial option disappears and we'll begin billing you automatically at the end of every month using your credit card information. You can estimate your monthly delivery charges by using the pricing estimator on our pricing page. For more detailed information on those monthly charges, including how we measure your usage and when we charge you for it, see our guide to how we calculate your bill.

Contact us at sales@fastly.com for more information if you plan to push at least 2TB of data per month for delivery and require one of our TLS service options, if you plan to push a minimum of 4TB of data per month, or if you want to purchase our Gold or Enterprise support offerings. We also offer solutions targeted to the needs of specific industries.

Other paid accounts

If you signed up for a paid Fastly account via a method other than our control panel, refer to your contract with Fastly for specific details about your services.

Fastly's open source and non-profit program

We provide free services to members of our open source and nonprofit program. If you are interested in participating in the program, contact us at community@fastly.com to get started.

---

* * *

📄	**Canceling your account**
🔗	/en/guides/canceling-your-account

You can cancel your Fastly account at any time. Have your account owner follow these steps:

1. Deactivate and then delete all services on your account.

2. If you've purchased one of Fastly's hosted or managed certificate options, deactivate TLS and delete the TLS domains.
3. If you've set up TLS with your own certificates, delete them and remove their private keys.
4. Go to **Account** > **Company settings**.
5. In the **Company settings** area, click **Cancel Account**.
6. In the **Your password** field of the confirmation window, enter the password associated with your account and click **Confirm and Cancel**.

After your account is canceled, you'll be billed for any outstanding charges accrued through the day you canceled. For questions about your final billing statement, contact our billing team for assistance. If you decide at a later date to reactivate your account, contact support and request reactivation.

---

* * *

	Managing account plans and usage details
🔗	/en/guides/managing-account-plans-and-usage-details

If you've been assigned a superuser or billing role, you can manage your account plans, including upgrading to a paid account, and review usage details and the associated charges by selecting **Billing** from the user quick links menu at the top right of any page.

Before you begin

Be sure you know how to access the web interface controls before learning about each of the pages you'll encounter there. Pay particular attention to the Billing menu.

Monitoring bill-related metrics

For paid-accounts, the Billing overview page allows you to view bill-related metrics for your account broken down by product and region over key, monthly timeframes. These metrics provide insights into what you're being charged for by Fastly and how that amount applies to


the various products you've purchased and the regions in which traffic to your services operates.

Monitoring account and service usage metrics


View your account usage metrics broken down by product and region over key, monthly timeframes by selecting **Plan usage** from the Billing menu. These metrics provide insights into the month-to-date usage of things your account's billing is based on (for example, Image Optimizer requests or Concierge TLS). Use the information here to help you estimate your bill and plan for the future.

Reviewing account charges and invoice details

View your account invoice information by selecting **Invoices** from the Billing menu. By default, the current balance for your account, if any, appears at the top, followed by your invoice history.



Clicking on the linked date of any invoice displays a summary of charges for that month. The billing invoice summary includes the overall bandwidth you used and the associated charges, followed by the charges you incurred for requests. The bottom of the summary displays the grand total dollar amount owed for the dated month.



Summary

Item	# of units	Total
Fastly TLS - Non-Profit CA / Bring Your Own Certificates Fastly TLS - Non-Profit CA / Bring Your Own Certificates (5 units @ $0)	5	$0.00
Fastly TLS - Non-Profit CA / Bring Your Own Certificates Fastly TLS - Non-Profit CA / Bring Your Own Certificates (300 units @ $20)	300	$6,000.00
Global Bandwidth Global Bandwidth (9,592,749.656134423 gigabytes @ $0)	9592749.6561344	$0.00
Global Requests Global Requests (63,834,206.1305 units @ $0)	63834206.1305	$0.00
Image Optimizer Professional Requests Image Optimizer Professional Requests (180.852185 units @ $0)	180.852185	$0.00
Subscriber Provided Prefix	1	$0.00
Grand Total		**$6,000.00**

Below the month's summary on the invoice, we include regional bandwidth and request details for each billing region. The bottom of each regional details section includes the total charge for bandwidth and requests for that region alone for the dated month.

> **NOTE**
>
> An itemized list of billing charges per service is not available. Check out our historical stats API for data on unrated request and bandwidth used by a service, aggregated by billing region.

You can print account use details for any month by finding that month in the invoice history and clicking **Print** in the **Actions** column for that month.

Upgrading to a paid account

If you are on a trial account for delivery services, you can upgrade to a paid account from the **Billing information** page, if you have the appropriate permissions to do so.

> **NOTE**
>
> To upgrade your account for Compute services, contact sales@fastly.com.

What's next

Continue to explore your account management and billing information.

* * *

	Paying your bill
🔗	/en/guides/paying-your-bill

At the end of each month, your account's billing contact will be sent an email summarizing your current usage levels and the charges your account incurred for the month. The email contains a link to an online copy of the related invoice.

You'll need both a valid credit card and current billing address when you switch to a paid, month-to-month account. Once your invoice gets generated, your credit card is automatically charged for the full, outstanding balance.

Changing your credit card information or billing address

To change your billing address or the information for the credit card we use for automatic billing, follow the steps below:

1. Log in to the Fastly control panel.
2. Go to **Account** > **Billing** > **Billing information**.
3. In the **Billing details** area, click **Edit**.
4. Make any necessary changes to the payment information in the fields provided.

> TIP
>
> Fastly never sees your credit card number. All transactions handled by our payment gateway are fully PCI compliant. The gateway privacy policy can be found at https://stripe.com/legal/privacy-center.

5. Click **Save payment information**.
6. Make any necessary changes to the billing address in the fields provided.
7. Click **Save billing address**.

Changing who receives your bill

By default, your account owner is considered your billing contact and will receive your bill for Fastly services. To change who receives your bill or to add multiple email addresses for several billing contacts, contact billing@fastly.com with the addresses you'd like to send invoices to.

IMPORTANT

Invoices are only sent to the email addresses of the account owner or the billing contact. Invoices are not sent to every user assigned a billing role.

* * *

Upgrading your account

/en/guides/upgrading-your-account

NOTE

To upgrade your account for Compute services, contact sales@fastly.com.

You can upgrade your Fastly account for delivery services in the control panel. Have an account superuser follow these steps:

1. Log in to the Fastly control panel.
2. Go to **Account** > **Billing** > **Billing information**.
3. Enter your billing address information in the fields provided.
4. Click **Save and continue**
5. Enter your credit card information in the fields provided.
6. Review the terms of the purchase agreement and click **Complete purchase** to upgrade your account.

TIP

Fastly never sees your credit card number. All transactions are handled by our fully PCI compliant payment gateway and their privacy policy can be found at https://stripe.com/legal/privacy-center.

* * *

Category: User access and control

These articles describe how to manage users with permission to access to your account.

Adding and deleting user accounts

/en/guides/adding-and-deleting-user-accounts

Fastly allows superusers to add users to an existing account via invitation, assigning them different roles and permissions as appropriate. You can delete user accounts when you no longer want someone to have access.

Before you begin

Before you begin working with user accounts, keep in mind the following:

- **Adding users to Signal Sciences accounts only**. If you only have a Signal Sciences account, not a Fastly account, follow the instruction in our guide to managing Next-Gen WAF users.
- **Changing who receives your bill.** Follow our billing contact instructions to change who receives your bill.

Adding account users

Adding account users happens via an emailed invitation. Follow these instructions to manage account invitations.

Adding a user to an account

To invite a user to an account:

1. Log in to the Fastly control panel.
2. Go to **Account** > **User management**.
3. In the **Pending user invitations** area, click **Invite a user**.
4. In the **Email** field, enter the email address of the user to invite.
5. From the **Role** options, select the role to assign the user once they accept the invitation.
6. *(Optional)* Select or deselect the **TLS management** box to grant or remove TLS configuration access to a user. Users with the role of superuser have this permission by default. You can grant this to other roles if you choose.
7. *(Optional)* Select or deselect the **Bypass SSO** box to allow this superuser to log in with a username and password even when SSO sign-on is enabled.
8. *(Optional)* Limit access to selected services for this user by doing the following:
   - From the **CDN & Compute service access** controls, select **Limit access to selected services**.
   - From the **Manage service access** controls, select the specific permission levels for each service this user should be able to access. Leave the permissions blank to keep specific services hidden.
9. *(Optional)* Limit access to selected workspaces for this user by doing the following:
   - From the **Next-Gen WAF workspace access** controls, select **Limit access to selected workspaces**.
   - From the **Manage service access** controls, click the switch next to the appropriate workspace to allow access to it.
10. Click **Invite** to send an invitation to the email you specified. The email address of the user you invited appears in the Pending user invitations area and remains there until the invitation is accepted or seven calendar days have passed.

> **TIP**
>
> Use the search box to search for a specific service or workspace. Click **Grant access to all** or **Revoke access to all** to enable or disable access to all services or workspaces at once.

Resending an account invitation

To resend a pending invitation before it has been accepted or expired:

1. Log in to the Fastly control panel.
2. Go to **Account** > **User management**.
3. In the **Pending user invitations** area, find the email address associated with the original invitation.
4. From the **Options** menu, select **Resend email**.

Deleting an account invitation

To delete an account invitation before it has been accepted or expired:

1. Log in to the Fastly control panel.
2. Go to **Account** > **User management**.
3. In the **Pending user invitations** area, find the email address associated with the original invitation.
4. From the **Options** menu, select **Delete invitation**.

Deleting account users

> IMPORTANT
>
> Deleting the owner of the account or the primary contact? Be sure to transfer ownership first or designate a new primary contact before deleting them.

To delete a user from an account, follow the steps below:

1. Log in to the Fastly control panel.
2. Go to **Account** > **User management**.
3. In the **Active users** area, find the name or email of the user to delete.
4. Click the **Options** menu to the right of the user to be deleted, then select **Delete user** from the menu that appears. A confirmation window appears.

5. If the user has active API tokens associated with their account, click **Review this user's API tokens** to manually review and revoke them. Alternatively, select the checkbox to automatically revoke all of the user's API tokens and delete the user.

   > WARNING
   >
   > Deleting an API token will break any integration actively using that credential. Review our guide on using API tokens and verify you've changed the API token for your integrations before proceeding.

6. Click **Confirm and delete**.

---

* * *

Changing and resetting passwords

/en/guides/changing-and-resetting-passwords

All users can change or reset their own password. If you've been assigned the role of superuser, you can reset the password of any user currently associated with your company.

> TIP
>
> Need to update a name or email address associated with your account or someone else's? Check out our guide on changing names and emails.

Before you begin

Keep in mind the following:

- Fastly follows guidelines from the National Institute of Standards and Technology when checking password strength and security (NIST SP 800-63B provides more details).
- Most password managers associate entries in their databases with specific website domains. If you've stored your username and password combination there for either your Fastly or Signal Sciences accounts, your password manager won't have any way of knowing when you've added or updated information. You must always manually enter and update the information in your password manager yourself.

- If your company sets up single sign-on, all passwords for existing users will be deleted and active sessions will be expired. You'll be notified of password reset requirements associated with SSO enablement, if any, at that time.

Changing your password

Log in to your account and follow these instructions to change the password currently associated with your account.

Changing passwords on Fastly accounts or linked Signal Sciences accounts

If you have a Fastly account or a Signal Sciences account that is linked to a Fastly account, use the following steps to change your password in the appropriate control panel.

1. Log in to the Fastly control panel.
2. Click **Profile & security** in the user quick links menu.
3. Click **Change password**.
4. Fill out the page as follows:
    - In the **Current password** field, enter your existing password.
    - In the **New password** field, enter the new password.
    - In the **Confirm password** field, enter the new password a second time.
5. Click **Change Password** to save the changes.

1. Log in to the Next-Gen WAF control panel.
2. Click **Profile & security** in the My Profile menu.
3. Click **Change password**.
4. Fill out the page as follows:
    - In the **Current password** field, enter your existing password.
    - In the **New password** field, enter the new password.
    - In the **Confirm password** field, enter the new password a second time.
5. Click **Change Password** to save the changes.

Changing passwords on unlinked Signal Sciences accounts

If you have a Signal Sciences account that is not linked to a Fastly account, follow these steps to change your password:

1. Log in to the Next-Gen WAF control panel.
2. From the **My Profile** menu, select **Account Settings**.
3. Fill out the fields in the **Password** area as follows:
    - In the **Current password** field, enter your existing password.
    - In the **New password** field, enter the new password.
    - In the **Confirm password** field, enter the new password a second time.
4. Click **Change Password**.

Resetting your password

To reset your password when you forget it, follow these steps:

1. Navigate to the appropriate login page for your account:
    - If you only have a Fastly account, use https://manage.fastly.com/.
    - If you only have a Signal Sciences account, use https://dashboard.signalsciences.net/.
    - If you have both a Fastly account and a Signal Sciences account, use https://manage.fastly.com/.
2. In the **Email** field, enter the email address associated with your account and click **Continue**.
3. Click **Forgot password** and then click **Continue**. Password reset instructions will be emailed to your email address, including a password reset link.
4. Check your email for the verification email. The subject line of the email will read `Fastly password reset requested`.
5. Click the password reset link in the email. The password reset screen appears.
6. In the **New password** field, enter a new password.
7. In the **Confirm new password** field, enter the new password a second time to confirm it.
8. Click **Continue** and then click **Log in** to access your account using the new password.

Resetting someone else's password

If you're a superuser, follow these instructions to reset the password currently associated with another user's account:

1. Log in to the Fastly control panel.
2. Go to **Account** > **User management**.
3. In the **Active users** area, find the appropriate user and then click the **Options** menu next to their name.
4. From the Options menu, select **Send password reset**.
5. Verify the email address of the user, and then click **Confirm and send** to save the changes. Password reset instructions are emailed to the user.

* * *



Changing names and email addresses



/en/guides/changing-names-and-email-addresses

The Fastly control panel allows you to change the name associated with your Fastly account.



TIP

Need to update a password associated with your account or someone else's? Check out our guide on changing and resetting passwords.

Changing names

Anyone can change the name associated with their Fastly account. If you've been assigned the role of superuser, you can change the name of anyone currently associated with your company's Fastly account.



IMPORTANT

> Looking to change your name on your Signal Sciences account? If you only have a Signal Sciences account or if you have both a Fastly account and a Signal Sciences account that share the same email address, you must contact support to change your name.

Changing your name

Follow these instructions to change the name currently associated with your Fastly account:

1. Log in to the Fastly control panel.
2. Go to **Account** > **Profile & security**.
3. Click **Your profile**.
4. In the **Name** field, enter your name.
5. Click **Update Profile** to save the changes.

Changing someone else's name

Follow these instructions to change the name currently associated with someone's Fastly account:

1. Log in to the Fastly control panel.
2. Go to **Account** > **User management**.
3. In the **Users** area, find the appropriate user and then click the gear ⚙ next to their name.
4. From the menu that appears, select **Edit user**.
5. In the **Name** field, enter the updated name.
6. Click **Update** to save the changes.

Changing email addresses

To change the email address associated with your account, contact support.

---

* * *

Configuring user roles and permissions

/en/guides/configuring-user-roles-and-permissions

This guide explains how to configure user roles and permissions to manage access within your account.

Accounts are often managed by multiple users, each requiring different types of access based on their role within your organization. You can manage this access using control panel settings that allow you to assign users to roles and limit the scope of those roles based on each user's responsibilities. By defining roles appropriately, you can ensure users have the right level of access without granting unnecessary privileges. This allows you to prevent unauthorized account changes, support compliance requirements, and protect sensitive information by restricting access to it.

User roles and what they can do

When invited to join an account, you'll be assigned a specific *role*. Think of roles as a way for your company to group the main business functions its users perform when invited to an account. Your role may afford you the ability to view and control a variety of things.

- **User** roles typically have limited ability to view (but not manage) basic information about service configurations and controls. Some of these abilities may be restricted on a per-service basis, however. You'll also have the ability to view real-time and historical stats. You won't have access to billing and payment information.
- **Billing** roles typically have full access to view (but not manage) basic information about service configurations, invoices, and account billing history. You'll also have the ability to manage payment information and account types and to view real-time and historical stats.
- **Engineer** roles typically have the ability to create services and manage their configurations. Some of these abilities may be restricted on a per service basis, however. When assigned this role, you'll also be able to invite new engineer and user roles via the API. You won't have access to billing and payment information.
- **Superuser** roles have full account access, with the ability to manage all aspects of service configurations and account settings, including full access to billing and

payment information and TLS management. When assigned this role, you cannot close or cancel an account unless you are also the account owner.

Abilities granted to user roles are selective, not additive. Regardless of your role, you'll have the ability to manage you personal profile information, personal multi-factor authentication, and personal API tokens, view basic stats information, and submit help requests to Fastly Customer Support.

Access permissions and what they allow

The ability to do things on an account is governed by *access permissions* associated with each role. As a superuser, you can set those permissions separately for each CDN or Compute service, as well as for each workspace if you've purchased Fastly's Next-Gen WAF.

CDN and Compute service access permissions

By default, all roles grant some amount of access to every CDN and Compute service on an account, including those services created in the future. The User and Engineer roles, however, can be limited on a per-service basis at the following permission levels:

- **Read-only.** Allows a user or engineer to view a specific service's configuration but does not allow them to issue purge requests for that service nor make changes to its configuration.
- **Purge select.** Allows an engineer to view a specific service's configuration and also allows them to issue purge requests for that service via URL or surrogate key. They cannot use the purge all function on the service, nor can they make configuration changes to that service.
- **Purge all.** Allows an engineer to view a specific service's configuration and issue purge requests for the entire service via the purge all function. They cannot, however, make configuration changes to that service.
- **Full access.** Allows an engineer full access to a specific service, including permission to issue purge requests via any method on that service. They can make configuration changes to that service and can activate new versions of it at will.

Service permission levels are additive, not selective. Each level includes the previous level's permissions. When new services are added to an account by a superuser, users and engineers with anything but full access to services will not have access to those services until a superuser specifically grants a permission level manually.

Workspace access permissions

Roles also grant some amount of access to specific workspaces if you've purchased Fastly's Next-Gen WAF. Each role grants progressively greater control over those workspaces as follows:

- The **User** and **Billing** roles have access to specific workspaces and can view things related to them (e.g., users, rules, signals, audit logs) but not create or edit them. Think of these roles as "observers" on your account.
- The **Engineer** role have access to specific workspaces and can view and edit their configuration settings, but they can't create them or delete them, nor can they manage your account-wide settings.
- The **Superuser** role has access to all workspaces and account features. They create and delete workspaces and can edit settings for all of them. They can also invite and remove users to and from an account and manage their roles.

Changing user roles and access permissions for existing users

If you've been assigned the superuser role, you can the role, service and workspace access, or permission levels for any existing user on your account. Plan your changes carefully.

> WARNING
>
> Changes to roles and access permissions for existing users apply instantly and get saved automatically.

To change roles and access permissions for existing users, do the following:

1. Log in to the Fastly control panel.
2. Go to **Account** > **User management**.
3. In the **Active users** area, click the **Options** menu next to a user name and then select **Access controls**.
4. *(Optional)* From the **Role** choices, select a new role for the user.
5. *(Optional)* Select or deselect the **TLS management** box to grant or remove TLS configuration access to a user. Users with the role of superuser have this permission by default. You can grant this to other roles if you choose.

6. *(Optional)* Select or deselect the **Bypass SSO** box to allow this superuser to log in with a username and password even when SSO sign-on is enabled.

7. *(Optional)* Limit access to selected services for this user by doing the following:
   - From the **CDN & Compute service access** controls, select **Limit access to selected services**.
   - From the **Manage service access** controls, select the specific permission levels for each service this user should be able to access. Leave the permissions blank to keep specific services hidden.

8. *(Optional)* Limit access to selected workspaces for this user by doing the following:
   - From the **Next-Gen WAF workspace access** controls, select **Limit access to selected workspaces**.
   - From the **Manage service access** controls, click the switch next to the appropriate workspace to allow access to it.

9. Click **Save**. The user's role and permission levels will be changed accordingly.

> TIP
>
> Use the search box to search for a specific service or workspace. Click **Grant access to all** or **Revoke access to all** to enable or disable access to all services or workspaces at once.

Account ownership

We assign the special role of *owner* to the first user who signs up for an account for your organization and we automatically assign that owner the superuser role. Any superuser on your account can change the permissions on an owner role or transfer ownership via the Company settings, which are accessible from the Account controls of the control panel.

Account owners typically serve as the primary point of contact for billing purposes. Invoices are sent to them, but if a specific billing contact has been defined for an account, invoices go to that contact instead. In addition, accounts can only be canceled by owners.

---

* * *

Managing multiple accounts

/en/guides/managing-multiple-accounts

Fastly's multi-account user access feature allows you to manage your access to multiple Fastly accounts. If you've been invited as a user to more than one Fastly account, you can quickly switch between those accounts without logging out of the Fastly control panel. The multi-account user access feature works with single sign-on (SSO) and two-factor authentication.

TIP

Looking to switch between Fastly and Next-Gen WAF control panels? Use our application switcher.

Accepting an invitation to join an account

If you've been invited to a customer account and you don't have a Fastly user account, follow the instructions sent via email to create a user account and accept the invitation.

If you're an existing user who already has a Fastly user account, you'll see any invitations to join an account each time you log in. To accept them, click **Accept invitation** and you'll be added to that account automatically.

Switching accounts

Follow the steps below to switch between the customer accounts you can access:

1. Log in to the Fastly control panel.
2. From the user quick links menu, click **Switch account**.
3. From the list of accounts that appear, find the appropriate account and click **Log in**.
4. If prompted, enter your password.
5. If you have two-factor authentication enabled for your account, enter the time-based authentication code from your mobile device, then click **Log in**.

Setting a default account

You can set a default customer account that appears automatically when you log in to the Fastly control panel.

> **IMPORTANT**
>
> Customer accounts configured to use single sign-on (SSO) can't be set as the default account.

Follow the steps below to set a default account:

1. Log in to the Fastly control panel.
2. Go to **Account** > **Your accounts**.
3. In the **Your accounts** area, find the appropriate account and click **Make default**.

The next time you log in, the account you set as the default will automatically be selected.

---

* * *

Setting up single sign-on (SSO)

/en/guides/setting-up-single-sign-on-sso

This guide explains how to set up and enable single sign-on (SSO) when using an identity provider (IdP) for authentication.

SSO allows users to access multiple applications with a single set of credentials. An IdP manages authentication requests, enforces security policies, and reduces the need for separate passwords across different systems. By centralizing identity management, you can simplify access control and ensure consistent authentication policies across your organization.

You can also enforce security measures such as multi-factor authentication (MFA) and role-based access control (RBAC) to protect sensitive information. Once configured, SSO provides a seamless login experience while maintaining strong security across all connected applications.

> **TIP**

You can set up SSO for Signal Sciences accounts too. Check out our enablement guide for details.

Prerequisites

To enable SSO or require that it be applied to all of your organization's users when they log in to the Fastly control panel, you must:

- be assigned the role of superuser for your Fastly account
- have access to your IdP's administration console

In addition, your IdP must support:

- Security Assertion Markup Language 2.0 (SAML 2.0)
- Service Provider (SP) or IdP-initiated SSO for login purposes

You should also review this feature's limitations before enabling SSO.

Enabling SSO

Start by selecting an IdP and configuring that provider's settings keeping in mind the prerequisites.

TIP

Save time by leaving both your Fastly control panel and your Okta windows open while you're enabling SSO. You'll be copying information back and forth between them while you set things up.

Start by selecting Okta as the IdP in the Fastly control panel:

1. Log in to the Fastly control panel.
2. Go to **Account** > **Single sign-on**.
3. From the **Identity provider** menu, select **Okta**.

Next, set up the Okta SSO settings:

1. Log in to the Okta app.

2. Go to **Applications** > **Applications** and select the Fastly app you're the administrator for.
3. Click **Sign On** from the application tabs.
4. From the **SAML 2.0** area, copy the **Metadata URL**.

Then, save the metadata file:

1. In the address field of a new browser window, paste the **Metadata URL** you just copied to display the IdP metadata.
2. Right click in your browser window and select **Save As** from the menu that appears to save this metadata file to a location locally. You'll need this file to complete the setup in the Fastly control panel.

Next, go back to the Fastly control panel window and upload the metadata file to Fastly:


1. Click **Upload XML IdP metadata file** to upload the metadata file you just saved.
2. From the **SSO token** field, copy the SSO token.

Go back to the Okta window to edit your remaining Okta settings:

1. On the **Sign On** tab in the **Settings** area, click **Edit**.
2. In the **SAML 2.0** area, deselect **Disable Force Authentication**.
3. In the **SSO token** field of the **Advanced Sign-on Settings** area, paste the authentication token you just copied from the Fastly control panel.
4. From the **Application username format** menu in the **Credentials Area**, select **Email**.
5. Click **Save**.

Then return to the Fastly control panel and click **Save and enable SSO** to complete the setup.


1. Log in to the Fastly control panel.
2. Go to **Account** > **Single sign-on**.
3. Click **Add SAML Configuration**.
4. From the **Identity provider** menu, select your organization's IdP.



5. Using the configuration details that appear in the Fastly control panel, create a new SAML 2.0 application in your IdP's administration console and assign the application to new and existing users. Refer to your IdP's documentation for more information.

6. After creating the SAML 2.0 application in your IdP, download the XML metadata file with your application's SAML configuration. The XML file includes a public certificate used to verify the signature of SAML assertions.

7. Upload your IdP metadata file. You can do this by dragging and dropping the file into the area provided or by browsing for the file and uploading it.




8. Click **Save and Enable SSO**.

9. In the confirmation window, click **Save and Enable SSO**. Your metadata will be saved and the SSO controls will indicate that SSO is enabled.

Requiring SSO for your organization

To require SSO for everyone in your organization except superusers, follow these instructions.

1. Log in to the Fastly control panel.
2. Go to **Account** > **Single sign-on**.



3. Select the **Immediately enforce SSO** checkbox that appears below the SAML configuration switch.
4. In the confirmation window, click **Start enforcing SSO**. Currently open non-SSO sessions for users assigned the role of user, billing, or engineer will be logged out and they will need to re-authenticate using SSO via your IdP.

> NOTE
>
> Users who have been assigned the role of superuser can always log in with their email address and password, whether or not **Single sign-on** is enabled.

Performing account tasks differently with SSO enabled

If your organization has enabled SSO, you may notice different feature availability in the Fastly control panel. This section describes the differences.

- **Changing your email address and password.** Because SSO requires user email addresses in Fastly to match those in the IdP, you won't be able to change your email address while logged in using SSO. You also won't be able to modify your password or enable two-factor authentication.
- **Creating an API token.** To create an API token while logged in to the Fastly control panel using SSO, you'll need to reauthenticate with your IdP. Follow the instructions for

creating an API token and click the **Re-Authenticate** button on the Create a Token page.

> NOTE
>
> You can't create API tokens when using G Suite for authentication.

- **Managing sessions.** Sessions created by logging in to the Fastly control panel using SSO or with a username and password expire after 3 hours.

Changing SSO providers

To change SSO providers, follow these instructions.

> WARNING
>
> Disabling the SSO feature for your organization will expire all active SSO sessions, including your own. Users will automatically be logged out of the Fastly control panel.


1. Log in to the Fastly control panel.
2. Go to **Account** > **Single sign-on**.
3. From the **Options** menu, select **Upload new SAML configuration**.
4. In the confirmation window, click **Continue** to delete your existing SAML confirmation.
5. Follow the instructions in the enabling SSO section.

Disabling SSO

To disable SSO for your organization, either permanently or temporarily (e.g., your SSO provider is experiencing an outage), follow these instructions. Disabling SSO won't delete your SSO settings and you can re-enable SSO at any point using the same IdP configuration metadata you uploaded when you first enabled SSO.

> WARNING
>
> Disabling the SSO feature for your organization, even temporarily, will expire all active SSO sessions, including your own, and will automatically log users out of the Fastly control panel.

1. Log in to the Fastly control panel.
2. Go to **Account** > **Single sign-on**.



3. Click the **Single sign-on** switch to disable SSO for your organization.
4. In the confirmation window, click **Disable SSO**. SSO will be disabled and will not be required for your organization's users. All active SSO sessions will expire, including your own, and users will automatically be logged out of the Fastly control panel.

Bypassing single sign-on for selected users

If your organization has single sign-on enabled for everyone, any superuser can enable another superuser to bypass SSO for their account. This allows them to log in to the Fastly control panel via their username and password, without needing to authenticate through your SSO provider. To do this, be sure to select **Bypass SSO** when adding them to your account or editing their roles and access permissions.

Limitations and considerations

Fastly's SSO feature has the following limitations:

- Users cannot create API tokens from the Fastly control panel when using G Suite SSO for a session's authentication.
- Fastly does not support automatic provisioning and de-provisioning of users using SCIM for Fastly accounts. To enable SCIM for your Signal Sciences account, check out our guide to automating user management.

Also, keep in mind that the SHA-1 cryptographic algorithm has been retired by the National Institute of Standards and Technology (NIST) and they recommend upgrading to more advanced and secure replacements such as those from the SHA-2 family of hash functions,

like SHA-256. Consider using or upgrading to these more advanced algorithms for SAML certificate signing for SSO setup in advance of the NIST recommended phase out deadline.

---

* * *

Unsubscribing from Fastly marketing email

/en/guides/unsubscribing-from-fastly-marketing-email

If you receive what appears to be a legitimate marketing communication or promotion from Fastly, you may opt-out of these emails at any time by clicking the unsubscribe link provided in the email or by forwarding it to abuse@fastly.com so that we can address it. You will still receive emails from support@fastly.com.

Dealing with other unsolicited emails

You may receive unsolicited email messages that are neither sent by Fastly nor associated with Fastly, even if you've never created a Fastly account. These unwanted emails use email spoofing to give the false impression that they were sent by Fastly. They may contain links to Fastly websites to give them the appearance of legitimacy.

If an email was not sent by Fastly's mail servers, there is nothing we can do to stop additional spam emails from being sent to your address. To block these messages entirely, you will need to use the spam protections made available by your email provider.

---

* * *

Compute guides

Category: Developer guides

These articles describe how to develop with Compute.

Frameworks

/en/guides/frameworks

---

* * *

Getting started with Compute

/en/guides/getting-started-with-compute

---

* * *

Migrate from VCL

/en/guides/migrate-from-vcl

---

* * *

Testing and debugging

/en/guides/testing-and-debugging

---

* * *

Using Go

/en/guides/using-go

---

* * *

Using JavaScript

/en/guides/using-javascript

---

* * *

Using other languages

/en/guides/using-other-languages

---

* * *

Using Rust

/en/guides/using-rust

---

* * *

Category: Edge Data Storage

These articles describe how to work with the edge data storage features available with Compute.

	Working with config stores
🔗	/en/guides/working-with-config-stores

Config stores are a type of versionless container that allow you to store often repeated data as key-value pairs that can be read from the edge and shared by multiple Compute services in your account. Once linked to a service, any updates you make to the store are automatically reflected on the service without needing to increment the service's version. Changes immediately impact all service versions, including the active one.

You can also create and work with config stores via the API.

Prerequisites

Config Store is only available for Fastly's Compute services, not for CDN (VCL-based) services.

Limitations and considerations

Before working with config stores, keep the following things in mind:

- Config stores can only be used by Compute services, not CDN (VCL-based) services.
- Trials for Compute include one config store with a maximum of 100 entries.
- Paid accounts include a minimum of five config stores (each having a maximum of 500 entries).

When naming config stores, be aware of the following limitations:

- Config store names must begin with an ASCII alphabetical character and can only include ASCII alphanumeric, underscore, and whitespace characters.
- Store names are limited to 255 characters.

- Store names are case-sensitive.

When working with config store keys and values, be aware of the following limitations:

- Config store keys are limited to 255 characters and their values are limited to 8,000 characters.
- Keys and their values are case-sensitive.

> **WARNING**
>
> Personal information, secrets, or sensitive data should not be included in config stores or incorporated into edge logic. In addition, we do not maintain version histories of your config stores. Our Compliance and Law FAQ describes in detail how Fastly handles personal data privacy.

Creating a config store

Creating a config store requires you to create at least one key-value pair before you associate it with a service. To create a new config store and its key-value pairs, follow these steps:

1. Log in to the Fastly control panel.
2. Go to **Resources** > **Config stores**.
3. Click **Create a config store**.
4. In the **Name of config store** field, enter a name for the config store and then click **Add**.
5. Click the **Key-value pairs** link.
6. Click **Add item**.
7. Enter the key and the value in the appropriate column and then click **Add**.
8. Continue adding additional key-value pairs as necessary.

Linking config stores to a service

Once you've added at least one key-value pair to a config store, you can link it to one or more services from the Resources controls or from the service configuration for the service. Any future updates made to the store are automatically reflected on the linked services.

Using the Resources controls to link config stores to a service

To link a config store to a service from the Resources controls:

1. Log in to the Fastly control panel.
2. Go to **Resources** > **Config stores**.
3. Click **Link to services** to the right of the store you want to link.
4. Select the checkbox next to any services you want to link your config store to.
5. Click **Next**.
6. Decide which version of the service to link to. By default, the system will assume you want to clone the most recently active version of your service. You can choose an existing draft version of the service instead by selecting it specifically from the **Version** menu.
7. Select one of the following options for linking the store to your service:
    - **Link only:** links the store to the selected service versions but leaves any cloned or draft versions un-activated so you can activate them at a later time.
    - **Link and activate:** links the store to the selected service versions and activates those versions at the same time.

    A success message appears once the config store is linked to the service.
8. Finally, do one of the following:
    - Click **Activate versions** to activate any cloned or draft versions of services linked to the config store.
    - Click **Finish** to leave the cloned or draft service versions un-activated so you can make additional configuration changes to them and activate them at a later time.

    You can immediately start referencing the config store in your edge logic.

Using the service configuration to link config stores to a service

To link a config store to a service from the service configuration:

1. Log in to the Fastly control panel.

2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Service configuration**.
4. From the **Resources** options in the on-page navigation, click **Config stores**.
5. From the **Link Config Store to service** menu, select the config store you want to link to the service. A success message appears once the config store is linked to the service.

Once linked, you can immediately start referencing the config store in your edge logic and activate the service when you're ready.

Unlinking config stores

You can unlink a config store from a service from the service configuration.

To unlink a config store:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Service configuration**.
4. From the **Resources** options in the on-page navigation, click **Config stores**.
5. Click **Unlink from service** next to the config store you want to unlink from your service.
6. Click **Confirm and unlink**. A new, draft version of the service is created.
7. Activate the service to finalize unlinking the config store.

Editing a config store

You can edit the name of a config store as well as the key-value pairs within the store from **Resources** > **Config stores**. You can also access this page by clicking **Edit in Resources** when accessing a config store from the service configuration.

To rename a config store:

1. Click the pencil to the right of the store you want to rename.
2. Enter a new name for the config store.

3. Click **Save** and then **Confirm and rename** to continue.

To add new key-value pairs to a config store:

1. Expand the **Key-value pairs** section.
2. Under **Key-value** pairs, click **Add item**.
3. Enter the key and the value in the appropriate column and then click **Add**.
4. Repeat for any additional key-value pairs.

To edit the key-value pairs within a config store:

1. Expand the **Key-value pairs** section.
2. Hover your cursor over the entry you want to edit, then click **Edit**.
3. Edit the key or value as necessary.
4. Click **Save**.

The changes you make will be immediately applied to your configuration including any deployed service versions associated with the config store.

Deleting a config store

You can delete a config store at any time. A config store must be unlinked from any services or an error will appear if you try to delete it.

Deleting a config store also deletes all key-value pairs within the store. If you have custom logic referencing these keys, ensure you update them before deleting the store.

To delete a config store:

1. Log in to the Fastly control panel.
2. Go to **Resources** > **Config stores**.
3. Click the trash to the right of the store you want to delete.
4. Click **Confirm and delete**.

---

* * *

	Working with KV stores
🔗	/en/guides/working-with-kv-stores

A KV store is a type of versionless container that allows you to store data in the form of key-value pairs for use in high performance reads and writes at the edge. A single KV store can be associated with multiple Compute services in your account.

Once linked to a service, any updates you make to the store are automatically reflected on the service without needing to increment the service's version. Changes immediately impact all service versions, including the active one. Also, because KV stores are stored at the edge, they allow you to offload that data from your origin and keep it closer to your end users.

You can also create and work with KV stores via the API.

> **TIP**
>
> Bulk operations can only be completed via the API.

Before you begin

KV Store is only available for Fastly's Compute services, not for CDN (VCL-based) services.

Make sure you review the limitations for using KV stores in the Compute resource limits.

> **WARNING**
>
> Personal information, secrets, or sensitive data should not be included in KV stores or incorporated into edge logic. In addition, we do not maintain version histories of your KV stores. Our Compliance and Law FAQ describes in detail how Fastly handles personal data privacy.

Creating a KV store

Creating a KV store requires you to create at least one key-value pair before you associate it with a service. To create a new KV store and its key-value pairs, follow these steps:

1. Log in to the Fastly control panel.

2. Go to **Resources** > **KV stores**.
3. Click **Create a KV store**.
4. In the **Name of KV store** field, enter a name for the KV store and then click **Add**.
5. Click **Key-value pairs**.
6. In the **Name of key** field, enter a name for the first set of key-value pairs associated with your KV store.
7. Upload the values for your key, clicking **Browse for file** to navigate to the file on your system using the file picker. Alternatively, drag and drop your key file directly into the drag and drop area below these controls.
8. Click **Add** to the right of the key controls.
9. Click **Add item** to continue adding additional key-value pairs as necessary.

> TIP
>
> By default, the web interface displays only the first 1,000 keys in the store. To view more keys, click the **Load more keys** button.

Linking KV stores to a service

Once you've added at least one key-value pair to a KV store, you can link it to a service from the Resources controls or from the service configuration for the service. Any future updates made to the store are automatically reflected on the linked services.

Using the Resources controls to link KV stores to a service

To link a KV store to a service from the Resources controls:

1. Log in to the Fastly control panel.
2. Go to **Resources** > **KV stores**.
3. Click **Link to services** to the right of the store you want to link.
4. Select the checkbox next to any services you want to link your KV store to and then click **Next**.
5. Decide which version of the service to link to. By default, the system will assume you want to clone the most recently active version of your service. You can choose an

existing draft version of the service instead by selecting it specifically from the **Version** menu.

6. Select one of the following options for linking the store to your service:

    - **Link only:** links the store to the selected service versions but leaves any cloned or draft versions un-activated so you can activate them at a later time.
    - **Link and activate:** links the store to the selected service versions and activates those versions at the same time.

    A success message appears once the KV store is linked to the service.

7. Finally, do one of the following:

    - Click **Activate versions** to activate any cloned or draft versions of services linked to the KV store.
    - Click **Finish** to leave the cloned or draft service versions un-activated so you can make additional configuration changes to them and activate them at a later time.

    You can immediately start referencing the KV store in your edge logic.

Using the service configuration to link KV stores to a service

To link a KV store to a service from the service configuration:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Service configuration**.
4. From the **Resources** options in the on-page navigation, click **KV stores**.
5. From the **Link KV Store to service** menu, select the KV store you want to link to the service. A success message appears indicating the store is linked to your service.

Once linked, you can immediately start referencing the KV store in your edge logic and activate the service when you're ready.

Unlinking KV stores

You can unlink a KV store from a service from the service configuration.

To unlink a KV store:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Service configuration**.
4. From the **Resources** options in the on-page navigation, click **KV stores**.
5. Click **Unlink from service** next to the KV store you want to unlink from your service.
6. Click **Confirm and unlink**. A new, draft version of the service is created.
7. Activate the service to finalize unlinking the KV store.

Editing a KV store

You can edit the name of a KV store as well as the key-value pairs within the store from **Resources** > **KV stores**. You can also access this page by clicking **Edit in Resources** when accessing a KV store from the service configuration.

To rename a KV store:

1. Click the pencil to the right of the store you want to rename.
2. Enter a new name for the KV store.
3. Click **Save** and then **Confirm and rename** to continue.

To add new key-value pairs to a KV store:

1. Expand the **Key-value pairs** section.
2. Under **Key-value** pairs, click **Add item**.
3. Enter a key name and upload a key file that has the values and then click **Add**.
4. Repeat for any additional key-value pairs.

To edit the key-value pairs within a KV store:

1. Expand the **Key-value pairs** section.
2. Hover your cursor over the entry you want to edit, then click **Edit** .

3. Drag and drop your key file that has the values into the drag and drop area to upload your list of keys. Alternatively, click **Browse for file** to navigate to the file on your system using the file picker.

4. Click **Save**.

The changes you make will be immediately applied to your configuration including any deployed service versions associated with the KV store.

Deleting a KV store

You can delete a KV store at any time.

Before deleting a KV store:

- Unlink the KV store from your services. If the KV store is linked to any service, an error will appear when you try to delete the store.
- Update any custom logic that references the key-value pairs in the KV store. Deleting a KV store also deletes all key-value pairs within the store.

To delete a KV store:

1. Log in to the Fastly control panel.
2. Go to **Resources** > **KV stores**.
3. Click trash to the right of the store you want to delete.
4. Click **Confirm and delete**.

---

* * *

	Working with secret stores
🔗	/en/guides/working-with-secret-stores

Secret stores are a type of versionless container that give you a secure location to place credentials so they are available to Compute services operating at the Fastly edge. Once linked to a service, any updates you make to the store are automatically reflected on the

service without needing to increment the service's version. Changes immediately impact all service versions, including the active one.

You can also create and work with secret stores via the API.

Prerequisites

Secret Store is only available for Fastly's Compute services, not for CDN (VCL-based) services.

Limitations and considerations

Before working with secret stores, keep the following things in mind:

- Trials for Compute include one secret store.
- Paid accounts include a minimum of 10 secrets regardless of the number of stores with additional secrets available for purchase.
- Secrets are limited to 5 secret reads per Compute request. To increase this limit contact Fastly Support.
- Secret stores support a maximum size of 64KB per secret.

When naming secret stores, be aware of the following limitations:

- Secret store names can only contain letters, numbers, dashes, underscores, and periods.
- Store names are limited to 255 characters.

Creating a secret store

Creating a secret store requires you to create at least one key-value pair containing secrets and then associating the store with a service. To create a new secret store and add secrets, follow these steps:

1. Log in to the Fastly control panel.
2. Go to **Resources** > **Secret stores**.
3. Click **Create a secret store**.

4. Enter a name for the secret store and then click **Add**. The secret store you just created appears.
5. Click **Key-value pairs**.
6. Click **Add item**. A row appears where you can add secrets.
7. In the **Name** field, enter a name for the secret.
8. In the **Secret** field, enter the secret value. Alternatively, click **Browse for file** to upload a secrets file on your system using the file picker.
9. Click **Add**.
10. Click **Add item** to continue adding additional secrets as necessary.

Linking secret stores to a service

Once you've added at least one secret to a secret store, you can link it to a service from the Resources controls or from the service configuration for the service. Any future updates made to the store are automatically reflected on the linked services.

Using the Resources controls to link secret stores to a service

To link a secret store to a service from the **Resources** controls:

1. Log in to the Fastly control panel.
2. Go to **Resources** > **Secret stores**.
3. Click **Link to services** to the right of the store you want to link.
4. Select the checkbox next to any services you want to link your secret store to and then click **Next**.
5. Decide which version of the service to link to. By default, the system will assume you want to clone the most recently active version of your service. You can choose an existing draft version of the service instead by selecting it specifically from the **Version** menu.
6. Select one of the following options for linking the store to your service:
    - **Link only:** links the store to the selected service versions but leaves any cloned or draft versions un-activated so you can activate them at a later time.

- **Link and activate:** links the store to the selected service versions and activates those versions at the same time.

A success message appears once the secret store is linked to the service.

7. Finally, do one of the following:

   - Click **Activate versions** to activate any cloned or draft versions of services linked to the secret store.
   - Click **Finish** to leave the cloned or draft service versions un-activated so you can make additional configuration changes to them and activate them at a later time.

Using the service configuration to link secret stores to a service

To link a secret store to a service from the service configuration:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Service configuration**.
4. From the **Linked resources** options in the on-page navigation, click **Secret stores**.
5. From the **Link Secret Store to service** menu, select the secret store you want to link to the service. A success message appears indicating the store is linked to your service.

Unlinking secret stores

You can unlink a secret store from a service from the service configuration.

To unlink a secret store:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Service configuration**.
4. From the **Resources** options in the on-page navigation, click **Secret stores**.
5. Click **Unlink from service** next to the secret store you want to unlink from your service.

6. Click **Confirm and unlink**. A new, draft version of the service is created.
7. Activate the service to finalize unlinking the secret store.

Editing a secret store

You can edit the secrets within the story or add new secrets to the store from **Resources** > **Secret stores**. You can also access this page by clicking **Edit in Resources** when accessing a secret store from the service configuration.

To edit secrets within a store:

1. Expand the **Key-value pairs** section.
2. Hover your cursor over the entry you want to edit, then click the **Edit** link that appears.
3. Update the secret value. Alternatively, click **Browse for file** to navigate to a file on your system using the file picker.
4. Click **Save**.

To add new secrets to a secret store:

1. Expand the **Key-value pairs** section.
2. Under **Key-value** pairs, click **Add item**.
3. Enter the name and secret in the appropriate columns and then click **Add**.
4. Repeat for any additional secrets.

The changes you make will be immediately applied to your configuration including any deployed service versions associated with the secret store.

Deleting a secret store

You can delete a secret store at any time. Before deleting a secret store:

- Unlink the secret store from your services. If the secret store is linked to any service, an error will appear when you try to delete the store.
- Update any custom logic that references the key-value pairs in the secret store. Deleting a secret store also deletes all key-value pairs within the store.

To delete a secret store:

1. Log in to the Fastly control panel.
2. Go to **Resources** > **Secret stores**.
3. Click the trash to the right of the store you want to delete.
4. Click **Confirm and delete**.

---

* * *

Category: AI Accelerator

These articles provide basic information about the AI Accelerator product.

	About the AI Accelerator page
🔗	/en/guides/about-the-ai-accelerator-page

AI Accelerator is a caching solution for artificial intelligence services from providers like OpenAI. By caching large language model (LLM) API responses and leveraging the cache for semantically similar queries, AI Accelerator can reduce latency and lower your LLM API usage costs.

Before you begin

Be sure you know how to access the web interface controls.

AI Accelerator can be enabled in the Fastly control panel by anyone assigned the role of superuser. Once enabled, all account users will be able to view the metrics.

Supported LLMs

AI Accelerator currently supports OpenAI, Azure OpenAI, Gemini, and LLMs with OpenAI-compatible APIs.

Enabling AI Accelerator

To enable AI Accelerator, follow these steps:

1. Log in to the Fastly control panel.
2. Go to **Tools** > **AI Accelerator**.
3. Click **Enable AI Accelerator**.
4. On the Enable AI Accelerator page, click **Enable Now**.

Configuring your application to use AI Accelerator

After AI Accelerator is enabled, you'll need to create a read-only API token and update your application to use the AI Accelerator endpoint. Refer to the code examples below if you need help updating your application's code.

OpenAI and OpenAI-compatible code examples

```python
from openai import OpenAI
client = OpenAI(
# Set the API endpoint
base_url="https://ai.fastly.app/api.openai.com/v1",
   # Set default headers
   default_headers = {
    "Fastly-Key": f"<FASTLY-KEY>",
   }
)

```

```javascript
import OpenAI from "openai";

const openai = new OpenAI({
  apiKey: request.env.OPENAI_API_KEY,
  baseURL: "https://ai.fastly.app/api.openai.com/v1",
  defaultHeaders: {
    "Fastly-Key": `<FASTLY-KEY>`,
  },
});

```

For LLMs with OpenAI-compatible APIs, use `https://ai.fastly.app/compat/openai/<llm-endpoint>` as the base URL.

Azure OpenAI code examples

```
from openai.lib.azure import AzureOpenAI
client = AzureOpenAI(
    api_key=azure_key,
    api_version="2024-06-01",
    azure_deployment="ai-member-4o-chat",
azure_en dpoint=f"https://ai.fastly.app/<AZURE RESOURCE>.openai.a
default_headers = {
    "Fastly-Key": f"<FASTLY-KEY>",
   }
)

```

Gemini code examples

```
project_region = "<GCP-REGION>"
project_id = "<GCP-PROJECT-ID>"
vertexai.init(
location=project_region,
      project=project_id,
  api_endpoint=f"ai.fastly.app/{project_region}-aiplatform.google
      api_transport='rest',
      request_metadata=[("fastly-key", f"<FASTLY-KEY>")]
)

model = GenerativeModel("gemini-pro")
print(model.generate_content("Why is the sky blue?"))

```

```
const {VertexAI} = require('@google-cloud/vertexai');

async function generate_from_text_input(projectId = '<GCP-PROJECT
  const vertexAI = new VertexAI({project: projectId, location: '<

  const generativeModel = vertexAI.getGenerativeModel({
    model: 'gemini-1.5-flash-001',
  });

  const prompt =
    "What's a good name for a flower shop that specializes in sel

  const resp = await generativeModel.generateContent(prompt);
  const contentResponse = await resp.response;
  console.log(JSON.stringify(contentResponse));
}

```

Setting and checking headers

You can use the following request and response headers to control and monitor how AI Accelerator caches LLM responses.

Header name	Type	Description
`x-semantic-threshold`	Request header	Controls the similarity threshold for responses from the semantic cache. The default is `0.75`. A lower threshold may increase the likelihood of a cached response at the risk of returning a lower quality response.
`x-semantic-cache-key`	Request header	User provided value that is used to segment the response in the cache. Only requests with a matching `x-semantic-cache-key` above the similarity threshold will be returned as a response. Not required to be set. If not set, the default value of `_default_` will be used.

Header name	Type	Description
`x-settings-overrides`	Request header	Controls whether or not semantic cache is enabled. The default is `{"semantic_cache_enabled": true}`.
`Cache-Control`	Request header	We currently only respect the `max-age` cache control directive. If a `Cache-Control` header is set on a request with a `max-age`, we will set that as the TTL on the cache entry up to a max TTL of 30 days (in seconds).
`x-semantic-cache`	Response header	Previously `x-cache`. Possible values are `HIT` or `MISS`.

About the AI Accelerator page

The AI Accelerator page provides metrics related to requests, tokens, and origin latency. The page displays the following charts:

- **Total requests:** The total number of requests sent to AI Accelerator.
- **Tokens served from cache:** The estimated number of tokens served from cache based on responses served from cache. A token is an LLM billing unit, the exact measure of which varies between vendor and version of LLM.
- **Estimated time saved:** The estimated amount of time saved in minutes based on responses served from cache.
- **Requests:** The total number of AI Accelerator requests aggregated across your account.
- **Tokens:** The estimated number of tokens served from cache or origin.
- **Origin Latency Percentiles:** The origin latency percentile approximations.

Purging the cache

IMPORTANT

This information is part of a beta release. For additional details, read our product and feature lifecycle descriptions.

You can purge all cache by using the AI Accelerator API endpoint. For example, you can purge all cache using curl in a terminal application.

```
$ curl -X POST -H "Fastly-Key: YOUR_FASTLY_TOKEN" https://api.fastly.com
```

NOTE

The API token must have `purge_all` scope.

Disabling AI Accelerator

To disable AI Accelerator, follow these steps:

1. Update your application code to remove the AI Accelerator integration.
2. Log in to the Fastly control panel.
3. Go to **Account** > **Billing** > **Overview**.
4. Click **Options** next to AI Accelerator, then click **Cancel**.
5. Click **Cancel AI Accelerator**.

---

* * *

Full Site Delivery guides

Category: Caching

These articles describe configuration settings and changes you can make to your cache settings when setting up Fastly services.

Caching configuration best practices

/en/guides/caching-best-practices

To ensure optimum origin performance during times of increased demand or during scheduled downtime for your servers, consider the following best practices for your service's caching configurations.

Integrate Fastly with your application platform

You can optimize caching with Fastly by customizing your application platform settings. For instructions, see our documentation on integrating third-party services and configuring web server software. We also provide a variety of plugins to help you directly integrate Fastly with your content management system.

Check your cache hit ratio

The number of requests delivered by a cache server, divided by the number of cacheable requests (hits + misses), is called the *cache hit ratio*. A high cache hit ratio means you've kept request traffic from hitting your origin unnecessarily. Requests come from cache instead. In general, you want your cache hit ratio as high as possible, usually in excess of 90%. You can check your hit ratio by viewing the Observability page for your service.

Set a fallback TTL

The amount of time information can be retained in cache memory is considered its *time to live* or TTL. TTL is set based on the cache related headers information returned from your origin server. You can specifically set a fallback TTL (sometimes called a *default TTL*).

WARNING

If you're using custom VCL, the fallback TTL will be specified in the VCL boilerplate and the fallback TTL configured via the Fastly control panel or the API will not be applied. Refer to our documentation on cache freshness and TTLs for more information.

TIP

If there's no other source of freshness in the response, setting the fallback TTL to 0 seconds in the Fastly control panel will set `return(pass)` in `vcl_fetch`.

We set a default fallback TTL that you can update at any time as follows:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Settings**.
5. In the **Fallback TTL** area, click the pencil next to the TTL setting.



6. In the **Fallback TTL (sec)** field, enter the new TTL in seconds.
7. Click **Save** to save your changes.
8. Click **Activate** to deploy your configuration changes.

NOTE

See our Google Cloud Storage instructions if you're changing the default TTL for a GCS bucket.

Understand how cache control headers work

You can use cache control headers to set policies that determine how long your data is cached.

Fastly looks for caching information in each of these headers as described in our documentation on cache freshness. In order of preference:

- `Surrogate-Control:`

- `Cache-Control: s-maxage`
- `Cache-Control: max-age`
- `Expires:`

`Surrogate` headers

`Surrogate` headers are a relatively new addition to the cache management vocabulary (described in this W3C tech note). These headers provide a specific cache policy for proxy caches in the processing path. `Surrogate-Control` accepts many of the same values as `Cache-Control`, plus some other more esoteric ones (read the tech note for all the options).

One use of this technique is to provide conservative cache interactions to the browser (for example, `Cache-Control: no-cache`). This causes the browser to re-validate with the source on every request for the content. This makes sure that the user is getting the freshest possible content. Simultaneously, a `Surrogate-Control` header can be sent with a longer `max-age` that lets a proxy cache in front of the source handle most of the browser traffic, only passing requests to the source when the proxy's cache expires.

With Fastly, one of the most useful `Surrogate` headers is `Surrogate-Key`. When Fastly processes a request and sees a `Surrogate-Key` header, it uses the space-separated value as a list of tags to associate with the request URL in the cache. Combined with Fastly's Purge API an entire collection of URLs can be expired from the cache in one API call (and typically happens in around 1ms). `Surrogate-Control` is the most specific.

`Cache-Control` directives

`Cache-Control` response directives, as defined by section 5.2.2 of RFC 9111, include:

- `Cache-Control: public` - Any cache can store a copy of the content. You don't need to add the `public` directive to a response as most are cacheable by default.
- `Cache-Control: private` - Don't store. This is intended for a single user.
- `Cache-Control: no-cache` - Re-validate before serving this content. This is ignored by Fastly.
- `Cache-Control: no-store` - Don't ever cache this content in a web browser. This is ignored by Fastly.
- `Cache-Control: max-age=[seconds]` - Caches can store this content for *n* seconds.

- `Cache-Control: s-maxage=[seconds]` - Same as max-age but applies specifically to proxy caches.

Only the `max-age`, `s-maxage`, and `private` `Cache-Control` directives will influence Fastly's caching. All other `Cache-Control` directives will not, but will be passed through to the browser. For more in-depth information about how Fastly responds to these cache control headers and how these headers interact with `Expires` and `Surrogate-Control`, check out our documentation on HTTP caching semantics.

`Expires` header

The `Expires` header tells the cache (typically a browser cache) how long to hang onto a piece of content. Thereafter, the browser will re-request the content from its source. The downside is that it's a static date and if you don't update it later, the date will pass and the browser will start requesting that resource from the source every time it sees it.

Fastly will respect the `Expires` header value only if the `Surrogate-Control` or `Cache-Control` headers are not found in the request.

Increase Cache-Control header times

During times of increased demand, you can instruct Fastly to keep objects in cache as long as possible by increasing the times you set on your Cache-Control headers. Consider changing the `max-age` on your `Cache-Control` or `Surrogate-Control` headers. Our documentation on HTTP caching semantics describes this in more detail.

Configure Fastly to temporarily serve stale content

If your origin becomes unavailable for an extended period of time (for example, being taken offline for maintenance purposes), temporarily serving stale content may help you. Serving stale content can also benefit you if your site's static content is updated or published quite frequently.

You can instruct Fastly to serve stale content by adding a `stale-while-revalidate` or `stale-if-error` statement on your `Cache-Control` or `Surrogate-Control` headers. Our guide to serving stale content describes this in more detail.

Decrease your first byte timeout time

After you have configured Fastly to temporarily serve stale, decreasing your first byte timeout time will cause stale content to be served to the requestor faster while fetching

fresh content from the origin. Decreasing your first byte timeout time as well as serving stale will reduce unnecessary 503 first byte timeout errors. Decrease the first byte timeout time to your origin as follows:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Origins**.
5. In the **Hosts** area, find your origin server and click the pencil to edit the host.
6. Click **Advanced options** at the bottom of the page.
7. In the **First byte timeout** field, enter the new first byte timeout in milliseconds. Approximately 15000 milliseconds is a good default to start with.
8. Click **Update** to save your changes.
9. Click **Activate** to deploy your configuration changes.

Configure caching actions for specific workflows

When you create a cache setting, the **Action** setting determines how the request will be handled. The action settings and the most common workflow for each are described below.

- **Do nothing now** - Selecting this option will apply the request setting options, but won't force a lookup or a pass action.
- **Pass (do not cache)** - Selecting this option will make the request and subsequent response bypass the cache and go straight to origin. Use this option if you need to conditionally prevent pages from caching or when using conditions
- **Restart processing (not common)** - Selecting this option will restart processing of the request. Use this option if you need to check multiple backends for a single request
- **Deliver (not common)** - Selecting this option will deliver the object to the client. Use this option if you need to create an override condition.

Consider custom error handling

When downtime can't be avoided, standard error messages might not ensure the best user experience. Consider creating custom error messages that include information specific to the request being made and pertinent to the user. Our guide to creating error pages with custom responses provides more detail.

HTTP status codes cached by default

Fastly caches the following response status codes by default. In addition to these statuses, you can force an object to cache under other states using conditions and responses.

Code	Message
`200`	OK
`203`	Non-Authoritative Information
`300`	Multiple Choices
`301`	Moved Permanently
`302`	Moved Temporarily
`404`	Not Found
`410`	Gone

TIP

You can override caching defaults based on a backend response. For example, if you don't want 404 error responses to be cached for the full caching period of a day, you could add a cache object and then create conditions for it.

To cache status codes other than the ones listed above, set `beresp.cacheable = true;` in `vcl_fetch`. This tells Varnish to obey backend HTTP caching headers and any other custom `ttl` logic. A common pattern is to allow all 2XX responses to be cacheable:

```
sub vcl_fetch {
  # ...
  if (beresp.status >= 200 && beresp.status < 300) {
    set beresp.cacheable = true;
  }
  # ...
```

```
6 }
7
```

Inform Fastly Customer Support

We like to be sure we're readily available for assistance during customer events. When you know in advance that an event is forthcoming, contact support with details. Be sure to include details about:

- the date and time of the event
- the type of event happening
- how long you expect it to last (if it's planned)
- the Fastly services that might be affected

If the event you're planning is designed to validate the security of your service behind Fastly, be sure to read our guide to security testing first.

---

* * *

	Checking cache
🔗	/en/guides/checking-cache

Checking the cache status of an object on your website can help when troubleshooting problems. You can use the Fastly control panel or the curl command (an open-source command line tool for transferring data with URL syntax from or to a server using one of many supported protocols) to check Fastly's cache nodes for a cached object, and you can use the information provided to examine the object's status, response time, and content hash.

Using curl

You can use one of two curl commands to tell if your request is caching in the Fastly network:

- a simple curl command that displays the request and response headers for a given object
- a slightly more complex curl command that uses the `Fastly-Debug` header to expose information normally stripped by the simple curl command

Using the simple curl command

The following curl command displays the request and response headers for a given object:

```
$ curl -svo /dev/null www.example.com/index.html
```

where `www.example.com/index.html` is replaced with the full object path of the object you're testing.

For example, using `curl -svo /dev/null www.example.com` produces something like the following section of output:

```
[...]

< Age: 142
< X-Served-By: cache-jfk1041-JFK, cache-ord1720-ORD
< X-Cache: HIT, HIT
< X-Cache-Hits: 1, 7

[...]
```

This output tells us the current age of the object in cache. It also shows shielding is enabled because two cache nodes display in `X-Served-By`. However, we're most interested in the output of the `X-Cache` header. A properly caching object displays a value of `X-Cache: HIT`, `X-Cache: HIT, HIT`, `X-Cache: HIT, MISS`, or `X-Cache: MISS, HIT`.

Using a Fastly-Debug header with curl

The `Fastly-Debug` header provides additional information for debugging by exposing specific information that is normally stripped when using a simple curl command:

```
$ curl -svo /dev/null -H "Fastly-Debug:1" www.example.com/index.html
```

where `www.example.com/index.html` is replaced with the full object path of the object you're testing.

For example, with optional shielding being used and a TTL set to 86400 (24 hours) using `Surrogate-Control`, the command `curl -svo /dev/null -H "Fastly-Debug:1" www.example.com` produces something like the following section of output:

```
[...]

< Surrogate-Control: max-age=86400
< Surrogate-Key: articles articles/1 articles/2

[...]
< Age: 403
< Fastly-Debug-Path: (D cache-ord1722-ORD 1470672957) (F cache-ord1743-C
< Fastly-Debug-TTL: (H cache-ord1722-ORD 85997.246 0.000 403) (H cache-j
< X-Served-By: cache-jfk1041-JFK, cache-ord1722-ORD
< X-Cache: HIT, HIT
< X-Cache-Hits: 1, 6

[...]
```

Because surrogate keys are present, the `Fastly-Debug` header exposes them. As with the simple curl command, this section of output tells us the current age of the object in cache. In addition, `Fastly-Debug` exposes specific header details to help with debugging as noted below.

Using the Fastly control panel


> **WARNING**
>
> When you click **Check Cache**, every Fastly cache node will send a request to your origin for the object. Clicking the button multiple times could overwhelm your origin with requests. Consider using curl to check the cache status instead.

Follow the steps below to check the cache status of an object using the Fastly control panel:

1. Log in to the Fastly control panel.


2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.

3. Click **Check Cache**.



4. In the **Full URL path** field, enter the full path to the object (e.g., `http://www.example.com/object.html`).

5. Click **Check Cache**. The results are displayed in the Check Cache window.



You can use this information to verify that the same copy of an object is stored on all of our servers. If the content hash is different across nodes, that usually indicates that there's a caching problem.

Information exposed by the Fastly-Debug header

`Fastly-Debug Path` contains information about which cache server handles fetching and delivery of an object. The edge POP appears first in the sequence and the shield POP appears second.

- `D` represents which cache by name in the edge or shield ran `vcl_deliver`
- `F` represents which cache by name in the edge or shield ran `vcl_fetch`
- the number following each specific server name is a timestamp in seconds

With shielding enabled, you should generally see four cache servers listed in this header. In rare cases where a cache server exists as both an edge and a shield within the cluster for that object, you may see two or three caches listed.

`Fastly-Debug-TTL` provides information on HIT and MISS timings.

- `H` represents a HIT, meaning the object was found in the cache
- `M` represents a MISS, meaning the object was not cached at the time of the query

For each of these timings:

- the first number specifies the TTL remaining for the object
- the second number specifies the grace period
- the third number specifies the current age of the object in cache

It may take a few requests to see these numbers populate as expected because they need to either hit the cluster node or a node where the content already exists in temporary memory.

`X-Served-By` indicates the shield and edge servers that were queried for the request. The shield POP appears first in the sequence and the edge POP appears second.

`X-Cache` indicates whether the request was a HIT or a MISS for the data center.

> **NOTE**
>
> Our shielding debugging documentation provides in depth details key to understanding the `X-Served-By`, `X-Cache`, and `X-Cache-Hits` headers with shielded services.

---

* * *

Controlling caching

/en/guides/controlling-caching

When we store your content in cache, we calculate a Time to Live (TTL). The TTL is the maximum amount of time we will use the content to answer requests without consulting your origin server. After the TTL expires, we may keep the content in storage, but we won't use it to answer requests unless we're able to revalidate it with your origin.

There's no guarantee that the content will stay cached for the length of time specified in the TTL. Depending on the size of the object and how popular it is relative to other objects, we may delete it before its TTL expires.

For more information about controlling how long Fastly caches your resources, start with our documentation on cache freshness. In general, we will honor any Cache-Control headers you send to us from your origin.

Determining the TTL of an object

You can determine the TTL of an individual object as follows:

- If you've set the `Surrogate-Control: max-age`, `Cache-Control: max-age`, or `Expires` headers, the TTL is whatever you specified in those headers
- If you've specified the TTL in the Fastly control panel or custom VCL, the TTL is whatever you specified
- If you've specified the TTL in the Fastly control panel or custom VCL and you've set the `Surrogate-Control: max-age`, `Cache-Control: max-age`, or `Expires` headers, the TTL specified in the control panel might override the TTL specified in the origin response
- If you haven't specified the TTL in the Fastly control panel or custom VCL and you haven't set the `Surrogate-Control: max-age`, `Cache-Control: max-age`, or `Expires` headers, the TTL is 3600 seconds. If you use custom VCL or Fiddle, the default is 120 seconds.

You can change the fallback TTL in the service configuration.

Setting different TTLs for Fastly cache and web browsers

Purging objects from the Fastly cache is easy. Clearing the caches of users' web browsers is much harder. For that reason, it can make sense to set different TTLs for content in the Fastly cache versus users' web browsers. You can set different TTLs for the Fastly cache and web browsers through Surrogate-Control headers defined by the W3C. For example, if you wanted Fastly to cache something for a year but you also wanted to set a maximum age of a single day for users viewing that object in a web browser, then you could return the following HTTP headers:

```
Surrogate-Control: max-age=31557600
Cache-Control: max-age=86400
```

The Surrogate-Control header in this example tells Fastly to cache the object for a maximum of 31557600 seconds (one year). The Cache-Control header in this example tells the browser to cache the object for a maximum of 86400 seconds (1 day).

TIP

CDNs can't invalidate an end user's web browser cache. If your content is going to change frequently or if you want new content immediately available to end users, the best strategy is to cache that content on Fastly and specifically instruct browsers not to cache it. Then, when you purge the Fastly cache, an end user's browser will display the new version the next time the content is requested.

One way to do this is to return the following headers:

```
Surrogate-Control: max-age=31557600
Cache-Control: private, no-store
```

This Surrogate-Control header tells Fastly to cache the object for a maximum of 31557600 seconds (one year). The Cache-Control header should be added in `vcl_deliver`. It tells the browser not to cache the object.


For Surrogate-Control, Fastly supports the `max-age`, `stale-if-error`, and `stale-while-revalidate` parameters.

For more information about controlling caching, check out our documentation on cache freshness.

Conditionally preventing pages from caching

To conditionally prevent pages from caching, follow the steps below.


1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Settings**.
5. Click **Create cache setting** to create a new cache setting.



6. Fill out the **Create a cache setting** fields as follows:
   - In the **Name** field, enter a descriptive name for the new cache setting (e.g., `Force Pass`).

- In the **TTL (seconds)** field, enter `0` to set the lifespan of the object in our cache nodes to zero.
- From the **Action** menu, select **Pass (do not cache)** to pass the request and avoid caching it.
- In the **Stale TTL (seconds)** field, enter `0` to set the amount of time to serve stale content, in seconds, to zero.

7. Click **Create**.
8. Click the **Attach a condition** link to the right of the newly created cache setting.



9. Fill out the **Create a new cache condition** fields as follows:

- In the **Name** field, enter a descriptive name for the condition (e.g., `Cacheable URLs`).
- In the **Apply if** field, create a condition that matches the URLs to not cache. For example, you could enter `req.url !~ "^/(cacheable|images|assets)"` to set the condition to look for URLs that do not start with `/cacheable`, `/images`, or `/assets`. If the condition finds them, the URLs should be cached. If the condition doesn't find them, the cache setting that is set to `Pass` ensures the URLs are explicitly not cached.

10. Click **Save and apply to**.
11. Click **Activate** to deploy your configuration changes.

TIP

You can use these steps to override default caching based on a backend response.

---

* * *


Enabling API caching

/en/guides/enabling-api-caching

Application Programming Interfaces (APIs) allow you to retrieve data from a variety of web services. Fastly makes it possible for you to cache your API so you can accelerate the performance of your service-oriented architecture. It optimizes your API's performance by efficiently handling traffic bursts and reducing latency.

An example

Let's look at an example to learn how API caching works. Imagine we're an online magazine with articles on which users can make comments. Each article can have many comments, and each comment is created by exactly one user.



We'll design a RESTful API specification and use it to manipulate and retrieve comments:

- `GET /comment` - Returns a list of all comments
- `GET /comment/:id` - Returns a comment with the given ID
- `POST /comment` - Creates a new comment
- `PUT /comment/:id` - Updates a comment with the given ID
- `DELETE /comment/:id` - Deletes a comment with the given ID

The create, read, update, and delete (CRUD) methods ensure the API can perform its basic operations, but they don't expose the relational aspect of the data. To do so, you would add a couple of relational endpoints:

- `GET /articles/:article_id/comments` - Get a list of comments for a given article
- `GET /user/:user_id/comments` - Get all comments for a given user

Endpoints like these allow programmers to get the information they need to do things like render the HTML page for an article, or display comments on a user's profile page. While there are many other possible endpoints we could construct, this set should suffice for the purposes of this guide. Let's assume that the API has been programmed to use an Object-Relational Mapper (ORM), such as ActiveRecord, when interacting with the database.

Determining which API endpoints to cache

Start by identifying the URLs you want to cache. We recommend splitting the specification endpoints into two groups.

The first group, called *accessors*, retrieves or accesses the comment data. These are the endpoints you want to cache using Fastly. Using the example, four endpoints match this description:

- `GET /comment`
- `GET /comment/:id`

- `GET /article/:article_id/comments`
- `GET /user/:user_id/comments`

The second group, called *mutators*, changes or mutates the comment data. These endpoints are always dynamic, and are therefore uncacheable. Using the example, three endpoints match this description:

- `POST /comment`
- `PUT /comment/:id`
- `DELETE /comment/:id`

You should see a pattern emerging. Because the example API is RESTful, we can use a simple rule to identify the accessor and mutator endpoints: GET endpoints can be cached, but PUT, POST, and DELETE endpoints cannot.

Once you've gathered this information, you're ready to program the API to configure PURGE requests.

Configuring PURGE requests

Don't be tempted to point at the PUT, POST, and DELETE endpoints as the place where data is modified. In most modern APIs, these endpoints represent an interface to the actual model code responsible for handling the database modifications.

In the example, we assumed that we'd be using an ORM to perform the actual database work. Most ORMs allow programmers to set special *callbacks* on models that will fire when certain actions have been performed (e.g., before or after validation, or after creating a new record).

For purging, we are interested in whether a model has saved information to the database — whether it's a new record, an update to an existing record, or the deleting of a record. At this point, we'd add a callback that tells the API to send a PURGE request to Fastly for each of the cacheable endpoints.

For an ActiveRecord comments model, you could do something like this:

```
require 'fastly'

class Comment < ActiveRecord::Base
  fastly = Fastly.new(api_key: 'FASTLY_API_TOKEN')
```

```
4
5     after_save do
6       fastly.purge "/comment"
7       fastly.purge "/comment/#{self.id}"
8       fastly.purge "/article/#{self.article_id}/comments"
9       fastly.purge "/user/#{self.user_id}/comments"
10    end
11  end
12
```

Keep two things in mind when creating the callback:

- The purge code should be triggered *after* the information has been saved to the database, otherwise a race condition could be created where Fastly fetches the data from the origin server before the data has been saved to the database. This would cache the old data instead of the new data.
- These URLs are being purged because they have content that changes when a comment is changed.

With the model code in place, the API is now ready to be cached.

Setting up Fastly

The final step to enabling API caching involves setting up Fastly. You'll need to:

- Create a new service
- Add the domain for the API
- Add the origin server that powers the API

In addition, you can optionally create rules that tell Fastly how to work with the specific elements that are exclusive to your API.

> NOTE
>
> By default, Fastly will not cache PUT, POST, and DELETE requests.

Creating a new service


Follow the instructions for creating a new service. You'll add specific details about your API server when you fill out the **Create a new service** fields:

- In the **Name** field, enter a name for this service that helps you identify it's related to caching your API information (e.g., `My API Service`).
- In the **Domain** field, enter the domain name associated with your API (e.g., `api.example.com`).
- In the **Address** field, enter the IP address or hostname of your API server.

Adding the domain

Follow these instructions to add the API's domain name to your Fastly service:

1. Click **Edit configuration** and then select the option to clone the active version.
2. Click **Create domain**.



3. Fill out the **Create a domain** fields as follows:
    - In the **Domain Name** field, enter the domain name for the API.
    - In the **Comment** field, enter an optional comment that describes your domain.
4. Click **Create**. Your API's domain name appears in the list of domains.

Adding the origin server

Follow the instructions for working with hosts. You'll add specific details about your API server when you fill out the **Create a host** fields:

- In the **Name** field, enter a name for the origin server that helps you identify it's related to caching your API information.
- In the **Address** field, enter the IP address (or hostname) of the API server.

---

* * *

	Implementing API cache control
🔗	/en/guides/implementing-api-cache-control

This guide explains how to implement API cache control. Once you've enabled API caching, and ensured purging works properly with your cached data, you can set up specific headers like Cache-Control and Surrogate-Control to change when data is cached.

Understanding Cache-Control headers

In general, we assume that GET requests are cached and PUT, POST, and DELETE requests are not. For an ideal REST API, this rule works well. Unfortunately, most APIs are far from ideal and require additional caching rules for some requests.

For these reasons, it's a good idea to set Cache-Control headers when migrating APIs to Fastly. Cache-Control, as defined by RFC 7234 (the HTTP specification), includes many different options for appropriate handling of cached data. Specifically, Cache-Control headers tell user agents (e.g., web browsers) how to handle the caching of server responses. For example:

- `Cache-Control: private`
- `Cache-Control: max-age=86400`

In the first example, `private` tells the user agent the information is specific to a single user and should not be cached for other users. In the second example, `max-age=86400` tells the user agent the response can be cached, but that it expires in exactly 86,400 seconds (one day).

Fastly respects Cache-Control headers by default, but you can also use another proxy-specific header: Surrogate-Control. Surrogate-Control headers are similar to Cache-Control headers, but provide instructions to reverse proxy caches like Fastly. You can use Cache-

Control and Surrogate-Control headers together. For more information about Cache-Control and Surrogate-Control headers, see our documentation on cache freshness.

An updated example

Let's take a look at how the Cache-Control headers could be used in our original example, the comments API. Recall the API endpoint that provided a list of comments for a given article:

```
GET /article/:article_id/comments
```

When a user submits a comment for a given article, the response from this endpoint will be purged from the Fastly cache by the comment model. It's hard to predict when content will change. Therefore, we'd like to ensure the following:

1. If the content doesn't change, it should stay cached in Fastly for a reasonable amount of time.
2. If the content does change, it should not be cached by the client longer than it needs to be.

The goal is to ensure that API responses will reach clients in a timely manner, but we also want to ensure that clients always have the most up-to-date information. The first constraint can be solved by using the Surrogate-Control header, and the second constraint can be solved by using the Cache-Control header:

```
Surrogate-Control: max-age=86400
Cache-Control: max-age=60
```

These headers tell Fastly that it is allowed to cache the content for up to one day. In addition, the headers tell the client that it is allowed to cache the content for 60 seconds, and that it should go back to its source of truth (in this case, the Fastly cache) after 60 seconds.

Implementing cache control

Migrating APIs isn't easy, even for experienced teams. When migrating an API to Fastly, we recommend separating the task into three strategic endpoint migrations to make the process more manageable while still maintaining the validity of the API as a whole.

Preparing the API

To ensure that the API bypasses the cache during the piecewise migration, we must have every API endpoint return a specific control header:

```
Cache-Control: private
```

This header tells Fastly that a request to any endpoint on the API should bypass the cache and be sent directly to the origin. This will allow us to serve the API via Fastly and have it work as expected.

> **NOTE**
>
> Modern web frameworks allow for blanket rules to be overridden by specific endpoints (for example, by the use of middlewares). Depending on how the API has been implemented, this step might be as simple as adding a single line of code.

Serving traffic with Fastly

The next step is configuring a Fastly service to serve the API's traffic. After you save the configuration, there will be an immediate speed improvement. This happens because Fastly's cache servers keep long-lasting connections to the API's origin servers, which reduces the latency overhead of establishing multiple TCP connections.

Migrating endpoints

Now we can implement instant purge caching for each cacheable API endpoint, one at a time. The order in which this is done depends on the API, but by targeting the slowest endpoints first, you can achieve dramatic improvements for endpoints that need them the most. Because each endpoint can be worked on independently, the engineering process is easier to manage.

Excluding endpoints

The last step is deciding which API endpoints you don't want Fastly to cache. To disable caching for endpoints, you'll need to add new conditions for the endpoints. As you learned in Preparing the API, using the `Cache-Control: private` header is another option for disabling caching.

---

* * *

Overriding caching defaults based on a backend response


/en/guides/overriding-caching-defaults-based-on-a-backend-response

---

In certain situations you may want to conditionally apply a different caching policy based on a backend response. In this particular case we have backend that on occasion returns 404 errors (e.g., document not found). We don't want those responses to be cached for the full caching period of a day but only for 5 minutes. To override default caching we add a cache object and then create conditions for it.

Creating the new Cache Object

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Settings**.
5. Click **Create cache setting**.



6. Fill out the **Create a cache setting** fields as follows:

    - In the **Name** field, enter a descriptive name for the new cache settings.
    - In the **TTL (seconds)** field, enter the amount of time, in seconds, to cache the objects (e.g., `300`).
    - From the **Action** menu, select **Deliver**.
    - In the **Stale TTL (seconds)** field, enter the amount of time to serve stale or expired responses, in seconds, should the backend become unavailable (e.g.,


`300`).

7. Click **Create**.

Creating an Override Condition for the new Cache Object

Once the object is created, add a condition to it.

1. Click **Attach a condition** to the right of the object.
2. Click **Create cache setting**.



3. Fill out the **Create a new cache setting** fields as follows:
    - In the **Name** field, enter a descriptive name for the new condition. For example, `Override cache default`.
    - In the **Apply if** field, enter an appropriate backend response header to specify when the condition will be applied. For example, `beresp.status == 404`.
4. Click **Save and apply to**.
5. Click **Activate** to deploy your configuration changes.

Other notes

You can use any backend response header in the **Apply if** field to make decisions on caching.

For example, `beresp.http.Content-Type ~ "^text/html"` can be used to specify different caching rules for HTML documents.

---

* * *

📄	**Preventing cache poisoning via HTTP X-headers**
🔗	/en/guides/preventing-cache-poisoning

Fastly service configurations may be vulnerable to cache poisoning if they do not take into consideration the interaction between HTTP "X-" headers used by backends to select content. This vulnerability can be mitigated using a VCL patch or by modifying backend configurations.

When cache poisoning can occur

If one or more of your backends uses the contents of the X-Forwarded-Host, X-Rewrite-URL, or X-Original-URL HTTP request headers to decide which of your users (or which security domain) it sends an HTTP response for, you could be impacted by vulnerability. If your site's Fastly configuration passes one of these headers to your backend and does not factor the contents of it into the effective edge cache key (for example, explicitly or via the Vary HTTP

response header), an attacker could potentially cause the edge to store a response with arbitrary content inserted into a victim's cache.

An attacker might be able to poison a Fastly customer URL by sending an HTTP request to a site that causes the affected backend to respond with an attacker-controlled response. The malicious response object would be stored in the site's cache at a poisoned URL. An attacker could then potentially lure a victim site user into browsing the poisoned URL, where they would be served malicious content.

How to mitigate cache poisoning

If your origin uses special values to select content for users or to otherwise select between security domains, consider reconfiguring your origin server and applying any corresponding security updates as suggested in our original security advisory. In addition, strip or normalize the values of X-Forwarded-Host, X-Rewrite-URL, or X-Original-URL in VCL.

To do this, set the vulnerable headers to a known-safe value or unset the headers completely. For example, the X-Forwarded-Host header can be set to the value of the Host header via the following VCL snippet:

```
set req.http.x-forwarded-host = req.http.host;
```

The X-Original-URL header can be unset via the following VCL snippet:

```
unset req.http.x-original-url;
```

And X-Rewrite-URL can be unset via the following VCL snippet:

```
unset req.http.x-rewrite-url;
```

Alternatively, the values could be included in your cache key or Vary header to prevent caching of content across security domains. See our guide to manipulating the cache key for more information.

---

* * *

📄	**Segmented Caching**
🔗	/en/guides/segmented-caching

Fastly's Segmented Caching feature allows you to cache resources of any size. Segmented Caching works by breaking resources into smaller segments in Fastly's cache then recombining or splitting these resources to respond to arbitrary size byte `Range:` requests from clients. Once enabled, Segmented Caching improves performance for `Range:` requests and allows Fastly to efficiently cache resources of any size.

> **WARNING**
>
> Fastly recommends enabling Segmented Caching on services that will be serving large resources. Without Segmented Caching enabled, the resource size limits for your account depend on when you become a Fastly customer:
>
> - If you created your account on or after June 17, 2020 and haven't enabled Segmented Caching, your Fastly services have a maximum object size of 20 MB.
> - If you created your account prior to June 17, 2020 and haven't enabled Segmented Caching, your Fastly services have a maximum cacheable object size of 2 GB for requests without Streaming Miss or 5 GB for requests with Streaming Miss.

How Segmented Caching works

When an end user makes a `Range:` request for a resource with Segmented Caching enabled and a cache miss occurs (that is, at least part of the range is not cached), Fastly will make the appropriate `Range:` requests back to origin. Segmented Caching will then ensure only the specific portions of the resource that have been requested by the end user (along with rounding based on object size) will be cached rather than the entire resource. Partial cache hits will result in having the cached portion served from cache and the missing pieces fetched from origin. (Requests for an entire resource would be treated as a byte `Range:` request from 0 to end of resource.)

Once Fastly has all of the objects necessary to respond to an end user's request, the Segmented Caching feature will assemble the response by concatenating or pulling portions of objects. The requests back to origin, also called "inner requests," will have a `true` value for `segmented_caching.is_inner_req` and requests from end users, also called "outer requests," will have a `true` value for `segmented_caching.is_outer_req`. If a request is made for an object without segmented caching enabled, both variables will have a FALSE value.

> **NOTE**

> The feature will only go back to origin for missing objects needed to handle the end-client's byte `Range:` request. Cache hits will occur based on having that portion of resource in cache even if the end user's range exact request is unique.

Limitations and considerations

This feature has the following limitations you should take into account:

- **Segmented Caching isn't intended for dynamically generated content.** If your content isn't fully static (e.g., you have dynamic content like user-generated comments), be sure to set up purging any time the content changes to avoid any potential for data corruption.
- **Segmented Caching is not compatible with object compression and ESI.** To use either of these features, you must ensure Segmented Caching is disabled.
- **Segmented Caching is not compatible with Fastly's Image Optimizer (IO).** If IO is enabled, Segmented Caching is disabled automatically.
- **HTTP chunked transfer encoding between Fastly and origin isn't supported.** Your origin server must frame responses to `Range:` requests with the `Content-Length` header.
- **URL purges must be authenticated.** Segmented caching allows you to purge all range objects for the resource by URL purge, but authentication for URL purge needs to be enabled due to its underlying implementation. Make sure you've provided an authorization token for URL purges as described in our purging documentation.
- **Segmented Caching cannot be enabled based on resource size.** The VCL code to enable Segmented caching must run *before* the resource is requested from cache, so it is not possible to know how large it will be. However, it is possible to make segmented caching conditional upon the URL (e.g. `/video/`) or file extension (e.g. *.m4v), and this is a common use case for resources which will benefit from it. Our instructions below contain an example of how to enable the Segmented Caching feature based on extension.

This feature also has the following considerations you should take into account:

- **Resources cached prior to enabling Segmented Caching are not used.** If you are enabling Segmented Caching on an existing service, whole resources already in cache are ignored and Varnish will go back to origin to build range request objects. You can choose to purge these or ignore them to be aged out of cache.

- **Your cache hit ratio (CHR) will appear lower than it actually is** because only outer requests are used in the calculation. For example, if there is a request for the first 100 MB of a resource but Fastly only has 99 MB of 100 MB in cache, the entire request will be counted as a miss in the CHR stat. In practice, only 1 MB had to be fetched from origin and you experienced 99% origin offload.

Enabling Segmented Caching

Use the following steps to enable Segmented Caching.

1. Determine which resources should use Segmented Caching.

   > **TIP**
   >
   > We recommend focusing on a set of file extensions or a well-defined URL structure that distinguishes the resources.

2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL Snippets**.
5. Click **Create your first VCL snippet**.
6. Fill out the **Create a VCL snippet** fields as follows:
   - In the **Name** field, enter an appropriate name (e.g., `Enable segmented caching`).
   - From **Type (placement of the snippets)** menu, select **within subroutine**.
   - From the **Select subroutine** menu, select **recv (`vcl_recv`)**.
   - In the **VCL** field, add a VCL snippet that sets the `req.enable_segmented_caching` VCL variable to `true` in `vcl_recv`. For example, to ensure proper caching of the large resources you've identified that contain MPEG-2-compressed video data, you could add this VCL snippet in `vcl_recv`:

```
# my custom enabled Segmented Caching code
if (req.url.ext == "ts") {
```

```
  set req.enable_segmented_caching = true;
}

```

This snippet tells Fastly to look for requests for files with the `ts` extension and then enable Segmented Caching for those files.

7. Click **Create** to create the snippet.
8. Click **Activate** to deploy your configuration changes.

---

* * *

📄	**Temporarily disabling caching**
🔗	/en/guides/temporarily-disabling-caching

Caching can be disabled:

- at the individual URL level,
- at the browser level, and
- at the site level.

Disabling caching at the individual URL level

To disable caching at the individual URL level:

1. Create a request setting that always forces a pass.
2. Add a condition to the request setting that looks for specific URLs.
3. Activate the new version of your service to enable the setting.

Disabling caching at the browser level

Theoretically, all browsers should follow the stated rules of the HTTP standard. In practice, however, some browsers don't strictly follow these rules. The following combination of headers seems to force absolutely no caching with every browser we've tested.

```
Cache-Control: no-cache, no-store, private, must-revalidate, max-age=0,
Pragma: no-cache
Expires: 0
```


In addition, IE8 has some odd behavior to do with the back button. Adding `Vary: *` to the headers seems to fix the problem.

> **IMPORTANT**
>
> If you want your content cached in Fastly but not cached on the browser, you must not add these headers on your origin server. Instead, add these as new Headers on the Content page and be sure the Type is set to Response.

Disabling caching at the site level

You can disable caching at the site level by creating a VCL Snippet to pass on all requests to your service:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL Snippets**.
5. Click **Create Snippet**.



6. Fill out the Create a VCL snippet fields as follows:
   - In the **Name** field, enter an appropriate name (e.g., `Pass All Requests`).
   - From the **Type** controls, select **within subroutine**.
   - From the **Select subroutine** menu, select **recv (`vcl_recv`)**.
   - In the **VCL** field, add the following condition:

```
return(pass);
```

7. Click **Create** to create the snippet.

8. Click **Activate** to deploy your configuration changes.

All requests will continue to be passed until you remove return(pass); from `vcl_recv` in your VCL or you delete this snippet.

---


* * *

Category: Conditions

These articles describe conditions and how to use them in VCL and the Fastly control panel.

	About conditions
🔗	/en/guides/about-conditions

Conditions are a configuration mechanism that you can add to your service to control how particular requests are processed. Like conditions in general programming, Fastly conditions use IF-statements to evaluate requests using the logic you specify and formulate a response based on whether the request meets the condition (TRUE) or does not meet the condition (FALSE).



You can apply a condition using the Conditions feature of the control panel or by using a VCL IF statement on a snippet or in custom VCL.

Before you start using conditions

Be sure you understand the construction of basic logical expressions before you start using conditions. Specifically, you should understand basic C-style logical expression syntax (e.g., basic logic, operators such as && and precedence) when working with conditions. A basic programming guide that deals with IF style expressions in either the C or Perl language (the Tizag Perl tutorial is a good one to start with). Even though they aren't directly applicable to our condition examples, the syntax of these languages is similar to VCL.

A simple condition example

The simplest way to explain how Fastly handles conditions is this IF statement:

```
IF
   this condition happens
THEN
```

```
    respond this way

```

A practical example can demonstrate this. The vast majority of the time, your site processes requests for information as usual, but every so often customers mistype a search term or simply can't find what they're looking for and you're forced to display a 404 Not Found error. You've realized that when that happens, the standard 404 Not Found errors on your website aren't as helpful as they could be. To fix this, any time your server can't find what a customer is looking for (a condition), you want to display a customized 404 message instructing customers to contact your support team for help (a response).

In plain English, the IF statement might look like this:

```
IF
   404 Not Found is what we have to tell the customer
THEN
   respond with the special Contact Support page

```

The IF line in the example above is the *condition* you've set. The THEN line describes what will happen if that condition is met.

If you were to replace the English in the example above with VCL variables and a little bit of HTML, it might look like this instead:

```
IF
  beresp.status == 404
THEN
  respond with <html><body><h1>Can't find it?</h1><p>Contact suppor

```

Interested in doing this? We have step-by-step instructions for creating error pages with custom responses.

Ideas for using conditions

Need some more ideas for when you could use conditions? Explore these:

Condition	Response	Learn how
A web robot wants to crawl a particular area of your website	Provide a customized robots.txt file defining which areas of your website should not be processed or scanned	Creating and customizing a robots.txt file
Your server needs to return a 404 Not Found response	Change the default caching time for only 404 responses from 3600 seconds (60 minutes) to 120 seconds (2 minutes)	Overriding caching defaults based on a backend response
Users request a popular page on your site but it's been moved to a different area	Have Fastly redirect the page requests at the edge, without having to go back to your origin server for it	Redirects

Types of conditions and when you can use them

We group conditions into three types:

- request conditions
- response conditions
- cache conditions

A condition's type dictates which configuration objects it can be applied to during a specific stage of the caching process. In addition, each stage of caching works with a different set of VCL variables that can be used to create conditions.

Condition type	Applied when Fastly ...	Works with which VCL variables
Request	processes a request	`client.*` `server.*` `req.*`
Response	processes a response to a request	`client.*` `server.*`

Condition type	Applied when Fastly ...	Works with which VCL variables
		`req.*` `resp.*`
Cache	receives a response from your origin, just before that response is (potentially) cached	`client.*` `server.*` `req.*` `beresp.*`

Where to go for more information

The Varnish Cache documentation provides a complete list of variables you can use to craft conditions. Keep in mind, however, some of the variables Varnish allows may not be available or may have no meaning in the context of Fastly services. For more information, see our Guide to VCL.

---

* * *

Troubleshooting conditions

/en/guides/troubleshooting-conditions

If you are having problems using conditions, here are some common things to look for.

Check the Apply if field for if statements

Most problems with conditions occur in the Apply if parameter because it uses logical expressions to represent actual VCL variables that specify when a condition should be applied to a configuration object. If you are having problems using conditions, start by checking to see if you've put an `if ()` statement in the wrong place. A condition's if statement is implied and doesn't need to be placed in the Apply if field of the condition window. You only need to enter an evaluated expression (e.g., `req.url ~ "^/special/"`).

Check the construction of inverse regex matches

Consider if inverse regular expression (regex) matching might be the issue, especially if you're using it to exclude a particular URL in your condition. When using the `!~` (inverse regex match) to build expressions that exclude particular URLs, be thoughtful when also using the `||` or `&&` operators and multiple patterns.

For example, if you want to apply something to all URLs except those that start with `/admin`, the condition you'd enter into the Apply if field would be `req.url !~ "^/admin"`. If you also wanted to exclude URLs starting with `/internal`, that expression would be `!(req.url ~ "^/admin" || req.url ~ "^/internal")`.

> **TIP**
>
> Keep in mind De Morgan's laws if you're using multiple conditions and negation.

Check for general regex formatting mistakes

Consider the following general regex issues that may have caused trouble:

- **Is case sensitivity the problem?** Varnish regex is case sensitive by default. To use a case insensitive check, you must use the `(?i)` flag.
- **Have you escaped forward slashes?** Forward slashes don't need to be escaped in Varnish regex.

Our cheatsheet provides additional examples of using VCL with regular expressions.

---

* * *

	Using conditions
🔗	/en/guides/using-conditions

Conditions use the Varnish Configuration Language (VCL) to define when a configuration object should be applied while processing requests to a cache server. Once you understand some basics about conditions, use this guide to learn about how to create conditions using the Fastly control panel and when to use them.

Where to find conditions

Conditions appear in two areas of Fastly's control panel:

- The Manage conditions page lists all conditions available to your configuration settings.
- Each configuration object displays conditions specifically attached to them.


Conditions on the Manage conditions page

The Manage conditions page provides an overview of all the conditions currently available to your service. You can see at a glance which conditions are mapped to configuration objects. It allows you to create new conditions and search for existing ones.


To view conditions on the Manage conditions page:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Conditions**. A list of all conditions for your service appears.

For example, this service has one request condition available:




The Example Request Condition shown above currently isn't applied to a configuration object (as indicated by "Not applied to anything"). If it was, it would instead appear similar to this:




Conditions attached directly to a configuration object

Configuration objects appear differently in the web interface when conditions are attached to them. For example, this request setting has no condition attached to it:



Once you click the Attach a condition link to create a new condition or attach an existing condition, however, the web interface changes how the configuration object appears:



By default, configuration objects hide the majority of details for any attached conditions. You can unhide those details by clicking the Show details link. When expanded, the details vary depending on the type of condition.

Parts of a properly configured condition

Conditions require only a few parameters, making them appear deceptively simple. Specifically, they require:

- a **Type** parameter that classifies the condition being added. If added via the Manage conditions page, the type can always be manually selected. If added via the Attach a condition link on a configuration object, the type is automatically applied whenever possible.
- a **Name** parameter that serves human-readable identifier of the condition.

- an **Apply if** statement containing the logical expression to execute in VCL to determine if condition resolves as True or False.

Most problems with conditions occur in the Apply if parameter.

Performing matches on basic logical expressions

Properly configured conditions can perform matches on complicated logical expressions specified in the Apply if parameter. For example:

This logical expression ...	Matches when ...
`client.ip == "127.0.0.1"`	The client requesting a resource on your service has the IP `127.0.0.1`.
`req.http.host == "example.com"`	The Host header of the incoming request is `example.com`.
`req.method == "POST" && req.url ~ "^/api/articles/"`	The request is a POST and the URL begins with `/api/articles/`.

The `client.ip`, `req.http.host`, `req.method`, and `req.url` conditions shown above all represent configuration variables in VCL.

Using operators to perform matches on complex logical expressions

You could also get creative and create a more complex condition used by Fastly that might have an Apply if parameter that looked like this:

```
req.http.host == "www.example.com" && (req.url !~ "/foo" && req.url
```

This condition tells the cache server that the Host should equal `www.example.com` and the URL cannot match `/foo` or `/bar` or `/baz`. You might use this type of condition when you have multiple variables or options and want to fine-tune your results. In this example, you are indicating that you don't want URLs that contain `foo`, `bar`, or `baz` by using the following operators:

This operator ...	Does this ...
`( )`	groups expressions and restricts alteration to part of the regex
`&&`	ensures each equation is true
`!~`	excludes any URLs that include the specified variables

An example of adding conditions

The scenario: You want to add a new origin server that handles a specific portion of your API requests. Some requests to this API must be cached differently than other requests to your API, so you want to set special headers for specific types of requests. Specifically, you don't want your new origin server to cache PUT, POST, or DELETE requests because they're special for this particular API and send back extra, time dependent, meta-information in each response. And finally, you want to track the effectiveness of doing this. To accomplish all of this using conditions via the Fastly control panel, you would:

1. Create a new origin server to handle the special API traffic.
2. Create a new condition that tells the cache how to route some of the API requests to that origin server.
3. Create a new cache setting object to ensure the origin server caches only the correct responses.
4. Create a new condition that specifies when the cache settings object should be applied.
5. Create a new header to track the specific type of API requests.
6. Create a new response condition to make sure that the header is only set on specific type of request.
7. Check your work.

Create a new origin server


To create a new origin server that will handle the special API traffic, follow the instructions for working with hosts. You'll add specific details about your API server when you fill out the **Create a host** fields:

- In the **Name** field, enter a name for your API server (for example, `Special API Server`).
- In the **Address** field, enter the IP address (or hostname) of the API server.

Create a request condition

Once you've created a new origin server to handle the special API traffic, tell the cache how to route requests to this origin server by creating a request condition.

1. In the **Hosts** area, click **Attach a condition** next to the name of the origin server you just created.
2. You can either select an available condition or you can click **Create a new request condition**.



3. Fill out the **Create a new request condition** fields as follows:

   - In the **Name** field, enter a descriptive name for the new condition (for example `Special API Request`).
   - In the **Apply if** field, enter the appropriate request condition that will be applied (for example, `req.url ~ "^/special/"` could address all requests related to the special API server).


4. Click **Save and apply to**. The new condition for the host is created.

Create a cache settings object

Requests are now are being properly routed to the new origin server. Next, create a cache settings object to ensure Fastly doesn't cache any responses from PUT, POST, or DELETE requests. They're special for this particular API and send back extra, time dependent, meta-information in each response.

1. Click **Settings**.

2. In the **Cache Settings** area, click the **Create cache setting**.



3. Fill out the **Create a cache setting** fields as follow:


- In the **Name** field, enter a descriptive name for the new cache settings.
- Leave the **TTL (seconds)** field set to its default value.
- From the **Action** menu, select **Pass (do not cache)**.
- Leave the **Stale TTL (seconds)** field set to its default value.

4. Click **Create**.

Create and apply a condition to the cache settings object

Create a new condition that specifies when the cache settings object should be applied.

1. In the **Cache Settings** area, click the **Attach a condition** link next to the name of the cache setting you just created.
2. Click **Create a new cache condition**.




3. Fill out the **Create a new cache condition** fields as follows:
    - In the **Name** field, enter a descriptive name for the new condition (for example, `Special API Origin Response`).
    - In the **Apply if** field, enter the appropriate request condition that will be applied (for example, `req.method ~ "PUT|POST|DELETE" && beresp.status == 200`).
4. Click **Save and apply to**. The new condition for the cache setting is created.

Create a new header

To make sure you can track the effectiveness the new API, create a new header so you can use it to gather information about the special API requests as they happen.

1. Click **Content**.

2. In the **Headers** area, click the **Create header** button to create a new header.



3. Fill out the **Create a header** fields as follows:


- In the **Name** field, enter a descriptive name for the new header (for example, `Special API Set Header`).
- From the **Type** menu, select **Response** and from the **Action** menu, select **Set**.
- In the **Destination** field, enter the name of the header that will be affected by the action (for example, `http.super`).
- In the **Source** field, enter a description of the source where the content for this header comes from (for example, `"Thanks for asking!"`).
- Leave the **Ignore if set** and **Priority** fields set to their default settings.

4. Click **Create**.

Create a response condition for the new header

Once the header is created, create an associated condition to ensure this header is only set on that special type of request.

1. In the **Headers** area, click **Attach a condition** next to the name of the new header you just created.



2. Fill out the **Create a new response condition** fields as follows:
    - In the **Name** field, enter a descriptive name for the new condition (for example, `Special API Response Condition`).
    - In the **Apply if** field, enter the appropriate request condition that will be applied (for example, `req.url ~ "^/special" && resp.status == 200`).
3. Click **Save and apply to**. The new condition for the header is created.

Check your work

Before activating the configuration, review the generated VCL to see how Fastly converted the objects and conditions into actual VCL. For the example shown above, the VCL for the request condition appears as:

```
# Condition: Special API Request Prio: 10
if (req.url ~ "^/special/") {
  set req.backend = F_Special_API_Server;
}
#end condition
```

The cache settings and condition VCL appears as:

```
if (req.method ~ "PUT|POST|DELETE" && beresp.status == 200) {
  set beresp.ttl = 0s;
  set beresp.grace = 0s;
  return(pass);
}
```

And the new header response condition VCL appears as:

```
# Condition Special API Response Condition Prio: 10
if (req.url ~ "^/special" && resp.status == 200) {

  # Header rewrite Special API Set Header: 10
  set resp.http.super = "Thanks for asking!";
}
```

As you become more familiar with the VCL syntax and programming, look at the generated VCL to see if the configuration is doing what you think it is doing (most VCL is pretty simple once you know what the variables are referring to).

* * *

Category: Custom VCL

These articles describe how to create your own VCL files with specialized configurations.

About VCL Snippets

/en/guides/about-vcl-snippets

VCL Snippets are short blocks of VCL logic that can be included directly in your service configurations. They're ideal for adding small sections of code when you don't need more complex, specialized configurations that sometimes require custom VCL. Fastly supports two types of VCL Snippets:

- **Regular VCL Snippets** get created as you create versions of your Fastly configurations. They belong to a specific service and any modifications you make to the snippet are locked and deployed when you deploy a new version of that service. You can treat regular snippets like any other Fastly objects because we continue to clone them and deploy them with a service until you specifically delete them. You can create regular snippets using either the Fastly control panel or via the API.
- **Dynamic VCL Snippets** can be modified and deployed any time they're changed. Because they are versionless objects (much like dictionaries or ACLs at the edge), dynamic snippets can be modified independently from service changes. This means you can modify snippet code rapidly without deploying a service version that may not be ready for production. Changes immediately impact all service versions, including the active one. You can only create dynamic snippets via the API.

Limitations of VCL Snippets

- Snippets are limited to 1MB in size by default. If you need to store snippets larger than the limit, contact support.

- Snippets don't currently support conditions created through the Fastly control panel. You can, however, use `if` statements in snippet code.
- Snippets cannot currently be shared between services.
- Snippets cannot be nested (e.g., you can't include a snippet into another snippet).

---

* * *

	Basic authentication
🔗	/en/guides/basic-authentication

Basic authentication is a simple way of protecting a website at the edge. Users enter a username and password combination to access pages protected by basic authentication. You can use basic authentication to restrict access to low-risk assets like testing and staging environments.

> ⚠ WARNING
>
> Basic authentication shouldn't be used to restrict access to sensitive information. See the security considerations section for more information.

Implementing basic authentication

Follow our HTTP basic auth example to implement basic authentication using custom VCL or Compute.

Using basic authentication with GCS

To use basic authentication with Google Cloud Storage (GCS) as a origin server, add a request header to delete the `http.Authorization` header and prevent it from being sent to GCS. That header causes GCS to respond with a "Not Authorized" message instead of your request.

Security considerations

There are several security considerations you should take into account before using basic authentication:

- Basic authentication can't protect high-risk information. Don't use it to restrict access to sensitive information.
- If you're not using TLS, the password will be transmitted over the wire in Base64 encoding. The encoded string could easily be captured using an application like Wireshark and converted to plaintext.
- The password is cached by the user's web browser, and it can be permanently saved by the user's web browser.

Using access control lists

As an alternative to basic authentication, you can use access control lists (ACLs) to restrict access to your assets by allowlisting a set of IP addresses. To allowlist IP addresses with an ACL, add custom VCL to Fastly's boilerplate VCL.

```
# Who is allowed access ...
acl local {
    "localhost";
    "192.168.1.0"/24; /* and everyone on the local network */
    ! "192.168.1.23"; /* except for the dial-in router */
}

```

See our ACL guides for more information.

* * *

Custom responses that don't hit origin servers

/en/guides/custom-responses-that-dont-hit-origin-servers

Fastly can send custom responses for certain requests that you don't want to hit your origin servers.

Creating a quick response


Fastly provides features that allow you to quickly enable and configure responses for a robots.txt file and 404 and 503 errors. For more information, check out our guides on creating and customizing a robots.txt file and creating error pages with custom responses.

Creating an advanced response

You can create an advanced response to specify the HTTP status code, MIME type, and content of the response. For example, if you wanted to restrict caching to a URL subtree that contains images and scripts, you could configure Fastly to return an `HTTP 404 Not Found` response to requests for anything other than `/Content/*` or `/Scripts/*`. To illustrate how to implement this example, we'll show you how to create a response and corresponding request condition.

Follow these instructions to create an advance response:


1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click **Set up advanced response**.



6. Fill out the **Create a synthetic response** fields as follows:

   - In the **Name** field, enter a human-readable name for the response. For example `Return Not Found`.
   - From the **Status** menu, select an HTTP code to return to the client. For example, `404 Not Found`.
   - In the **MIME Type** field, enter the MIME type of the response. For example, `text/html`.
   - In the **Response** field, enter the plaintext or HTML content to return to the client. For example `Page not found`.


7. Click **Create** to create the response. The new response appears in the Responses area of the Content page.




Creating the request condition

Follow these instructions to attach a request condition to the response you just created:

1. Click the **Attach a condition** link next to the response that you just created.




2. Click **Create a new condition**.



3. Fill out the **Create a new condition** fields as follows:
    - From the **Type** menu, select the type of condition you want to create.
    - In the **Name** field, enter a human-readable name for the condition. For example, `Return Not Found`.

- In the **Apply if** field, enter the request condition you want inserted into a VCL if statement. For example, `! ( req.url ~ "^/(Content|Scripts)/" )`. See below for more examples of request conditions.

4. Click **Save and apply to**. The Responses area now displays the condition that must be met in order for your response to begin being used.



5. Click **Activate** to deploy your configuration changes.

Example request conditions

Respond only if URLs don't match a certain mask, in this case `/Content/*` or `/Scripts/*`:

```
! (req.url ~ "^/(Content|Scripts)/")
```

Respond only if URLs match `/secret/*` or are Microsoft Word or Excel documents (`*.doc` and `*.xls` file extensions):

```
! (req.url ~ "^/secret/" || req.url ~ "\.(xls|doc)$")
```

Ignore POST and PUT HTTP requests:

```
req.method == "POST" || req.method == "PUT"
```

Deny a spider or crawler using `user-agent` `"annoying_robot"`:

```
req.http.user-agent ~ "annoying_robot"
```

Prevent a specific IP from connecting, in this case the IP `225.0.0.1`:

```
client.ip == "225.0.0.1"
```

Use geographic variables to block traffic from a specific location (e.g., China):

```
client.geo.country_code == "CN"
```

Match the `client.ip` against a CIDR range, such as `240.24.0.0/16` (this requires first creating an ACL object in VCL):

```
client.ip ~ ipRangeObject
```

* * *

Developer guide: Best practices for VCL

/en/guides/developer-guide-best-practices-for-vcl

* * *

Developer guide: Clustering with VCL

/en/guides/developer-guide-clustering-with-vcl

* * *

Developer guide: Getting started with VCL

/en/guides/developer-guide-getting-started-with-vcl

* * *

Developer guide: Synthetic errors in VCL

/en/guides/developer-guide-synthetic-errors-in-vcl

* * *

Developer guide: Using VCL

/en/guides/developer-guide-using-vcl

* * *

Guide to VCL

/en/guides/guide-to-vcl

Fastly's Edge Cloud services use the Fastly Varnish Configuration Language (VCL), a scripting language used to configure and add logic to Varnish caches. Fastly VCL allows you to generate and compile changes to your Fastly services. These changes can be distributed to all Fastly caches worldwide and then loaded and activated without requiring maintenance windows or service downtime. Fastly VCL is generated automatically per your service configurations specified via the Fastly control panel.

VCL and what you can do with it

We allow you to create your own VCL files with specialized configurations. Your custom VCL files can be uploaded into Fastly caches and activated.

You can also mix and match custom VCL and Fastly VCL, using them together at the same time. You will never lose the options on the Fastly control panel when you use custom VCL, but keep in mind that custom VCL always takes precedence over any VCL generated by the control panel. Be mindful of where your custom VCL sits in the default VCL.

IMPORTANT

Personal data should not be incorporated into VCL. Our Compliance and Law FAQ describes in detail how Fastly handles personal data privacy.

Embedding inline C code in VCL

Currently, we don't provide embedded C access to our users. Fastly is a shared infrastructure. By allowing the use of inline C code, we could potentially give a single user the power to read, write to, or write from everything. As a result, our varnish process (i.e., files on disk, memory of the varnish user's processes) would become unprotected because inline C code opens the potential for users to do things like crash servers, steal data, or run a botnet.

We appreciate feedback from our customers. If you are interested in a feature that requires C code, contact support. Our engineering team looks forward to these kinds of challenges.

Where to learn more about VCL and Varnish

Fastly's Developer Hub provides a reference of Fastly VCL for programming custom edge logic on VCL services. You can also discover more about learning to build on the Fastly platform using VCL and the current best practices involved.

The official Varnish documentation is a good place to start when looking for online information. In addition, Varnish Software, who provides commercial support for Varnish, has written a free online book.

---

* * *

Isolating header values without regular expressions

/en/guides/isolating-header-values-without-regular-expressions

---

Fastly supports the ability to extract header subfield values without regular expressions in a human-readable way. *Headers subfields* are headers with a body syntax style similar to `value1=123value123; testValue=asdf_true; staff_user=true;` or `max-age=0, surrogate-control=3600` These headers include Cookie, Set-Cookie, Cache-Control, or a custom header. Fastly allows you to isolate these key values with the following syntax:

```
req.http.Header-Name:key-name
```

For example, if a `Cookie` request from a client was `value1=123value123; testValue=asdf_true; staff_user=true;`, you could isolate the `staff_user` value using this logic:

```
set req.http.Staff-User = req.http.Cookie:staff_user;
```

The same can be accomplished by using the subfield function:

```
set req.http.Staff-User = subfield(req.http.Cookie, "staff_user", " ;
```


You can add this logic using VCL Snippets or using a custom header.

> **WARNING**
>
> The subfield function as well as the `:` accessor cannot be used for `Set-Cookie` headers.

Using VCL Snippets

To execute this logic based on the value of `staff_user` within `req.http.Cookie` using a VCL Snippet, you would:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL Snippets**.
5. Click **Create Snippet**.



6. In the **Name** field, enter an appropriate name (e.g., `Staff User Cookie`).

7. From the **Type** controls, select **within subroutine**.

8. From the **Select subroutine** menu, select **recv (`vcl_recv`)**.

9. In the **VCL** field, add the following condition:

```
# in vcl_recv
if (req.http.Cookie:staff_user ~ "true") {
  # some logic goes here
  return(pass);
```


```
4  }
5
```

10. Click **Create** to create the snippet.

11. Click **Activate** to deploy your configuration changes.

Using a custom header

You can isolate the value of `staff_user` from `Cookie` to the header `req.http.staff_user` by creating a custom header with the following settings:



Fill out the **Create a header** fields as follows:

- In the **Name** field, enter `Staff User Header`.

- From the **Type** menu, select **Request**, and from the **Action** menu select **Set**.
- In the **Destination** field, enter `http.staff_user`.
- In the **Source** field, enter `req.http.Cookie:staff_user`.
- From the **Ignore if set** menu, select **No**.
- In the **Priority** field, enter `10`.

This will send the `staff_user` header in every inbound request.

> **NOTE**
>
> You can use the `Attach a condition` link to only create this header when it's needed. See our Using Conditions docs for more information.

---

* * *



Manipulating the cache key



/en/guides/manipulating-the-cache-key

Before you begin

If your origin uses special values (e.g., request headers) to select content for users or to otherwise direct requests to appropriate security domains, consider including those values in your cache key or Vary header. Doing so will prevent you from accidentally caching content across security domains and could prevent malicious attackers from poisoning your cache.

Redefining the cache key

> **WARNING**
>
> By default, Fastly uses the URL and the Host of a request (plus a special, internal Fastly variable for purging purposes) to create unique HTTP objects. Although Fastly allows you to explicitly set the cache key to define this more precisely, changing the default behavior risks the following:

1. If you add too much information to the cache key, you can significantly reduce your hit ratio.
2. If you make a mistake when explicitly setting the cache key, you can cause all requests to get the same object.
3. If you add anything to the hash, you will need to send a purge for each combination of the URL and value you add in order to purge that specific information from the cache.

To avoid these dangers, consider using the Vary header instead of following the instructions below.


Explicitly setting the cache key

You can set the cache key explicitly (including attaching conditions by adding a request setting via the Settings page in the service configuration controls and including a comma-separated list of cache keys. The values of the cache keys listed are combined to make a single hash, and each unique hash is considered a unique object.

For example, if you don't want the query string to be part of the cache key, but you don't want to change `req.url` so that the query string still ends up in your logs, you could use the following text for the hash keys:

```
req.url.path, req.http.host
```

In the web interface, the text would appear in the Cache keys field:



As a general rule, you should always have `req.url` as one of your cache keys or as part of one.

Purging adjustments when making additions to cache keys

Because purging works on individual hashes, additions to cache keys can complicate purging URLs. However, it can also be simplified.

For example, if you were to change your cache key to just `req.url` and not the default `req.url, req.http.host`, then purging `http://foo.example.com/file.html` would also purge `http://bar.example.com/file.html`. Keep in mind this is because they're actually the same object in the cache!

On the other hand, if you were to change your cache key to `req.url, req.http.host, req.http.Fastly-SSL`, you would have to purge `http://example.com/` and `https://example.com/` individually.

In the latter case, if you were to use the Vary header instead of changing the cache key, you could still have different content on the two URLs, yet purge them with a single purge. In this case you would add a new Cache Header, use `http.Vary` as the Destination, and use the following as the Source:

```
if(beresp.http.Vary, beresp.http.Vary ",", "") "Fastly-SSL"
```

Using a cookie as a cache key

You can use a cookie as a cache key or just check for the presence of a cookie set to a specific value by controlling its request conditions. Both methods are simple and shown in the steps below.


To use a cookie as a cache key

Using a cookie as a cache key looks complicated but it's actually quite simple. Let's say your cookie is called "MyCookie" and it looks like `mycookie=`.

Create new headers

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.

5. Click **Create header**.




6. Fill out the **Create a header** fields as follows:

   - In the **Name** field, enter `Set MyCookie Header Default`.
   - From the **Type** menu, select **Request**, and from the **Action** menu select **Set**.


- In the **Destination** field, enter `http.X-MyCookie`.
- In the **Source** field, enter `"0"` (with quotes).
- Leave the **Ignore if set** menu set to the default, **No**.
- In the **Priority** field, enter a number representing the order in which the header rule should execute. The default is set to `10` for new headers.

7. Click **Create**. The new header appears in the Headers area of the Content page.
8. Click **Create header** again and create a second new header by filling out the fields as follows:
   - In the **Name** field, enter `Set MyCookie Header from Cookie`.
   - From the **Type** menu, select **Request**, and from the **Action** menu select **Set**.
   - In the **Destination** field, enter `http.X-MyCookie`.
   - In the **Source** field, enter `req.http.cookie:mycookie`.
   - Leave the **Ignore if set** menu set to the default, **No**.
   - In the **Priority** field, enter a larger number than the priority of previous header you just created. For example, if you left the default priority set to `10`, enter `20`.
9. Click **Create**. The second header appears in the Headers area of the Content page.




Attach conditions to the new headers

1. Click **Attach a condition** next to the `Set MyCookie Header from Cookie` header.
2. Click **Create a new request condition**.




3. Fill out the fields of the **Create a new request condition** page as follows:
   - In the **Name** field, enter `Has MyCookie cookie`.
   - In the **Apply if** field, enter `req.http.cookie:mycookie`.


4. Click **Save and apply to**. The Headers area now displays the condition that must be met in order for your header to begin being used.



5. Click **Settings**.
6. Click **Create request setting**.
7. In the **Name** field, enter `Set Hash from Cookie`.
8. Click **Advanced options** at the bottom of the page.
9. In the **Cache keys** field, enter `req.url, req.http.host, req.http.X-MyCookie`
10. Click **Create**.
11. Click **Attach a condition** next to the new request.



12. From the **Select a condition** menu, select `Has MyCookie cookie`. The Request settings area now displays the condition that must be met in order for your request to begin being used.



13. Click **Activate** to deploy your configuration changes.

To check for the presence of a cookie set to a specific value

An alternative way if you're just checking for the presence of the cookie set to some specific value (e.g., 1):

1. Add a new Request setting where the Cache key field is set to `req.url, req.http.host, "Has mycookie"`.
2. Add a condition to that Request setting where the Apply if field contains `req.http.cookie:mycookie`.

---

* * *

Response Cookie handling

/en/guides/response-cookie-handling

The traditional way to read response cookies in VCL is to inspect either the `beresp.http.Set-Cookie` or the `resp.http.Set-Cookie` variables and then extract values using regular expressions. However this is not ideal since attempting to parse potentially complicated or quoted strings with regular expressions is brittle and prone to being tripped up by edge cases. It also doesn't allow for reading multiple headers with the same name such as when an origin sends multiple `Set-Cookie` headers. Because of these two reasons Fastly supports a method for extracting a named value out of `Set-Cookie` headers no matter how many there are.

To access a named value simply use the function with either `beresp` or `resp` depending on what part of the request you're in - so either

```
setcookie.get_value_by_name(beresp, "name")
```

or

```
setcookie.get_value_by_name(resp, "name")
```

as appropriate, replacing `"name"` with whatever the name of the value is. So for example, given this HTTP response from an origin:

```
HTTP/1.1 200 OK
Cache-Control: max-age=60
Content-Type: text/html; charset=utf-8
```

```
Content-Length: 80806
Accept-Ranges: bytes
Date: Tue, 11 Aug 2015 19:00:04 GMT
Age: 123
Connection: keep-alive
Set-Cookie: one=a; httponly; secure
Set-Cookie: two=b or not to b; httponly
```

then using the function like this:

```
set resp.http.X-One = setcookie.get_value_by_name(resp, "one");
set resp.http.X-Two = setcookie.get_value_by_name(resp, "two");
```

will set `resp.http.X-One` to be "a" and `resp.http.X-Two` to "b or not to b".

This logic can be used in uploaded custom VCL, as well as throughout the Fastly control panel. For example:

Create a header

Learn more about this section in our headers tutorial.

CONDITION This will happen all the time unless you attach a condition.

Name x-One header * Required

The name of your header, such as **My header**.

Type / Action Response Set

The type of header and the action performed on it.

Destination http.x-One * Required

The name of the header that will be affected by the selected action. For example: **http.Content-Type**, **http.Set-Cookie**, **http.Via**, **http.Location**, or **http.Access-Control-Allow-Origin**.

Source setcookie.get_value_by_name(resp, "name") * Required


New content for the header. Can be a static value (e.g., string or number) or a dynamic value (e.g., existing header or a GeoIP value). Remember to use quotes for string values.

Ignore if set No

If switched to **Yes**, the action will not be performed if the header in Destination exists.

Priority 10 * Required

The order in which the header rules execute within the condition. Lower numbers execute first.



* * *

Tracking your origin's name, IP, and port

/en/guides/tracking-your-origins-name-ip-and-port

Being able to track information related to your origin can be helpful in troubleshooting errors and making sure requests are processed as expected. Fastly provides three VCL variables that allow you to see and track origin information:

- `beresp.backend.name`
- `beresp.backend.port`
- `beresp.backend.ip`

You can create VCL Snippets that use these variables to capture information about an origin and then set up remote log streaming to save that information.

Retrieve the origin information

Create a regular VCL Snippet to retrieve the origin information:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL snippets**.
5. Click **Create snippet**.
6. Fill out the Create a VCL snippet fields as follows:

- In the **Name** field, enter an appropriate name (for example, `Retrieve-Origin-Information`).
- From the **Type** menu, select **within subroutine**.
- From the **Select subroutine** menu, select **fetch (`vcl_fetch`)**.
- In the **VCL** field, add the following VCL logic:

```
# save the variables for access in deliver
set beresp.http.Your-Backend-Name = beresp.backend.name;
set beresp.http.Your-Backend-IP-Port = beresp.backend.ip ":" be
```

7. Click **Create** to create the snippet.

Change the response header to a request header

Create another regular VCL Snippet that changes the response header to a request header before logging the information:

1. Click **VCL snippets**.
2. Click **Create snippet**.
3. Fill out the Create a VCL snippet fields as follows:
   - In the **Name** field, enter an appropriate name (for example, `Remove-Origin-Information`).
   - From the **Type** controls, select **within subroutine**.
   - From the **Select subroutine** menu, select **deliver (`vcl_deliver`)**.
   - In the **VCL** field, add the following VCL logic:

```
if (fastly_info.state ~ "(MISS|PASS)") {
   # only on a miss or pass
   # save the responses back to req.request because
   # request headers are not sent back to the client
   set req.http.Your-Backend-Name = resp.http.Your-Backend-N
   set req.http.Your-Backend-IP-Port = resp.http.Your-Backer
```

```
    }

# remove the identifying information from the response
unset resp.http.Your-Backend-Name;
unset resp.http.Your-Backend-IP-Port;

```

4. Click **Create** to create the snippet.

> **NOTE**
>
> If a response header like `beresp.http.Your-Backend-Name` exists in `vcl_fetch` when VCL is processed, then a corresponding response header `resp.http.Your-Backend-Name` will exist in `vcl_deliver` and will be logged by default. This means that response headers will be included in response output, exposing origin information (e.g., IP address, port number, or origin name) in the process. Fortunately, request headers are not passed back to the client, but their information remains accessible from `vcl_log`.

Set up remote log streaming

Once your snippets are created, you can set up remote log streaming for tracking purposes. Do this by adding `req.http.Header-Name` to the **Log format** field in the logging endpoint you configured in the remote log streaming guide. Using the example above, you would add `req.http.Your-Backend-Name` and `req.http.Your-Backend-IP-Port`. Once you've reviewed the changes you've made, click the **Activate** button to deploy these configuration changes for your service.

> **NOTE**
>
> When you configure remote log streaming to capture this information, remember the VCL is executed twice, once on the shield node and again on the edge node. This means that the first log (from the shield node) will have the origin's information and the second log (from the edge node) will have the shield's information.

* * *


	Understanding the different PASS action behaviors
🔗	/en/guides/understanding-the-different-pass-action-behaviors

---

Passing with a request setting and with a cache setting triggers very different behavior in Varnish. Within VCL, passing with a request setting is the same as `return(pass)` in `vcl_recv`. Passing with a cache setting is the same as `return(pass)` in `vcl_fetch`. If you are familiar with Varnish 3+, passing with a cache setting is equivalent to `return(hit_for_pass)`.

Using a request setting

Passing with a request setting translates within your generated VCL to `return(pass)` in `vcl_recv`. Varnish will not perform a lookup to see if an object is in cache and the response from the origin will not be cached.




Passing in this manner disables request collapsing. Normally simultaneous requests for the same object that result in cache misses will be collapsed down to a single request to the origin. While the first request is sent to the origin, the other requests for that object are queued until a response is received. When requests are passed in `vcl_recv`, they will all go to the origin separately without being collapsed.

Using a cache setting

Passing with a cache setting translates within your generated VCL to `return(pass)` in `vcl_fetch`. At this point in the flow of a request, Varnish has performed a lookup and determined that the object is not in cache. A request to the origin has been made; however, in `vcl_fetch` we have determined that the response is not cacheable. In Fastly's default

VCL, this can happen based on the presence of a `Set-Cookie` response header from the origin.



Passing in `vcl_fetch` is often not desirable because request collapsing is *not* disabled. This makes sense since Varnish is not aware in `vcl_recv` that the object is uncacheable. On the first request for an object that will be later passed in `vcl_fetch`, all other simultaneous cache misses will be queued. Once the response from the origin is received and Varnish has realized that the request should be passed, the queued requests are sent to the origin.

This creates a scenario where two users request an object at the same time, and one user must wait for the other before being served. If these requests were passed in `vcl_recv`, neither user would need to wait.

To get around this disadvantage, when a request is passed in `vcl_fetch`, Varnish creates what is called a hit-for-pass object. These objects have their own TTLs and while they exist, Varnish will pass any requests for them as if the pass had been triggered in `vcl_recv`. For this reason, it is important to set a TTL that makes sense for your case when you pass in `vcl_fetch`. All future requests for the object will be passed until the hit-for-pass object expires. Hit-for-pass objects can also be purged like any other object.

Even with this feature, there will be cases where simultaneous requests will be queued and users will wait. Whenever there is not a hit-for-pass object in cache, these requests will be treated as if they are normal cache misses and request collapsing will be enabled. Whenever possible it is best avoid relying on passing in `vcl_fetch`.

Using req.hash_always_miss and req.hash_ignore_busy

Setting `req.hash_always_miss` forces a request to miss whether it is in cache or not. This is different than passing in `vcl_recv` in that the response will be cached and request collapsing will not be disabled. Later on the request can still be passed in `vcl_fetch` if desired.

A second relevant variable is `req.hash_ignore_busy`. Setting this to true disables request collapsing so that each request is sent separately to origin. When `req.hash_ignore_busy` is enabled all responses will be cached and each response received from the origin will overwrite the last. Future requests for the object that are served from cache will receive the copy of the object from the last cache miss to complete. `req.hash_ignore_busy` is used mostly for avoiding deadlocks in complex multi-Varnish setups.

Setting both these variables can be useful to force requests to be sent separately to the origin while still caching the responses.

---

* * *



Uploading custom VCL



/en/guides/uploading-custom-vcl

Fastly allows you create your own Varnish Configuration Language (VCL) files with specialized configurations. By uploading custom VCL files, you can use custom VCL and Fastly VCL together at the same time. Any time you upload VCL files, you can preview the


VCL prior to activating a new version of your service. Keep in mind that your custom VCL always takes precedence over VCL generated by Fastly.

> IMPORTANT
>
> Personal data should not be incorporated into VCL. Our Compliance and Law FAQ describes in detail how Fastly handles personal data privacy.

Uploading a VCL file

Follow these instructions to upload a custom VCL file:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Custom VCL**.
5. Click **Upload a new VCL file**.



6. In the **Name** field, enter the name of the VCL file. For included files, this name must match the include statement in the main VCL file. See how to include additional VCL configurations for more information.
7. Click **Upload file** and select a file to upload.

> IMPORTANT


> Don't upload generated VCL that you've downloaded from the Fastly control panel. Instead, edit and then upload a copy of Fastly's VCL boilerplate to avoid errors.

8. Click **Create**. The VCL file appears in the Varnish Configurations area.
9. Click **Activate** to deploy your configuration changes.

Editing a VCL file

To edit an existing VCL file, follow these instructions:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Custom VCL**.
5. In the **Varnish Configurations** area, click the VCL file you want to edit.




6. *(Optional)* In the **Name** field, enter a new name for the VCL file.
7. Click **Download** to download the appropriate file.

8. Make the necessary changes to your file and save them.
9. Click **Replace file** and select the file you updated. The selected file replaces the current VCL file and the file name appears next to the button.
10. Click **Update** to update the VCL file in the Fastly application.
11. Click **Activate** to deploy your configuration changes.

Including additional VCL configurations

To make your full VCL configuration easier to maintain, you can split it up into multiple files that are accessed by a main VCL file. This allows you to separate out chunks of logic (for example, logic that has a specific purpose or that might change frequently) into as many separate files as makes sense.

1. Start by isolating a portion of VCL and placing it in a separate file. The name of the file doesn't matter, nor does the file extension. A `foo.vcl` file will work just as well as a `bar.txt` file.
2. Upload the file to include it in your Varnish configurations and give it a unique name when you fill out the **Name** field at the time of upload (for example, you could call it `Included VCL`). The uploaded file will appear in the Varnish Configurations area along with your main VCL file.



3. Enter the name of the included VCL file on a separate line in the main VCL configuration file. For example, your **Included VCL** file would get added to the main VCL file in a single line like this:

```
include "Included VCL";
```

4. Continue uploading VCL files and then including them in your main VCL using the syntax `include "<VCL FILE>";` where `<VCL FILE>` exactly matches the name you


entered in the **Name** field.

> **TIP**
>
> Our guide to manually creating access control lists demonstrates a common example of using included VCL.

Previewing VCL before activation

Follow these instructions to preview VCL prior to activating a service version:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Show VCL**.



The VCL preview page appears.

---

* * *

	Using dynamic VCL Snippets
🔗	/en/guides/using-dynamic-vcl-snippets

Dynamic VCL Snippets are one of two types of snippets that allow you to insert small sections of VCL logic into your service configuration without requiring custom VCL (though you can still include snippets in custom VCL when necessary).

You can only create dynamic snippets via the API. Because they are versionless objects (much like dictionaries or ACLs at the edge), dynamic snippets can be modified independently from changes to your Fastly service. This means you can modify snippet

code rapidly without deploying a service version that may not be ready for production. Changes immediately impact all service versions, including the active one.

Creating and using a dynamic VCL Snippet

Using the curl command line tool, make the following API call in a terminal application:

```
$ curl -X POST -s https://api.fastly.com/service/<Service ID>/versi<E
```

Fastly returns a JSON response that looks like this:

```
{
 "service_id": "<Service Id>",
 "version": "<Editable Version>",
 "name": "my_dynamic_snippet_name",
 "type": "recv",
 "priority": 100,
 "dynamic": 1,
 "content": null,
 "id": "decafbad12345",
 "created_at": "2016-09-09T20:34:51+00:00",
 "updated_at": "2016-09-09T20:34:51+00:00",
 "deleted_at": null
}
```

NOTE

The returned JSON includes `"content": null`. This happens because the content is stored in a separate, unversioned object.


Viewing dynamic VCL Snippets in the Fastly control panel

You can view a list of dynamic VCL snippets. You can also view just the source of a specific snippet or a specific snippet's location in generated VCL.

Viewing a list of dynamic VCL Snippets

To view the entire list of a service's dynamic VCL Snippets directly in the Fastly control panel:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate VCL service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL Snippets**. The VCL Snippets page appears listing all dynamic VCL Snippets for your service in the Dynamic snippets area.



Viewing the source of a specific snippet

You can view just the source of a specific snippet:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate VCL service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL Snippets**.

5. Click **View Source** to the right of the name of the snippet.

Viewing the location of a specific snippet in generated VCL

You can view a specific snippet's location in generated VCL:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate VCL service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL Snippets**.
5. Click **Show in Generated VCL** to the right of the name of the snippet. The Generated VCL window appears.

Fetching a list of all dynamic VCL Snippets

To list all dynamic VCL Snippets attached to a service, make the following API call in a terminal application:

```
$ curl -X GET -s https://api.fastly.com/service/<Service ID>/versio Ve
```

Fetching an individual dynamic VCL Snippet

To fetch an individual snippet, make the following API call in a terminal application:

```
$ curl -X GET -s https://api.fastly.com/service/<Service ID>/snippe Sn
```

Unlike fetching regular VCL Snippets, you do not include the version in the URL and you must use the ID returned when the snippet was created, not the name.

Updating an existing dynamic VCL Snippet

To update an individual snippet, make the following API call in a terminal application:

```
$ curl -X PUT -s https://api.fastly.com/service/<Service ID>/snippet Sn
```

Deleting an existing dynamic VCL Snippet

To delete an individual snippet, make the following API call in a terminal application:

```
$ curl -X DELETE -s https://api.fastly.com/service/<Service ID>/vers n/
```

Including dynamic snippets in custom VCL

By specifying a location of `none` for the `type` parameter, snippets will not be rendered in VCL. This allows you to include snippets in custom VCL using the following syntax:

```
include "snippet::<snippet name>"
```

The same VCL Snippet can be included in custom VCL in as many places as needed.

Example use: blocking site scrapers

Say you wanted to implement some pattern matching against incoming requests to block someone trying to scrape your site. Say also that you've developed a system that looks at all incoming requests and generates a set of rules that can identify scrapers using a combination of the incoming IP address, the browser, and the URL they're trying to fetch. Finally, say that the system updates the rules every 20 minutes.

If, during system updates, your colleagues are also making changes to the rest of your Fastly configuration, you probably don't want the system to automatically deploy the latest version of the service since it might be untested. Instead you could generate the rules as a Dynamic VCL Snippet. Whenever the snippet is updated, all other logic remains the same as the currently deployed version and only your rules are modified.

* * *

Using regular VCL Snippets

🔗 /en/guides/using-regular-vcl-snippets

Regular VCL Snippets are one of two types of snippets that allow you to insert small sections of VCL logic into your service configuration without requiring custom VCL (though you can still include snippets in custom VCL when necessary).

Unlike dynamic snippets, regular snippets can be created via the Fastly control panel or via the API. They are considered *versioned* objects. They belong to a specific service and any modifications you make to the snippet are locked and deployed when you deploy a new version of that service. We continue to clone them and deploy them with a service until you specifically delete them.


Creating a regular VCL Snippet

You can create regular VCL Snippets via the Fastly control panel or via the API.

Via the Fastly control panel

To create a regular VCL Snippet via the Fastly control panel:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL Snippets**.
5. Click **Create Snippet**.



6. In the **Name** field, enter an appropriate name (for example, `Example Snippet`).
7. Using the **Type** controls, select the location in which the snippet should be placed as follows:
   - Select `init` to insert it above all subroutines in your VCL.
   - Select `within subroutine` to insert it within a specific subroutine and then select the specific subroutine from the **Select subroutine** menu.
   - Select `none (advanced)` to insert it manually. See Including regular snippets in custom VCL for the additional manual insertion requirements if you select this option.

8. In the **VCL** field, enter the snippet of VCL logic to be inserted for your service version.
9. Click **Advanced options** at the bottom of the page.
10. *(Optional)* In the **Priority** field, enter the order in which you want the snippet to execute. Lower numbers execute first.
11. Click **Create** to create the snippet.

Via the API

To create a regular VCL Snippet via the API, make the following API call using the curl command line tool in a terminal application:

```
$ curl -X POST -s https://api.fastly.com/service/<Service ID>/versi<E
```

Fastly returns a JSON response that looks like this:

```
{
 "service_id": "<Service Id>",
 "version": "<Editable Version>",
 "name": "my_regular_snippet",
 "type": "recv",
 "content": "if ( req.url ) {\n set req.http.my-snippet-test-header
 "priority": 100,
 "dynamic": 0,
 "id": "56789exampleid",
 "created_at": "2016-09-09T20:34:51+00:00",
 "updated_at": "2016-09-09T20:34:51+00:00",
 "deleted_at": null
}
```

NOTE

When regular VCL snippets get created, an `id` field will be returned that isn't used. The field only applies to dynamic VCL Snippets. In addition, the returned JSON

includes a populated `content` field because the snippet content is stored in a versioned object.


Viewing regular VCL Snippets in the Fastly control panel

You can view a list of regular VCL snippets. You can also view just the source of a specific snippet or a specific snippet's location in generated VCL.

Viewing a list of regular VCL Snippets

To view the entire list of a service's regular VCL Snippets directly in the Fastly control panel:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL Snippets**. The VCL Snippets page appears listing all available VCL snippets for your service.



Viewing the source of a specific snippet

You can view just the source of a specific snippet:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.

3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL Snippets**.
5. Click **View Source** to the right of the name of the snippet. A view source window appears.

Viewing the location of a specific snippet in generated VCL

You can view a specific snippet's location in generated VCL:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL Snippets**.
5. Click **Show in Generated VCL** to the right of the name of the snippet. The Generated VCL window appears.

Fetching regular VCL Snippets via the API

You can fetch regular VCL Snippets for a particular service via the API either singly or all at once.

Fetching an individual regular VCL Snippet

To fetch an individual snippet, make the following API call in a terminal application:

```
$ curl -X GET -s https://api.fastly.com/service/<Service ID>/versio
```

Unlike fetching dynamic VCL Snippets you include the version in the URL and you must use the name of the snippet, not the ID.

Fetching a list of regular VCL Snippets

To list all regular VCL Snippets attached to a service, make the following API call in a terminal application:

```
$ curl -X GET -s https://api.fastly.com/service/<Service ID>/versio
```


Updating an existing regular VCL Snippet

You can update existing regular VCL Snippets via the Fastly control panel or via the API.


Via the Fastly control panel

To update an individual snippet via the Fastly control panel:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL Snippets**.
5. Click the pencil next to the name of the snippet to be updated.



The Edit snippet page appears.



6. Update the snippet's settings or VCL as appropriate.

7. Click **Update** to save your changes.

Via the API

To update an individual snippet via the API, make the following API call in a terminal application:


```
$ curl -X PUT -s https://api.fastly.com/service/<Service ID>/versio
```

Deleting an existing regular VCL Snippet

You can update existing regular VCL Snippets via the Fastly control panel or via the API.

Via the Fastly control panel

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL Snippets**.
5. Click the trash to the right of the name of the snippet to be updated.



6. Click **Confirm and Delete**.

Via the API

To delete an individual snippet via the API, make the following API call in a terminal application:

```
$ curl -X DELETE -s https://api.fastly.com/service/<Service ID>/vers
```

Including regular snippets in custom VCL

Snippets will not be rendered in VCL if you select `none (advanced)` for the snippet type in the Fastly control panel or specify a location of `none` for the `type` parameter in the API. This allows you to manually include snippets in custom VCL using the following syntax:

```
include "snippet::<snippet name>"
```

The same VCL Snippet can be included in custom VCL in as many places as needed.

Example use: location-based redirection

Say that you work at a large content publisher and you want to redirect users to different editions of your publication depending on which country their request comes from. Say also that you want the ability to override the edition you deliver to them based on a cookie.

Using regular VCL snippets, you could add a new object with the relevant VCL as follows:

```
if (req.http.Cookie:edition == "US" || client.geo.country_code "
  set req.http.Edition = "US";
  set req.backend = F_US;
} elseif (req.http.Cookie:edition == "Europe" || server.region ~ "^
  set req.http.Edition = "EU";
  set req.backend = F_European;
} else {
  set req.http.Edition = "INT";
  set req.backend = F_International;
}

```

This would create an Edition header in VCL, but allow you to override it by setting a condition. You would add the Edition header into Vary and then add a false condition (e.g., `!reg.url`) to your other backends to ensure the correct edition of your publication gets delivered (Remember: VCL Snippets get added to VCL before backends are set.)

---

* * *

📄	**VCL regular expression cheat sheet**
🔗	/en/guides/vcl-regular-expression-cheat-sheet

Fastly VCL uses a subset of Perl Compatible Regular Expression (PCRE) syntax. This is case sensitive and forward slashes don't need to be escaped. To disable case sensitivity, add `(?i)` to the start of your expression.

Basic matching

```
req.url == "/phrase"
```

Matches only if `req.url` is exactly `/phrase`.

```
req.url ~ "phrase"
```

Matches `phrase` anywhere.

Matching at the beginning or end of a string

```
req.http.host ~ "^www"
```

Matches if `req.http.host` starts with `www`.

```
req.url ~ "\.jpg$"
```

Matches if `req.url` ends with `.jpg`.

Multiple matches

```
req.url ~ "\.(png|jpg|css|js)$"
```

Matches if `req.url` ends with either `.png`, `.jpg`, `.css`, or `.js`.

```
req.url ~ "\.php(\?.*)?$"
```

Matches if `req.url` ends with `.php`, `.php?foo=bar` or `.php?`, but not `.phpa`.

> **NOTE**
>
> You can also use `req.url.ext` to find the file extension specified in a URL. For example, in the request `www.example.com/1/hello.gif?foo=bar`, `req.url.ext` will contain `gif`.

```
req.url ~ "\.[abc]server$"
```

Matches if `req.url` ends with `.aserver`, `.bserver` or `.cserver`.

Matching wildcards

```
req.url ~ "jp.g$"
```

Matches if `req.url` ends with `jpeg`, `jpag`, and `jp0g`, but doesn't match if `req.url` ends with `jpg`. It also matches if any other character is between the `jp` and the `g`.

```
req.url ~ "jp.*g$"
```

Matches `jp` followed by 0 or more random characters ending with the letter `g` (`jpeg`, `jpg`, and `jpeeeeg` all match).

Capturing matches

```
set req.http.Foo = "abbbccccc";
if (req.http.Foo ~ "^(a+)(b+)(c+)") {
  set resp.http.match0 = re.group.0; # now equals 'abbbccccc'
  set resp.http.match1 = re.group.1; # now equals 'a'
  set resp.http.match2 = re.group.2; # now equals 'bbb'
  set resp.http.match3 = re.group.3; # now equals 'ccccc'
}

```

The `re.group.[0-9]` objects allow you to capture matches. The `re.group.0` object evaluates to the entire matched string even if no capture groups have been supplied. You can use these objects to replace this example:

```
if (req.url ~ "(?i)\?.*some_query_arg=([^&]*)") {
  set req.http.Thing-I-Want = regsub(req.url, "(?i)\?.*some_query_a
}
```

You can use `re.group` to greatly simplify the previous example:

```
if (req.url ~ "(?i)\?.*some_query_arg=([^&]*)") {
  set req.http.Thing-I-Want = re.group.1;
}
```

You could even get really fancy and do something like this:

```
set req.http.Thing-I-Want = if(req.url ~ "(?i)\?.*some_query_arg=([ *)
```

Replacing content

```
set req.http.host = regsub(req.http.host, "^www\.","");
```

Removes a leading `www.` from the host, if present.

```
set req.http.api-test = regsub(req.http.host, "^www\.","api.");
```

Sets the `api-test` header to contain the host-header, but replaces a leading `www.` with `api.`:

```
Host: www.example.com ->
Host: www.example.com
api-test: api.example.com
Host: example.com ->
Host: example.com
```

```
api-test: example.com

```

```
set req.url = regsuball(req.url, "/+", "/");
```

Changes all occurrences of multiple slashes in the URL to a single slash. For example, `//docs///intro.html` will be transformed to `/docs/intro.html`.

---

* * *

Category: Dictionaries

These articles describe how to move rapid key/value pair decision logic to the edge using dictionaries.

About dictionaries

/en/guides/about-dictionaries

Dictionaries are a type of container that allow you to store data as key-value pairs that can be used in a service without being attached to a single version.

Using dictionaries, you can turn frequently repeated statements like this:

```
if (something == "value1") {
  set other = "result1";
} else if (something == "value2") {
  set other = "result2";
}

```

into a single function that acts as constant, like this:

```
table things {
  "value1": "result1",
  "value2": "result2",
  ...
}

set other = table.lookup(things, something);

```

This allows you to easily make changes to these statements without it being tied to a specific version.

When dictionaries might be useful

- Content sharing and social media outlets updating large referer block lists
- Mobile advertisers validating a key to prevent cache-bust guessing
- Customers authenticating valid user keys at the edge (see private dictionaries)
- Global publishers redirecting users to a specific country site based on geo-location
- Image providers performing token checks for certain objects
- Advertising technology companies blocking bad actors at edge
- Customers deploying control panel versions with simple value change via API

How dictionaries work

Dictionaries are made up of dictionary containers and the dictionary items within them. Once you attach a dictionary container to a version of your service and that service is activated, the data in it becomes *versionless*. This means you can add to and update the data a dictionary contains at any time after it is created, without ever incrementing a service's version. Changes immediately impact all service versions, including the active one.

For example, say you have a referer block list that changes frequently and you want to associate it with a service. Any time that service's configuration changes, especially if the configuration rolls back to a previous version, you would want the block-listed referer

domains to continue to remain with the service configuration instead of being removed. Dictionaries would help you do this.

How to create and use dictionaries

To create a dictionary and use it within your service, start by creating an empty dictionary container and then add its entries in a working version of a service that's unlocked and not yet activated. You can create dictionaries:

- via the Dictionaries page.
- via VCL snippets.
- via the Fastly API.

> TIP
>
> You can create a private dictionary to store dictionary items that can't be listed or read via the control panel or the API.

Limitations and considerations

When creating dictionaries, keep the following things in mind:

- **Dictionaries created with custom VCL cannot be manipulated using the API or the Dictionaries page.** If you create a dictionary container using custom VCL, that dictionary must always be manipulated via custom VCL. Dictionaries uploaded via custom VCL aren't versionless.
- **Dictionary containers, item keys, and their values have specific limits.** Dictionary containers are limited to 1000 items. Dictionary item keys are limited to 255 characters and their values are limited to 8000 characters. If you find your dictionaries approaching these resource limits, contact support. We may be able to help you figure out more efficient ways to do things.
- **Dictionary item keys are case sensitive.** The names of dictionary items are case sensitive. When designing your dictionaries, be sure to take this into account.
- **The contents of dictionaries are stored as VCL.** Personal data should not be incorporated into VCL. Our Compliance and Law FAQ describes in detail how Fastly handles personal data privacy.

When making changes to dictionaries, keep the following things in mind:

- **When you delete a dictionary container, you'll only delete it from the service version you're editing.** Dictionary containers are tied to versions and can be cloned and reverted. When using dictionaries, we want you to be able to do things like delete a dictionary container from a current version of your service in order to roll back your configuration to a previous version using as few steps as possible.
- **When you delete a dictionary container, we don't delete the dictionary items inside it.** The dictionary items in a dictionary container are versionless. When you change service versions, we want you to still be able to access the data.
- **Dictionary item deletions are permanent.** Because we don't store data, if you delete a dictionary item, the entry is gone forever from all service versions.
- **Event logs don't exist for dictionary changes.** If you add, update, or remove a dictionary item, there will be no record of it. The only record of a change will exist when you compare service versions to view the point at which the dictionary container was associated with the service version in the first place.

IMPORTANT

Personal information, secrets, or sensitive data should not be included in dictionaries or incorporated into VCL. In addition, we do not maintain version histories of your dictionaries. Our Compliance and Law FAQ describes in detail how Fastly handles personal data privacy.

---

* * *

Working with dictionaries

/en/guides/working-with-dictionaries

Dictionaries are a type of container that allow you to store data as key-value pairs that can be used in a service without being attached to a single version. Dictionaries are made up of dictionary containers and dictionary items. You use dictionary items to create and store the key-value pairs, which are then added to a dictionary container. The dictionary container is attached to a service version but can be updated at any time after it is created, without ever incrementing a service's version.

You can work with dictionaries using the Dictionaries page, custom VCL snippets, or Fastly API. You can also create private dictionaries.

Before you begin

Before working with dictionaries, be sure to review our About dictionaries guide to familiarize yourself with how dictionaries work, common use cases, and limitations to using dictionaries.

Working with dictionaries via the Dictionaries page

You can create and interact with dictionaries using the Dictionaries page.

Viewing dictionaries created using the Dictionaries page

To view a dictionary via the Dictionaries page, navigate to the dictionary management area of your service:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Dictionaries** under **Data**. Existing dictionaries, if any, associated with the currently selected service version appear.

From the Dictionaries page, you can use the search bar to filter the list of dictionaries. On any dictionary card, use the search bar to filter for keys or values within the dictionary.

> NOTE
>
> Remember that dictionary containers are versioned. If you don't see an dictionary attached to your service, check the service version to make sure you're looking at the right one.

Creating a dictionary via the Dictionaries page

Creating a dictionary via the Dictionaries page requires you to create a dictionary container and then create the items that will exist in it.

Creating a dictionary container


Start by creating a dictionary container using the following steps:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Dictionaries** under **Data**.
5. Click **Create a dictionary**.
6. In the **Name of dictionary** field, enter a descriptive name for the dictionary (e.g., `Example Dictionary`).
7. Click **Add**.
8. Click **Activate** to deploy your configuration changes to the service version you're editing.

Creating a dictionary item

Once you've created a dictionary container, add items into it:


1. Click **Add item**.
2. In the **Key** field, enter the unique identifier for some item of data (e.g., `example.com`).
3. In the **Value** field, enter the value associated with the unique identifier (e.g., `yes`).
4. Click **Add**. The key-value pair appears in the dictionary container. This addition will become effective immediately. Changes immediately impact all service versions, including the active one.



Using a dictionary

Once you've created a dictionary, you can start using it. To use a dictionary, you'll need to create and add a header. Follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click **Create header**.



6. Fill out the **Create a header** fields as follows:


   - In the **Name** field, enter the name of your header rule (for example, `Redirect lookup`).
   - From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.

- In the **Destination** field, enter the name of the header affected by the selected action (e.g., `url`).
- In the **Source** field, enter where the content for the header comes from (e.g., `table.lookup(redirects, req.url)`).
- From the **Ignore if set** menu, select **No**
- Leave the **Priority** field as is.

7. Click **Create** to create the header. A new header appears on the Content page.

Once you've created a header, you can create a condition to specify when to use the dictionary:

1. Click **Attach a condition** next to new header you just created.
2. Click **Create a new request condition**.



3. In the **Name** field, enter a name for your condition (e.g., `My dictionary condition`)
4. In the **Apply if** field, enter a condition (e.g., `table.lookup(redirects, req.url)`)
5. Click **Save and apply to**.
6. Click **Activate** to deploy your configuration changes.

Editing a dictionary container via the Dictionaries page

You can edit the name of a dictionary container that was created via the Dictionaries page in any unlocked service version:

1. Find a dictionary associated with an unlocked version of your service.
2. Click the pencil next to the dictionary container name.
3. Change the name, then click **Save**.

Editing a dictionary item via the Dictionaries page

You can edit the dictionary items within a container at any time. To edit the key-value pair in a dictionary container that was created via the Dictionaries page:

1. Find any dictionary associated with your service in which the key-value pairs appear. Because dictionary items are versionless, the service version you choose doesn't matter. Choose the one that makes the most sense to you.
2. Hover your cursor over a dictionary item, then click the pencil that appears.
3. Edit the key or value as necessary.
4. Click **Save**. The changes you make will be immediately applied to your configuration. If your dictionary container has already been associated with a deployed service version, those changes will happen live. Changes immediately impact all service versions, including the active one.

Deleting a dictionary via the Dictionaries page

Keeping in mind their limitations, dictionary containers and the items within them can be deleted via the Dictionaries page.

Deleting a dictionary container

You can delete a dictionary container that was created via the Dictionaries page in any unlocked service version:

1. Find a dictionary associated with an unlocked version of your service.
2. Click the trash in the top right corner of the dictionary.
3. Click **Confirm and delete**.
4. Click **Activate** to deploy your configuration changes to the service version you're editing.

Deleting a dictionary entry

You can delete the dictionary entries within a container at any time.

> **WARNING**
>
> Dictionary entry deletions are permanent and immediate. They cannot be recovered. Deleting a dictionary entry immediately impacts all service versions associated with the dictionary container holding the deleted entries, including the active service version.

To delete a key-value pair included in a dictionary container that was created via the Dictionaries page:

1. Find any dictionary associated with your service in which the key-value pairs appear. Because dictionary items are versionless, the service version you choose doesn't matter. Choose the one that makes the most sense to you.
2. Hover your cursor over a dictionary item, then click the trash that appears.
3. Click **Confirm and delete**.

Working with dictionaries using VCL snippets

You can create and interact with dictionaries using custom VCL snippets. Dictionaries created with custom VCL cannot be manipulated using the API or the Dictionaries page. If you create a dictionary container using custom VCL, that dictionary must always be manipulated via custom VCL. Dictionaries uploaded via custom VCL aren't versionless.

Viewing dictionaries created by VCL snippets


To view a dictionary under the VCL Snippets link, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL Snippets**.
5. To view the contents of the dictionary, click **View source**.

Creating a dictionary using VCL snippets

To create a dictionary using VCL snippets, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL snippets**.
5. Click **Create snippet**.



6. In the **Name** field, enter an appropriate name (e.g., `Example Dictionary`).
7. From the **Type (placement of the snippet)**, select **init**.
8. In the **VCL** field, create a table and add key-value pairs. For example, if you want to create a table that redirects a URL to another path:

```
table redirects {
  "/source1": "/dest1",
  "/source2": "/dest2"
```

```
}
```

where the table is a set of key-value pairs that you can reference in your code. You can replace the contents of this table with different key-value pairs.


9. Click **Create** to create the snippet.

Using a dictionary with VCL snippets

Once you've created a dictionary, you can start using it.

To start using your dictionary with VCL Snippets, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL snippets**.
5. Click **Create snippet**.



6. Fill out the Create a VCL snippet fields as follows:

   - In the **Name** field, enter an appropriate name (e.g., `URL redirect`).
   - From the **Type (placement of the snippet)** controls, select **within subroutine**.
   - From the **Select subroutine** menu, select **recv (`vcl_recv`)**.
   - In the **VCL** field, add a condition to use the table you created in Creating a dictionary using VCL Snippets. For example, if you need to rewrite your URL

destination, you could use:

```
if (table.lookup(redirects, req.url)) {
   set req.url = table.lookup(redirects, req.url);
}
```

where `table.lookup` checks the dictionary for the contents you want. The first parameter is the table being looked in and the second parameter is the key you're looking for. If the key exactly matches the second parameter, that value is returned. Be aware that regex doesn't work with a dictionary lookup.

7. Click **Create** to create the snippet.
8. Click **Activate** to deploy your configuration changes.

Editing a dictionary using VCL snippets

You can edit the dictionary name and the condition that was created using VCL Snippets in any unlocked service version:

1. Find a dictionary associated with an unlocked version of your service.
2. Click the pencil next to the dictionary. You can now make changes to the name and the condition.
3. Click **Update** once you're finished with your changes.
4. Click **Activate** to activate the version you made the edits in and view the changes in your VCL.

Deleting a dictionary using VCL snippets

You can delete a dictionary using VCL Snippets by following the steps below. Keep in mind the limitations involved when deleting a dictionary.

1. Find a dictionary associated with an unlocked version of your service.
2. Click the trash on the top right corner of the snippet
3. Click **Confirm and delete**.

4. Click **Activate** to deploy your configuration changes to the service version you're editing.

Private dictionaries

Private dictionaries store dictionary items that can't be listed or read via the Fastly control panel or the API.

Limitations and considerations

When creating private dictionaries, keep the following things in mind:

- You can create, read, update, and delete a private dictionary. Private dictionaries can only be created via the API.
- You cannot update the `write_only` attribute of a dictionary after it has been created.
- You can create, update, and delete items that belong to a private dictionary. After you've activated a service version, you can only update the values of existing private dictionary items via API. You can add new items to a private dictionary via the Fastly control panel or the API.
- You cannot view items that belong to a private dictionary via the API. After you've activated a service version, you cannot use the Fastly control panel to view items that belong to a private dictionary.
- Depending on how your service is configured, data stored in private dictionaries can be sent in headers and to log streaming endpoints.

> **WARNING**
>
> To edit or delete dictionary items in a private dictionary, you'll need to remember the keys of the dictionary items.

Creating a private dictionary container

To use a private dictionary container, start by creating an empty one within an unlocked version of a service.

Before a private dictionary can be manipulated, its private dictionary container must be associated with at least one service version that is not locked and not active so that the service becomes aware of the private dictionary's existence.

For example, if you were creating a `my_example_dictionary` private dictionary via the API, you would make an API call by running this command:

```
$ curl -X POST -H 'Fastly-Key: FASTLY_API_TOKEN' -d 'name=my_exampl
```

which would return:

```
{
  "created_at": "2017-05-03T16:11:41+00:00",
  "deleted_at": null,
  "id": "<dictionary_id>",
  "name": "my_example_dictionary",
  "service_id": "<service_id>",
  "updated_at": "2017-05-03T16:11:41+00:00",
  "version": <version_number>,
  "write_only": true
}
```

You can start adding dictionary items after you've created the dictionary. Don't forget to activate the service when you're finished.

Viewing private dictionaries in VCL

The contents of private dictionaries are hidden in VCL. The private dictionary's metadata is displayed, as shown below:

```
table my_example_dictionary {
     # REDACTED dictionary content
     # last_updated: 2017-10-16 20:44:43
     # item_count: 2
     # digest: 8f92141234567890da30ba9cea7d98ef614
 }
```

What's next

Explore custom VCL examples for using dictionaries on Developer Hub.

IMPORTANT

Personal information, secrets, or sensitive data should not be included in dictionaries or incorporated into VCL. In addition, we do not maintain version histories of your dictionaries. Our Compliance and Law FAQ describes in detail how Fastly handles personal data privacy.

* * *

Category: Domains and origins

These articles describe configuration settings and changes you can make to your domains and origins when setting up Fastly services.

Automatic load balancing

/en/guides/automatic-load-balancing

This guide describes how to automatically load balance between two or more origin servers. Load balancing distributes requests across multiple servers to optimize resource use and avoid overloading any single resource.

Before you begin

Before you configure load balancing, keep in mind the following:

- To prevent errors when shielding is enabled, all backends in the automatic load balancing group must use the same shielding location.
- Conditions on your origin server can directly change how automatic load balancing behaves. Be sure to review conditions behavior to ensure automatic load balancing works properly.

- Many customers configure failover at the same time they configure load balancing functionality. Our guide on configuring failover can show you how.

Enabling load balancing

To enable load balancing across two or more origin servers, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Origins**.
5. Click the name of the Host you want to edit.
6. From the **Auto load balance** menu, select **Yes**.
7. In the **Weight** field, enter the percentage of the total traffic to send to the origin server.

> TIP
>
> When you specify a whole number in the **Weight** field, you specify the percentage of the total traffic to send to a specific origin server. Each origin server receives the percentage (/) of the total traffic equal to the number you specify. For example, if you have two origin servers, A and B, setting the weight to 50 on both splits the traffic between them equally. Each origin server receives 50 percent of your total traffic. If you increase the weight on origin server A to 55 and decrease the weight on origin server B to 45, the percentage of traffic changes to 55 percent and 45 percent respectively.

8. Click **Update**.
9. Repeat steps 5, 6, 7, and 8 for each origin server you want to include in the automatic load balancing group.

> NOTE
>
> Each Fastly service can be configured with up to five origin servers. Contact sales@fastly.com to enable more than five origin servers per service in your account.

10. Click **Activate** to deploy your configuration changes.

Using conditions with load balancing

You can set conditions on origin servers to change how load balancing works. The load balancing autodirector groups servers together based on like conditions, giving you the flexibility to effectively create subsets of the autodirector by assigning a condition to one group of origins and another condition to another set of origins. If each group of origin servers has a different condition that affects load balancing, the auto load function will not randomly load balance between the different servers.

What's next

For more advanced load balancing scenarios, refer to our load balancing documentation.


---

* * *

📄	**Changing connection timeouts to your origin**
🔗	/en/guides/changing-connection-timeouts-to-your-origin

Connection timeouts to your origin server control how long Fastly will wait for a response from your origin server before exiting with an error. Changing the connection timeout is a good way to start troubleshooting 503 backend read errors. Follow the steps below to change the connection timeouts to your origin server:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Origins**.
5. Click the name of the Host that you want to edit.
6. Click **Advanced options**.



7. Type the new timeout in the appropriate field of the **Timeouts** section.
8. Click **Update**.

---

* * *

Changing origins based on user location

/en/guides/changing-origins-based-on-user-location

Fastly allows you to change origin servers based on the user's geographic location. This is useful when you need to serve different content to users who are in different locations. For example, you could change origin servers to serve a restricted version of your website to users in a different country.


Using the Fastly control panel

You can use the Fastly control panel to create the headers and the condition.

Creating the header for the default origin server

First, create a header for the default origin server to serve content to the majority of users. Follow these instructions to create the header:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click **Create header**.



6. Fill out the **Create a header** fields as follows:

   - In the **Name** field, enter the name of your header rule (for example, `Set default origin`).


- From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
- In the **Destination** field, enter `backend`.
- In the **Source** field, enter the name of the origin server you want to serve content to the majority of users (here it's `F_global`). Preview the VCL to find the name of the origin server.
- From the **Ignore if set** menu, select **No**.
- In the **Priority** field, enter `10`.

7. Click **Create**.

Creating the header for the restricted origin server

Now, create a header for the restricted origin server to serve content to the users residing in the countries specified in the condition. Follow these instructions to create the header:

1. Click **Content**.
2. Click **Create header**.



3. Fill out the **Create a header** fields as follows:

    - In the **Name** field, enter the name of your header rule (for example, `Set restricted origin`).


- From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
- In the **Destination** field, enter `backend`.
- In the **Source** field, enter the name of the restricted origin server you want to serve content to the users residing in the countries specified in the condition (here it's `F_restricted_content`). Preview the VCL to find the name of the origin server.
- From the **Ignore if set** menu, select **No**.
- In the **Priority** field, enter `11`.

4. Click **Create**.

Creating a condition for the restricted origin header

Finally, create a condition for the restricted origin header. The condition checks the geolocation header. If the user's geolocation matches a location specified in the condition, Fastly uses the restricted origin server. Follow these instructions to create the condition:

1. Click **Content**.
2. In the Headers section, click **Attach a condition** next to the **Set restricted origin** header.



3. Fill out the **Create a new request condition** fields as follows:

    - In the **Name** field, enter a descriptive name for the new condition (for example, `From Restricted Location`).
    - In the **Apply if** field, enter a request condition. For example, to send all users in Asia and Europe to the restricted origin server, enter `client.geo.continent_code == "AS" || client.geo.continent_code == "EU"`. See Geolocation-related VCL features for more information.

4. Click **Save and apply to**.

5. Click **Activate** to deploy your configuration changes.

Using custom VCL

If you'd prefer not to use the Fastly control panel, you can use custom VCL to configure your service to change origin servers based on the user's geographic location. Use the following VCL as a starting point:

```
# default conditions
  set req.backend = F_global;

  # Use restricted content if the user is in Asia, France or German
  if (client.geo.continent_code == "AS" || client.geo.country_code
    set req.backend = F_restricted_content;
  }

```

* * *

Enabling dualstack connections

/en/guides/enabling-dualstack-connections

When working with Fastly, you can enable IPv6 to allow for **dualstack** connections, meaning traffic to your websites and applications can be served over both IPv4 and IPv6. This can be done without any changes to your backend infrastructure and shouldn't negatively impact performance as most modern clients implement an approach called Happy Eyeballs. With this approach, clients connect over either IPv4 or IPv6, whichever is faster, choosing IPv6 over IPv4 when all else is equal.

To enable traffic to be served over IPv6 and IPv4 addresses, follow the instructions below appropriate to your CNAME record. If you're using one of our TLS products, you can find your CNAME records in the **HTTPS and network** tab, under **DNS details**. If the name ends in `map.fastly.net`, it is a customer-specific hostname. Otherwise, it is a Fastly-shared hostname.

Once enabled, test that you can connect over IPv6.

Limitations and considerations

Note the following limitations and considerations:

- If you use our Anycast IPv4 addresses for apex domains, contact Fastly support and we'll provide you with the appropriate Anycast IPv6 addresses.
- Fastly's geolocation features work with IPv6 addresses.
- You can track whether a request came in as an IPv6 request with the `req.is_ipv6` VCL variable as well as by the IPv6 format itself when logging `%h`.

Enabling dualstack for Fastly-shared hostnames

You can enable IPv6 dualstack (IPv4 and IPv6) functionality for your hostname by prefixing your CNAME record with `dualstack`. For example, if you have traffic on an IP address pool nicknamed `j.sni` (which supports a minimum TLS version of 1.2, a maximum TLS version of 1.3, does not support 0RTT, and offers HTTP/2), then you could use the following dualstack options:

- `dualstack.j.sni.global.fastly.net` (dualstack global map)
- `dualstack.j.sni.us-eu.fastly.net` (dualstack NA/EU)

If you are using `m.ssl` (which supports a minimum and maximum TLS version of 1.2 and HTTP/1.x only), then you could use the following dualstack options:

- `dualstack.m.ssl.global.fastly.net` (dualstack global map)
- `dualstack.m.ssl.us-eu.fastly.net` (dualstack NA/EU)

> **TIP**
>
> For more information on updating your CNAME record, see our instructions on updating your CNAME record with your DNS provider.

Enabling dualstack on customer-specific hostnames

If you have a customer-specific hostname, contact support and we'll provide you with a parallel IPv6 map or enable dualstack on your current one. By default, maps will be HTTP/2

enabled and have a global billing region set. Be sure to specify any required changes when having a new map created.

Testing IPv6

Once you're up and running with IPv6, test IPv6 by entering a dig command in a terminal application to make sure your map returns AAAA records. For example, you can type something similar to this:

```
$ dig www.example.com AAAA +short
```

where `www.example.com` is the domain that you're testing.

Your output should appear similar to the following:

```
2606:2800:220:1:248:1893:25c8:1946
```

You can also use a tool like What's my DNS and choose the AAAA option to see how clients around the world are resolving to your CNAME record.

---

* * *

	Failover configuration
🔗	/en/guides/failover-configuration

This guide describes how to configure failover origin servers. Failover (backup) servers ensure you can maintain availability of your content if your primary server is not available.

Before you begin

To configure failover origin servers you must make sure you have health checks configured for your primary server. If you configure your failover servers but don't configure health checks on the primary server, the failover won't work properly if your primary server stops responding.

Configuring a failover origin server

Once you've confirmed health checks are configured, you must:

1. Enable automatic load balancing on all primary origin servers and any servers that will become your failover.
2. Attach a condition to the failover server that specifies exactly when to use is as a backup.

Enable automatic load balancing

To configure a failover origin server, turn on automatic load balancing for your primary and failover origin servers by following the steps in our guide on configuring load balancing.

Specify when to use the failover server

Once you've configured your primary and failover servers, attach a condition that specifies exactly when the failover servers should be used. The settings for the condition differ depending on whether you have a single primary origin server or multiple primary origin servers.

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Origins**.
5. In the **Hosts** area, find your failover origin server and click **Attach a condition**.
6. Click **Create a new request condition**.
7. In the **Name** field, enter the name of your request condition (for example, `Primary origin down`).
8. In the **Apply if** field, enter the conditions under which to use the failover server:
   - If you have multiple primary servers, enter the following in the **Apply if** field: `backend.autodirector_.healthy == false`.
   - If you have a single primary server, enter the following in the **Apply if** field: `backend.{name of primary server}.healthy == false`.

   NOTE

> Preview the VCL to find the name of the primary server. Typically the name is prefixed with `F_` and spaces are replaced with underscores. For example, a backend called `Host 1` has the VCL name `F_Host_1`.

9. Click **Save and apply**.
10. For any other failover origin servers, click **Attach a condition** and select the condition you already created to apply it.

---

* * *

	Forcing an HTTPS redirect
🔗	/en/guides/forcing-an-https-redirect

If you only want to allow HTTPS connections on your site, you can use Fastly to force unencrypted requests to the Transport Layer Security (TLS) protocol. When you force TLS, any unencrypted request to your website returns a **301 Moved Permanently** response which redirects to the TLS equivalent. For example, a request for `http://www.example.com` redirects to `https://www.example.com`.

Because requests can still happen over HTTP first, even if you force a TLS redirect, you can also use Fastly to enable HTTP Strict Transport Security (HSTS). Once enabled, HSTS forces the browser to redirect to the HTTPS URL (typically with a status code 307) as long as the URL has previously been visited.

Fastly provides a setting that allows you to force TLS and enable HSTS at the same time. Alternatively, for more control, you can manually force a TLS redirect then enable HSTS.

Prerequisites

These instructions assume that you've set up TLS service with Fastly.

Forcing TLS and enabling HSTS


To force TLS and enable HSTS at the same time using a service configuration, follow these steps.

> **NOTE**
>
> Services activated using a previous version of the Force TLS controls may temporarily display an additional, older testing duration. Once you select the recommended new testing duration, this older option will disappear.

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Settings**.

> **NOTE**
>
> If you have **Force TLS** enabled for any request settings without a condition, conflicts in the VCL logic may occur. Delete the existing request setting or modify it to add a condition.

5. Click the **Force TLS and enable HSTS** switch to force TLS and enable HSTS for the service.



   The request setting for forcing TLS and the header for enabling HSTS will automatically be created for you.

6. Click **Activate** to deploy your configuration changes.

WARNING

You may experience problems if you enable this setting along with the global override host setting. Instead of enabling the global override host setting, create a new request setting and specify the override host in the advanced options.


Manually forcing an HTTPS redirect

To manually force an HTTPS redirect, you must create a request setting that forces TLS and add a header that enables HSTS.

Forcing TLS

To manually force TLS, create a new request setting as follows:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Settings**.
5. Click **Create request setting**.




6. Fill out the **Create a request setting** fields as follows:
    - In the **Name** field, enter a human-readable name for the request setting. This name is displayed in the Fastly web interface.
    - From the **Force TLS** menu, select **Yes**.
7. Click **Create** to save your request setting changes.
8. Click **Activate** to deploy your configuration changes.

Enabling HSTS

After manually forcing a TLS redirect, enable HSTS by adding a new header as follows:

1. Click **Content**.

2. Click **Create header**.



3. Fill out the **Create a header** fields as follows:

   - In the **Name** field, enter a human-readable name, such as `HSTS`. This name is displayed in the Fastly web interface.
   - From the **Type** menu, select **Response**, and from the **Action** menu select **Set**.

- In the **Destination** field, enter `http.Strict-Transport-Security`.
- In the **Source** field, enter `"max-age=<max age in seconds>"`. For example, `"max-age=31536000"`. As described below, `max-age` is required and two additional HSTS options can be specified.
- Leave the **Ignore if set** menu and the **Priority** field set to their defaults (or set them as appropriate for your service).

4. Click **Create**.
5. Click **Activate** to deploy your configuration changes.

HSTS options

If you manually configured the HSTS header, you can specify additional HSTS options.

HSTS requires the max-age directive be set in order to function properly. It specifies how long in seconds to remember that the current domain should only be contacted over HTTPS. The example shown above sets `max-age` to one year (31536000 seconds = 1 year). You may want to experiment using a smaller value than what is shown.

Two additional options can be specified with the HSTS response header:

- `includeSubdomains` - This token applies HSTS to all of your site's subdomains. Before you include it, be certain none of your subdomains require functionality on HTTP in a browser. Ensure your TLS certificate is a wildcard or has certificate coverage for all subdomain possibilities.

  > **IMPORTANT**
  >
  > All subdomains will be unreachable on HTTP by browsers that have seen the HSTS header once `includeSubdomains` is enabled.

- `preload` - This token allows you to submit your domain for inclusion in a preloaded HSTS list that is built into several major browsers. Although the token is not part of the HSTS specification, including it in the header is a prerequisite for submitting to this preloaded list.

  > **WARNING**
  >
  > Don't request browser preload inclusion unless you're sure that you can support HTTPS for the long term. Inclusion in the HSTS Preload List cannot be

undone easily. See https://hstspreload.org/ for submission instructions and more information.

Combining all of these options together in the **Source** field would look like this:

```
"Strict-Transport-Security: max-age=<max age in seconds>; includeSul ma
```

To disable HSTS for whatever reason, simply set the `max-age` to `0` on an HTTPS connection.

NOTE

The HSTS Preload List is managed by a third party, not by Fastly. Consult https://hstspreload.org/ for more information.

---

* * *

Maintaining separate HTTP and HTTPS requests to origin servers

/en/guides/maintaining-separate-http-and-https-requests-to-backend-servers

---

It is common to use the same origin web application to serve both HTTP and HTTPS requests and let the application determine which actions to take to secure communications depending on the incoming protocol. Fastly allows users to set this up to preserve this functionality within their servers. To set Fastly up to send HTTP requests to the non-secure service and HTTPS requests to the secure service, configure two origins, one each for the secure and non-secure ports, then set up the conditions under which requests will be sent there.

Create multiple origins

Begin by configuring the same origin address with a different port as a separate origin server. Follow the instructions for working with hosts. You'll add specific details about the

non-secure server (port `80`) when you fill out the **Create a host** fields:

- In the **Name** field, enter a name for the non-secure server (for example, `Server Name (plain)`).
- In the **Address** field, enter the address of the non-secure server (for example, `server.example.com`).
- In the **Transport Layer Security (TLS)** section, set **Enable TLS?** to **No**.

Follow the instructions for working with hosts to create another origin server, this time for your secure server. You'll add specific details about the secure server (port `443`) when you fill out the **Create a host** fields:


- In the **Name** field, enter a name for the non-secure server (for example, `Server Name (secure)`).
- In the **Address** field, enter the address of the non-secure server (for example, `server.example.com`).
- In the **Transport Layer Security (TLS)** section, leave the **Enable TLS?** default set to **Yes**.

Conditionally send traffic to origins


To conditionally determine which server receives secure and non-secure requests, Fastly relies on the presence or absence of a specific header when the backend is selected. When an incoming connection is received over TLS, Fastly sets the `req.http.fastly-ssl` header to determine which server to use.

Set a condition for this header on each origin by following the steps below.

1. On the **Origins** page, click **Attach a condition** next to the name of the non-secure server.



2. Fill out the **Create a new request** fields as follows:
    - In the **Name** field, enter the name of the condition specifying use of the non-secure server (for example, `Use non-secure`).
    - In the **Apply if** field, enter `!req.http.fastly-ssl`.
    - Leave the priority set to its default value.
3. Create the new condition by clicking **Save and apply to**.
4. On the **Origins** page, click **Attach a condition** next to the name of the secure server.



5. Fill out the **Create a new request condition** window as follows:
    - In the **Name** field, enter the name of the condition specifying use of the secure server (for example, `Use secure`).
    - In the **Apply if** field, enter `req.http.fastly-ssl`.
    - Leave the priority set to its default value.
6. Create the new condition by clicking **Save and apply to**.
7. Click **Activate** to deploy your configuration changes.

* * *

Setting up redundant origin servers

/en/guides/setting-up-redundant-origin-servers

Sometimes you want to set up two different origin servers, one as a primary and one as a backup in case the primary becomes unavailable. You can do this via the Fastly control panel or using custom VCL.


NOTE

Each Fastly service can be configured with up to five origin servers. Contact sales@fastly.com to enable more than five origin servers per service in your account.


Using the Fastly control panel

Set up redundant origins via the Fastly control panel using these steps.


1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Origins**.
5. In the **Health Checks** area, define a health check and assign it to the primary origin server.
6. In the **Hosts** area, find your secondary origin server and click **Attach a condition**.



7. Click **Create a new request condition**.



8. Fill out the **Create a new request condition** fields as follows:
    - In the **Name** field, enter the name of your request condition (for example, `Primary Unhealthy`).
    - In the **Apply if** field, enter `!req.backend.healthy`.
9. Click **Save and apply to**. The Hosts area now displays the condition that must be met (Primary Unhealthy) in order for your secondary origin server to begin being used.



Once you've added the condition to your secondary origin server, the VCL generated by Fastly will reflect the new condition.

10. Preview the VCL, and confirm the following snippets appear in `vcl_recv`:

```
# default conditions
set req.backend = F_primary;
```

```
# Request Condition: primary unhealthy Prio: 10
if (!req.backend.healthy) {
  set req.backend = F_secondary;
}
#end condition
```

Using custom VCL

Set up redundant origins with custom VCL using these steps.

1. In the Fastly control panel, define a health check and assign it to the primary origin server.
2. Copy the boilerplate VCL from our guide on mixing Fastly VCL with custom VCL, and paste it into a new file.
3. Replace the `vcl_recv` sub with:

```
sub vcl_recv {
#FASTLY recv
  set req.backend = F_<primary_origin>;
  if (!req.backend.healthy) {
    set req.backend = F_<secondary_origin>;
  }
  if (req.method != "HEAD" && req.method != "GET" && req.method
    return(pass);
  }
  return(lookup);
}

```

To find the exact backend names, view the generated VCL.

4. Upload your VCL file.

---

* * *

Specifying an override host

/en/guides/specifying-an-override-host

To rewrite the Host header being sent to your origin regardless of the Host used in the initial request, specify an override host. Use this if you have multiple domains tied to a service and want them all served by the same origin, if the domain your origin is expecting is different than one specified in your Fastly service, or if the Host header being sent to your origin is different from the Host used in the initial request.

You can override the Host header being sent to your origin by specifying the domain name of your override Host on the **Settings** page for a specific service or by specifying a host on the **Origins** page for a specific Host.

Here are some examples of when to use an override host:

- When using backends such as Amazon S3 or Google Cloud Storage, you want to ensure you use the proper Host header so these providers know how to route requests directly to your content. Each provider uses the Host header to associate requests with your account's storage location. For example, if you set up your origin using Amazon S3, you send the name of your S3 bucket as your Host header. Amazon is set up so that it only accepts Host headers that have the same name as the bucket hosting your content. A request to `your-domain.com` must be re-written to `<BUCKET>.s3.<REGION>.amazonaws.com`, or else the request is denied.
- You have a service that contains three sites: `www.abc.com`, `www.myexample.com`, and `www.mysite.com` and you have one origin. You can have the same origin respond to each domain by overriding the Host header to one accepted by your origin, for example, `origin.example.com`. The result will be that a request to `www.abc.com`, `www.myexample.com`, or `www.mysite.com` returns content from `origin.example.com`.

> **NOTE**
>
> If you've initially set an override Host globally and then switch the configuration to set an override Host per origin, this will temporarily increase cache MISS and origin traffic because the Host header that Fastly was using for the cache lookup was changed from the client's original Host header. Once a new object is cached with the new host, cache HIT will be served.

Overriding a host at the origin level

You can add an override Host per origin if you're using an origin that requires a specific hostname to be passed to it. Once you've added a host, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Origins**.
5. In the **Hosts** area, click the pencil next to the Host you want to edit.
6. In the **Override host** field, enter the hostname of your override Host header based on the origin you're using. The value in this field will take precedence over anything you've set using the global override Host configuration. For example:

- If you're using Amazon S3 as your origin, enter `<BUCKET>.s3.<REGION>.amazonaws.com`.
- If you're using Google Cloud Storage as your origin, enter `<BUCKET>.storage.googleapis.com`.

> **TIP**
>
> To see other examples of Host headers for third-party services, refer to our developer documentation on overriding the Host header.

7. Click **Update**. The new override Host appears under the **Show all details** field of the **Override host** section and a code block is added to the origin definition in your VCL that will look similar to the following:

```
Backend F_Host_1 {
    .host = "..."; # IP or hostname
    .host_header = "example.com";
    .always_use_host_header = true;
     ...
}
```

8. Click **Activate** to deploy your configuration changes.


Overriding a host globally

> **NOTE**
>
> Use the global override if you only have one backend. If you do use the global override, be sure to read all the caveats below.

You can globally override a Host if your service has multiple domains to serve but they are all same assets (e.g., `assets1.example.com` and `assets2.example.com`) and you want to normalize them (e.g., `assets.example.com`). To globally override a host, follow the steps below:

1. Log in to the Fastly control panel.

2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Settings**.
5. Click the **Override host** switch.



6. In the **Override host header** field, enter the hostname of your override Host based on the origin you are using:
   - If you are using Amazon S3 as your origin, enter `<yourbucket>.s3.amazonaws.com`.
   - If you are using Google Cloud Storage as your origin, enter `<your bucket name>.storage.googleapis.com`.
7. Click **Save**. The new override host header appears in the Override host section.
8. Click **Activate** to deploy your configuration changes.

Caveats about using the global override host

There are situations when you may not want to use an override host:

- **Forcing TLS and enabling HSTS.** You may experience problems if you enable this setting along with the force TLS and enable HSTS setting. Instead of enabling this setting, create a new request setting and specify the override host in the advanced options.
- **Using multiple origins.** When you specify a Host override, you're specifying what hostname is actually sent to your origin. If you have a service with two different origins and each origin requires a different hostname, specifying a Host override for all requests results in one origin not returning valid responses. If you specify a default

hostname that matches only one of the origins, then no content is returned from the other origin requests.

> **NOTE**
>
> To serve content from multiple backends, you should conditionally route to them. Check out our guide on URL path-based routing for more information.

- **Shielding is enabled.** If you enable a Host override along with shielding and the specified override host doesn't match to a domain within the service, the shield won't route the request properly and an error of 500 is expected. Refer to Shielding for more information.

> **NOTE**
>
> To ensure consistent behavior of Fastly customer services and origins, we normalize the host header's value to all lowercase in the `vcl_hash` function. This means that no matter how your site's domain name is capitalized in the request, the hash function will behave predictably. This does not apply to any other parts of the URL, which remain case-sensitive.

---

* * *

Using Fastly with apex domains

/en/guides/using-fastly-with-apex-domains

If you're working with a new domain, we recommend using a subdomain such as `www` wherever you publish links to your site and redirecting your apex domain to the subdomain. If you're already using the second-level or apex domain (e.g., `example.com` rather than `www.example.com`) as your canonical domain, you may need to carry out additional steps. Due to restrictions in the DNS specification, a CNAME record cannot be placed at the apex domain nor do we recommend using proprietary CNAME flattening features offered by some DNS providers (e.g., ALIAS or ANAME).

Instead, we offer anycast IP addresses for content that must be hosted on a second-level or apex domain. Our anycast options allow you to add A (IPv4) or AAAA (IPv6) records that

point your apex domain at Fastly, prioritizing either performance or cost, depending on the option you choose.

> IMPORTANT
>
> Because anycast addressing methods don't offer Fastly as much flexibility in routing requests, our anycast options may not be as performant as our CNAME-based system. We recommend using our CNAME-based system for as much content as possible, particularly for large resources or streaming video.

Anycast options

Fastly offers the following anycast options to all paid customers.

Global anycast option

Fastly offers anycast IP addresses that allow you to use our entire global network to route requests to the nearest Fastly POP (from a network perspective), without regard to the billing region in which that POP resides.

Choose this option to prioritize traffic routing performance and to avoid restricting traffic to specific POPs. We'll provide you with a list of anycast IP addresses, which you then enter into your DNS records.

Billing Zone anycast options

> IMPORTANT
>
> Billing Zone anycast options are part of a limited availability release. For more information, see our product and feature lifecycle descriptions.

Fastly offers anycast IP addresses that allow you to prioritize where requests get routed based on the cost of its travel through groups of specific billing regions called *zones*.

Choose one of these options to prioritize cost savings over routing performance:

- **Maximum Billing Zone (MBZ) 100:** This option includes only the Fastly POPs located in the North America and Europe billing regions.
- **Maximum Billing Zone (MBZ) 200:** This option includes all Fastly POPs in MBZ 100 as well as those in the billing regions of Asia, Australia and New Zealand, Mexico, and

South America. It does not include POPs in the South Korea, India, and Africa billing regions.

Availability versus routing accuracy

> **IMPORTANT**
>
> Fastly prioritizes service availability over routing accuracy. Fastly will not offer invoice credits for traffic delivered from Fastly POPs outside of intended billing zones when that traffic is intentionally diverted to preserve the integrity or performance of Fastly services, for scheduled maintenance, or when the traffic routing changes are outside of Fastly's control.

Because most anycast routing on the public internet is outside of our direct control, we cannot guarantee traffic routed to us will never arrive at POPs in higher billing zones. When routing changes on the public internet shift your traffic to higher priced Fastly POPs, however, we will make our best effort to investigate the cause and work with all parties involved to correct any problems discovered.

In addition to factors outside of our control, Fastly performs traffic engineering on a regular basis to ensure the availability of all Fastly services during incidents and scheduled maintenance to our network. When necessary, we may temporarily choose to route traffic to POPs outside of the chosen Billing Zones.

If you observe traffic being served from Fastly POPs outside of the intended Maximum Billing Zone, then before opening a support ticket:

- Check the Fastly Service Status page. Verify that there are no events that would explain the temporary rerouting of your traffic.
- Check the DNS records for your impacted domain names. Only the Fastly provided Billing Zone anycast IP addresses should be present in the DNS records of your impacted domain names.

If neither of the above issues explain your observed Fastly POP routing issue, open a support ticket within 30 days of the Fastly invoice date that reflects the billed traffic in question by contacting support.

Finding anycast IP addresses

When you choose a Billing Zone anycast option, we'll provide you with the list of anycast IP addresses for you to enter into your DNS records. Fastly will use these addresses to serve

traffic only from the POPs included in the zones listed above, even if those POPs are unlikely to give the best performance for any given request.

When you have TLS configured

If TLS is configured for your Fastly service, you can obtain your global anycast IP addresses in the Fastly control panel by following these steps:

1. Go to **Security** > **TLS management** > **Domains**.
2. Click **View details** for the domain you would like to route to Fastly via the global anycast option. The domain's details page appears.

The A records section contains the global anycast IP addresses for you to enter into your DNS records of this domain.

When you don't have TLS configured

If you don't have TLS configured for the domain you would like to use with the global anycast option or would like to use one of the new Billing Zone anycast options, you can request your anycast IP addresses by contacting support. We'll provide you with the anycast IP addresses appropriate for the option you choose so you can enter those addresses into your DNS records. Be sure to enter all of them to ensure maximum availability and reliability. We don't charge extra for these options, however, you must be using one of Fastly's paid plans (with or without a contract) to take advantage of them.

> **TIP**
>
> Fastly's billing regions can be found on our pricing page. We announce changes to these regions via our network status page.

Apex domain problems and their workarounds

The DNS instructions in RFC1034 (section 3.6.2) state that, if a CNAME record is present at a node, no other data should be present. This ensures the data for a canonical name and its aliases cannot be different. Because an apex domain requires NS records and usually other records like MX to make it work, setting a CNAME at the apex would break the "no other data should be present" rule.

In general, the problem with apex domains happens when they fail to redirect to their www equivalents (`example.com` points nowhere instead of pointing to `www.example.com`). Two workaround options exist:

- only use Fastly for API or AJAX calls, images, and other static assets (e.g., serve `example.com` yourself and CNAME to Fastly for assets at `assets.example.com`).
- redirect from the apex domain to the version proxied by Fastly (e.g., redirect any requests for `example.com` to `www.example.com`).

Neither workaround, however, is ideal.

> **IMPORTANT**
>
> To use TLS with an apex domain, explicitly add it to a certificate using one of our TLS products. For wildcard entries on our shared certificates, add an apex domain as a separate SAN entry.

* * *

Category: Headers

These articles describe configuration settings and changes you can make to your headers when setting up Fastly services.

Adding or modifying headers on HTTP requests and responses

/en/guides/adding-or-modifying-headers-on-http-requests-and-responses


---

HTTP header fields are components of the header section of request and response messages in the Hypertext Transfer Protocol (HTTP). They define the operating parameters of an HTTP transaction. When you create and configure headers, you can determine how you want your content served to your users. The following steps show you how to add and edit headers.

Create new headers

To create a new header, follow these steps:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click **Create header**.



6. Fill out the **Create a header** fields as follows:
   - In the **Name** field, enter the name of your header rule (for example, `My header`).
   - From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
   - In the **Destination** field, enter the name of the header affected by the selected action.

- In the **Source** field, enter where the content for the header comes from.
- From the **Ignore if set** menu, select **No** if you want the header in the **Destination** field modified or select **Yes** if you don't want it modified.
- In the **Priority** field, enter the order the header rules execute.


The Field description table below provides additional details about each of these controls.

7. Click **Create**.
8. Click **Activate** to deploy your configuration changes.

Edit headers

To edit an existing header, follow these steps:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click the name of the header you want to edit.



6. Fill out the **Edit this header** fields as follows:
    - In the **Name** field, enter the name of your header rule (for example, `My header`).
    - From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
    - In the **Destination** field, enter the name of the header affected by the selected action.

- In the **Source** field, enter where the content for the header comes from.
- From the **Ignore if set** menu, select **No** if you want the header in the **Destination** field modified or select **Yes** if you don't want it modified.
- In the **Priority** field, enter the order the header rules execute.

7. Click **Update**.
8. Click **Activate** to deploy your configuration changes.

Field description table

This table describes what each field in the Header window means:

Field	Description
Name	The Name field specifies a memorable word or phrase that allows you to recognize and remember a particular Header rule.
Type	The Type menu can be set to **Request**, **Response**, or **Cache**. Selecting **Request** modifies the request coming from the user, and this will carry through to the request that gets sent to your origin server. Selecting **Response** affects the HTTP response that is sent back to the user. Selecting **Cache** affects the HTTP response that your origin server returns before it gets stored on Fastly servers, meaning whatever changes you make there will be remembered on a cache hit.
Action	The Action menu can be set to **Set**, **Append**, **Delete**, **Regex**, and **Regex All**. Selecting **Set** (the default) will write a value into the header (potentially overwriting it, if it already exists). Selecting **Append** will add a value onto the end of a header or set it if it doesn't exist. Selecting **Delete** will remove a header. When selected, it hides the Source field in the Header window. Selecting **Regex** allows you to perform a find and replace on specific text and is based on a regular expression you type in. When selected, the Regex and Substitution controls appear in the Header window. Selecting **Regex All** allows you to perform the same function as **Regex** but it performs a find and replace multiple times. When selected, the Regex and Substitution controls appear in the Header window.
Destination	The Destination field determines the name of the header that is going to be affected by our Action. Because header rules can be used to

Field	Description
	affect more than just HTTP headers, your input to this field should be formatted like this: `http.Header-Name`.
Source	The Source field is available on Set, Append, Regex, and Regex All actions. This field becomes hidden in the Header window when you select Delete from the Action menu. It determines where the new content for the header comes from. There are a plethora of options for Source. The simplest is a static string such as `"My Static String"` (including the quotes). Other options include VCL variables like those related to client connections, HTTP headers, and geolocation variables.
Regex	The Regex field only appears in the Header window when you select Regex or Regex All from the Action menu. It allows you to perform a find and replace on specific text and is based on a regular expression that you type in.
Substitution	The Substitution field only appears in the Header window when you select the Regex and Regex All from the Action menu. It replaces the text that was removed by the regex expression with the text you typed in the Substitution field.
Ignore if set	By default this is set to No, which means that if the header you are modifying already exists, it will be modified.
Priority	The Priority field determines the order in which the header rules execute (e.g., a priority of 1 means the header rule executes first). This can be important if you set headers and then set other headers based on the earlier ones.

* * *

Enabling cross-origin resource sharing (CORS)

/en/guides/enabling-cross-origin-resource-sharing


Enabling Cross-Origin Resource Sharing (CORS) allows a server to indicate that other origins can request sub-resources, like scripts and stylesheets, from it. These origins might use a

different scheme (HTTP vs HTTPS) or an entirely different domain or port. This guide describes how to add an `Access-Control-Allow-Origin` header, which is sufficient for simple scenarios, and is often useful when using static bucket providers like Amazon S3 and Google Cloud Storage as an origin.

> **IMPORTANT**
>
> We recommend only enabling CORS when you have sub-resources on your server that you want other origins to load, especially if you allow requesting code from *any* origin, as it makes things less secure.

To enable CORS, set up a custom HTTP header for your service by following the steps below.

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click **Create header**.



6. Do the following with the **Create a header** controls depending on whether you're creating a header for all origins or creating a header for a specific origin:

For this control	When creating a header for any origin	When creating a header for a specific origin
Name	Enter a descriptive name for the new header (e.g., `CORS S3 Allow`).	Enter a descriptive name for the new header (e.g., `CORS S3 Allow`).
Type	Select **Cache**.	Select **Response**
Action	Select **Set**.	Select **Set**.
Destination	Enter `http.Access-Control-Allow-Origin`.	Enter `http.Access-Control-Allow-Origin`.
Source	Enter `"*"`.	Enter a specific origin (e.g., `https://example.com`).
Ignore if set	Leave the default value.	Leave the default value.
Priority	Leave the default value.	Leave the default value.

Any time you specify a single origin in the **Source** field to ensure CORS rules are applied in `vcl_deliver`, the system will generate VCL under `vcl_deliver` as `set resp.http.Access-Control-Allow-Origin = "<specified origin>";`.

7. Click **Create**. The new header appears on the Content page.
8. Click **Activate** to deploy your configuration changes.

IMPORTANT

Objects already cached won't have this header applied until you purge them.

Test it out

Running the command:

```
$ curl -I example.tld/path/to/resource
```

should include similar information to the following in your header:

```
Access-Control-Allow-Origin: http://example.tld
```

```
Access-Control-Allow-Methods: GET
Access-Control-Expose-Headers: Content-Length, Connection, Date...
```

TIP

`Access-Control-Allow-Methods` and `Access-Control-Expose-Headers` are examples of additional headers you can add with CORS. For more information about these headers, check out MDN Web Docs.

* * *

Removing headers from backend response


/en/guides/removing-headers-from-backend-response

You can remove headers from any backend response. This may be necessary if your application automatically sets headers. For example, Drupal can set the following Expires and Cache-Control headers to prevent caching:

```
Expires: Sun, 19 Nov 1978 05:00:00 GMT
Last-Modified: Wed, 18 Jul 2012 18:52:16 +0000
Cache-Control: no-cache, must-revalidate, post-check=0, pre-check=0
```

To remove a header from the backend response, add a new header as follows:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click **Create header**.



6. Fill out the **Create a header** fields as follows:

   - In the **Name** field, enter a descriptive name for the header rule (e.g., `Remove Expire Headers`).
   - From the **Type** menu, select **Cache**, and from the **Action** menu, select **Delete**
   - In the **Destination** field, enter the name of the header (e.g., `http.Expires`).
   - From the **Ignore if set** menu, select **No**.
   - In the **Priority** field, enter `10`.

7. Click **Create**.
8. Click **Activate** to deploy your configuration changes.

> **TIP**
>
> You may also be interested in our information on setting content type based on file extension.

---


* * *

Setting Content Type based on file extension

/en/guides/setting-content-type-based-on-file-extension

In some situations you may want to override the content type that a backend returns. To do that you will need to create a new header object and an associated condition.

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click **Create header**.




6. Fill out the **Create a header** fields as follows:
    - In the **Name** field, enter an appropriate name (e.g., `Add Content Type`).
    - From the **Type** menu, select **Cache**, and from the **Action** menu, select **Set**.
    - In the **Destination** field, enter `http.Content-Type`.

- In the **Source** field, enter the content type you want to match, such as `"application/javascript; charset=utf-8"`.
- From the **Ignore if set** menu, select **No**.
- In the **Priority** field, enter `10`.

7. Click **Create**.

Once you have created the header object, apply a condition. Otherwise, that particular object is applied to all requests.

1. Click **Attach a condition** to the right of the new header name.



2. Fill out the **Create a new cache condition** fields as follows:
    - In the **Name** field, enter a descriptive name, such as `Files ending with .js`.
    - In the **Apply if** field, enter the condition that matches your request, such as `req.url.ext == "js"` (to match the request for files ending in .js).
3. Click **Save and apply to**. The new condition is created.
4. Click **Activate** to deploy your configuration changes.

TIP

You may also be interested in our guide to Removing headers from backend response.

* * *

Category: Image optimization

These articles provide basic instructions for and examples of setting up and beginning to use the Fastly Image Optimizer.

About Fastly Image Optimizer

/en/guides/about-fastly-image-optimizer

Fastly's Image Optimizer (Fastly IO) is an image optimization service that manipulates and transforms your images in real time and caches optimized versions of them. When an image is requested from your origin server, Fastly IO can perform one or more transformation tasks before serving and caching the optimized version. For example, you can resize, adjust quality, crop and trim, serve responsive images, and more.

WARNING

Only send image content through Fastly IO. Non-image content can't be optimized using it, but will still be counted and charged as an image optimization request, which may cost you more.

Before you begin

Before you begin using Fastly IO, keep the following in mind:

- Fastly's Image Optimizer is disabled by default. Anyone assigned the role of superuser can enable a 30-day trial directly in the web interface on the Trials page. After your trial expires, Image Optimizer can be purchased for an account by contacting sales@fastly.com and then enabled for a service by any superuser or engineer, which will result in changes to your monthly bill.

- Services that use image optimization require shielding. When setting up shielding, be sure to choose a shield location as geographically close to your image's origin as possible. Our guide to enabling shielding provides more information on how to enable shielding. Take special note of the step immediately following your shielding location selection in that guide. If the Host header for the service has been changed from the default, you must ensure the new hostname is added to the list of domains.
- Using premium Fastly IO features (e.g., the AVIF encoding format) requires the purchase of Image Optimizer Professional. Contact sales@fastly.com to purchase Image Optimizer Professional for your account.

Enabling and disabling the Fastly Image Optimizer

Enable or disable the Fastly Image Optimizer directly in the Fastly control panel using the steps below or via the API.

> **WARNING**
>
> Enabling or disabling the Fastly Image Optimizer on a service immediately impacts all service versions, including the active one.

Enabling the Fastly Image Optimizer

To enable Fastly IO for a service, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Image Optimizer**.
5. Click the **Image Optimizer** switch to enable Fastly IO for the service.

Disabling the Fastly Image Optimizer

To disable Fastly IO for a service, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.

3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Image Optimizer**.
5. Click the **Image Optimizer** switch to disable Fastly IO for the service.

Setting up image optimization


Once you've enabled Fastly IO for your service, you can set up image optimization by following this process:

1. Add a header.
2. Create a request condition.
3. Test an image.

Add the Fastly Image Optimizer header

Once image optimization has been enabled for your service, configure your service by adding the Fastly Image Optimizer header.

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click **Create header**.



6. Fill out the **Create a header** window as follows:
    - In the **Name** field, enter `Fastly Image Optimizer`.
    - From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
    - In the **Destination** field, enter `http.x-fastly-imageopto-api`.

- In the **Source** field, enter `"fastly"`. By default, the Fastly Image Optimizer removes any additional query string parameters that are not part of our image API. If your source image requires delivery of additional query string parameters from origin then enter `"fastly; qp=*"` instead.
- From the **Ignore if set** menu, select **No**.
- In the **Priority** field, enter `1`.


7. Click **Create** to create the new header.

> TIP
>
> For more help with adding or modifying headers, see our guide.

Create a request condition

To ensure only your image assets are routed via the Fastly Image Optimizer, create a request condition.

1. Click **Attach a condition** next to the `Fastly Image Optimizer` header.
2. Click **Create a new request condition**.



3. Fill out the **Create a new request condition** window as follows:

    - In the **Name** field, enter a descriptive name for the new condition (for example, `Fastly Image Optimizer Request Condition`).

- In the **Apply if** field, enter the appropriate request condition. For example, `req.url.ext ~ "(?i)^(gif|png|jpe?g|webp|avif|jxl|heic)$"` will send all files with GIF, PNG, JPG, JPEG, WEBP, AVIF, JXL, and HEIC extensions via the Fastly Image Optimizer. Likewise, `req.url ~ "^/images/"` will send all files in the `images` directory via the Fastly Image Optimizer.

4. Click **Save and apply** to create the new condition for the header.

5. Click **Activate** to deploy your configuration changes.

> **TIP**
>
> For more help using conditions, see our guide.

Confirm everything is working

Once you've activated your changes, check to see if the Fastly Image Optimizer is processing your image request by typing the following command on the command line:

```
$ echo -n "Image Width: " ; curl -sI "https://www.fastly.io/image.j wi
```

Replace `https://www.fastly.io/image.jpg?width=200` with the full image URL and width of the image you're testing.

The command line output will display the image's width, which should match the width query string you added to your image's URL. For example, the output might be:

```
Image Width: 200
```

Configuring default image settings

The Fastly Image Optimizer supports a variety of image formats and applies specific settings to all images by default. Use the Fastly control panel to review and adjust the default settings as appropriate. Changes to other image settings, including most image transformations, require using query string parameters.


To review and edit the default image settings via the control panel, follow the steps below:

1. Log in to the Fastly control panel.


2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.

3. Click **Edit configuration** and then select the option to clone the active version.

4. Click **Image Optimizer**.



5. Click the pencil next to the **Default settings**.




6. Adjust the **Edit default settings** as follows:

    - From the **Auto WebP** controls, leave the settings at their default or select **Yes** to convert images to the WebP format in browsers that support it. When you use the default setting, **No**, Fastly uses the image file type instead.
    - In the **Default WebP (lossy) quality** field, leave the settings at their default or enter the compression level for lossy file-formatted images. Fastly uses `85` for the default quality but you can specify any whole number between `1` and `100`.
    - From the **Default JPEG format** controls, leave the settings at their default or select the JPEG type to use when delivering the image. By default, Fastly sets the JPEG type to **Auto** to deliver images with the output type matching the input type. You can also select **Baseline** to display the image line by line starting from top left

and going to the bottom right, or **Progressive** to display a blurry image that becomes clear as it loads.

- In the **Default JPEG quality** field, leave the settings at their default or enter the compression level for quality of lossy file formats. Fastly uses `85` for the default quality but you can specify any whole number between `1` and `100`.
- From the **Allow upscaling** controls, leave the settings at their default or select **Yes** to return images larger than the original source file so they can fit the requested dimensions.

7. Click **Advanced options**.



8. Adjust the **Advanced options** settings as follows:

- From the **Enable Animated GIF to Video** controls, leave the settings at their default or select **Yes** to enable Animated GIF to video functionality. Each video frame will be counted and charged as an image optimizer request.
- From the **Resize filter** controls, select the image quality filter to use when resizing and generating new images to use a higher or lower number of pixels. By default, Fastly uses the **Lanczos3** filter. You can also choose **Lanczos2**, **Bicubic**, **Bilinear**, and **Nearest**.

Using advanced image settings

To go beyond the basic image optimization and transformation settings in the Fastly control panel, you must change your existing image URLs by adding query string parameters. For example, if your image source existed at `http://www.example.com/image.jpg`, you would need to add `?<PARAMETER=VALUE>` to the end of the URL to create the proper query string structure for Fastly to transform the image.

Our Fastly IO documentation describes each of the available image transformations in detail and includes the exact pattern you can add to URLs, along with a description and example of how to use each parameter and its values. These examples perform transformations and optimizations on our `www.fastly.io/image.jpg` URL so you can see exactly how they work before you change your image URLs. Additionally, it provides details you should know before you start adding Fastly IO query strings to your existing image URLs.

Debugging

Running into problems? See our details on image optimization debugging for more information.

What's next

Start experimenting with Fastly IO by following along with Introduction to Fastly Image Optimizer, a step-by-step tutorial that shows you how to set up Fastly IO for a real website. It builds on the concepts introduced in Introduction to Fastly's CDN, and it guides you through the steps of optimizing the images for Taco Labs, the static website we used as an example in Introduction to Fastly's CDN.

> **NOTE**
>
> This article describes a product that may use third-party cloud infrastructure to process or store content or requests for content. For more information, check out our cloud infrastructure security and compliance program.

* * *

Category: Object Storage

Fastly Object Storage is an Amazon S3-compatible large object storage solution that works seamlessly with Fastly services.

About Object Storage

/en/guides/about-object-storage

Fastly Object Storage is an Amazon S3-compatible large object storage solution that works seamlessly with both Deliver and Compute services. Using Fastly Object Storage, you can store larger file sizes with Fastly, improving latency, increasing cache hit ratios, and reducing egress charges.

To work with Fastly Object Storage, use the Fastly control panel or API to create access keys that allow you to work with the S3-compatible API while storing and accessing large files from Fastly. The S3-compatible API is used to create and manage *buckets*, the containers used to store your data, also thought of as *objects*. When working with bucket operations, a specific region is identified which corresponds with a Fastly regional endpoint.

Prerequisites

- Fastly Object Storage is an add-on and is priced in addition to Fastly services. On most accounts, anyone assigned the role of superuser can purchase this product from the Fastly control panel. If you have not been assigned that role, you can use the control panel to request that a superuser purchase it for you.
- AWS Signature Version 4 (SigV4) is required to access S3-compatible API endpoints.

Limitations and considerations

Note the following limitations and considerations when using the S3-compatible API with Object Storage. Be sure to also review the limitations and considerations applied to storing your data in Fastly Object Storage:

- Access keys created through the control panel grant access to Fastly Object Storage at the account-level, not the bucket-level. If you want to create access keys with bucket-level access, use the Fastly API.
- Bucket names cannot start with `fst` or `fastly`.

- Public access (i.e., unauthenticated access to buckets or objects) is not supported.
- Chunked uploads are not supported. Payloads must be transferred in a single chunk per request.
- Fastly Object Storage automatically encrypts uploaded objects. Uploaded objects have ETags that aren't an MD5 digest of their object data, which may require configuration changes to S3-compatible tooling in order to interact with the objects.

What's next

Once you meet the prerequisites required to work with Fastly Object Storage and have reviewed all limitations and considerations, create an Object Storage access key to begin working with the S3-compatible API.

---

* * *

	Working with Object Storage
🔗	/en/guides/working-with-object-storage

When working with Fastly Object Storage, you can use the Fastly control panel to create, view, and delete access keys. An access key is used when sending requests to the S3-compatible API from your Fastly services as a way to provide authentication to your bucket interactions. Access keys define which S3 buckets can be accessed and the scope of access, either read or read and write.

Before you begin

Make sure to review all prerequisites, limitations, and considerations for using Fastly Object Storage.

Getting started

To get started with Fastly Object Storage, create an access key. The first key you create must have *full access* to buckets in the account and the ability to *read and write* to the buckets.

Once you have a key created meeting these properties, use the S3-compatible API to create a bucket, using the key details to provide authentication in the API. Then, use the same key to interact with buckets using other compatible bucket operations or create additional keys and buckets.

Although an account-level key (full bucket access and read and write scope) is required to create buckets, other bucket operations can be performed by keys with more limited access. Once you have buckets created, you may choose to provide certain people or tools with keys that have limited access to only specific buckets or read-only access.

Working with access keys

Access keys are used to authenticate requests to buckets using the S3-compatible API to perform various bucket operations. The level of access you have to work with these operations depends on the combination of access key properties you select.

IMPORTANT

The first access key you create must have **Full access** and **Read and write** scope as this is the only way you can create buckets. Only after this first key is created and used to create a bucket with the S3-compatible API can you create access keys with limited access or scope.

Access key properties	Access granted	Considerations
Full access + Read and write scope	Access to all current and future buckets in the account and the ability to read and modify those buckets	Only key type that enables **creating** buckets
Full access + Read scope	Access to all current and future buckets in the account and the ability to read those buckets	
Limited access + Read and write scope	Access to specific buckets and the ability to read and modify the contents of those buckets	Buckets must already be created

Access key properties	Access granted	Considerations
Limited access + Read scope	Access to specific buckets and the ability to read the contents of those buckets.	Buckets must already be created

Creating an Object Storage access key

To create an Object Storage access key:

1. Log in to the Fastly control panel.
2. Go to **Resources** > **Object Storage**.
3. Click **Create key**.
4. In the **Description** field, enter a description of the key.
5. In the **Bucket access** field, select whether to give the key **Full access** to current and future buckets or **Limited access** to certain buckets.
    - **Full access:** grants access to all current and future buckets.
    - **Limited access:** grants access to select buckets. If you choose this option, use the menu to select specific buckets the key has access to.
6. In the **Scope** field, select the level of access you want available to the key. The first key you create must have read and write access.
    - **Read:** access to read existing and future buckets.
    - **Read and write:** access to read and write to existing and future buckets.
7. Click **Create**.
8. Note the access key and secret key details. Record the secret key in a secure location because you won't be able to see it again.

Viewing Object Storage keys

Once at least one Object Storage access key is created, you can view details on all Object Storage access keys created on your account from **Resources** > **Object Storage**. The Object Storage page displays the following details:

- **Access Key ID:** the access key ID returned from the S3-compatible API.
- **Description:** a description of the access key.
- **Scope:** the level of access available to the access key.
- **Buckets:** the buckets the key grants access to.
- **Created on:** the date on which the access key was created.

Deleting Object Storage access keys

You can delete an Object Storage access key at any time. If the access key is being used by an active application, deleting it can cause unexpected behavior.

1. Log in to the Fastly control panel.
2. Go to **Resources** > **Object Storage**.
3. Click the trash to the right of the access key you want to delete.
4. Click **Confirm and delete**.

Working with the S3-compatible API

Use the S3-compatible API to create and interact with buckets that store your data. The access key is used to provide authentication.

> IMPORTANT
>
> In order to work with S3-compatible API, you must use an access key with **full** access to all buckets and **read and write** scope.

Send requests to one of the following regional Object Storage endpoints, including the matching region in the `credential scope` portion of the SigV4 signature:

- `us-east.object.fastlystorage.app`
- `us-west.object.fastlystorage.app`
- `eu-central.object.fastlystorage.app`

> NOTE

The regional Object Storage endpoints are different from AWS regions. Make sure you set all region options, like `LocationConstraint`, to the correct Object Storage region name or you may receive an `InvalidRequest` error.

Interact with your buckets by including the bucket name as part of the request path. For example, to access a bucket named `my-bucket` in the `us-east` region, you'd use the request path `https://us-east.object.fastlystorage.app/my-bucket`.

NOTE

Object Storage doesn't support using bucket names in the hostname (i.e., `https://my-bucket.us-east.object.fastlystorage.app`).

Compatible bucket operations

Object Storage supports the following processing operations for the S3-compatible API. These operations are categorized into two groups, each with differing prices. Refer to the Object Storage product description for more information on how operations are billed.

Class A operations

- CreateBucket
- DeleteBucket
- HeadBucket
- GetBucketLocation
- ListBuckets
- PutObject
- CopyObject
- DeleteObject
- DeleteObjects
- ListObjectsV1
- ListObjectsV2
- CreateMultipartUpload

- CompleteMultipartUpload
- AbortMultipartUpload
- ListMultipartUploads
- ListParts
- UploadPart
- UploadPartCopy

Class B operations

- GetObject
- HeadObject

---

* * *

Category: Performance

These articles describe how to adjust the performance of Fastly's services beyond standard configuration methods.

Debugging with mtr

/en/guides/debugging-with-mtr

We think the mtr tool offers a great way to test network speed, evaluate performance, and perform connection diagnostics. The mtr tool combines traceroute and ping programs in a single network diagnostic tool. The program's source and installation instructions live in GitHub.

While mtr provides a number of practical uses for network engineering needs, the following command works well:

```
$ mtr -c 20 -w -r www.example.com
```

Be sure to replace `www.example.com` with the hostname of the domain you're working with. The command will generate the network hops to the destination you specify, any packet loss experienced, and aggregate connection statistics.

For example, if we wanted to test the network connection from Fastly's San Francisco office to the CDN, we would use the above command for `www.fastly.com`. The following output would appear:

```
$ mtr -c 20 -w -r www.fastly.com
Start: Mon Feb  2 15:27:20 2015
HOST: test-local-machine.local                    Loss%   Snt   Last   Avg
  1.|-- 10.100.20.2                                0.0%    20    2.1   2.2
  2.|-- ge-4-3-4.mpr4.sfo7.us.zip.zayo.com         0.0%    20    2.3   2.4
  3.|-- ae5.cr2.sjc2.us.zip.zayo.com               0.0%    20    4.6   6.5
  4.|-- ae10.mpr4.sjc7.us.zip.zayo.com             0.0%    20    4.7   4.8
  5.|-- be6461.ccr21.sjc03.atlas.cogentco.com      5.0%    20    5.1   5.9
  6.|-- fastly-inc.edge2.sanjose3.level3.net       0.0%    20    5.0   4.7
  7.|-- ???                                       100.0    20    0.0   0.0
  8.|-- 23.235.47.184                              0.0%    20    4.7  14.3
```

* * *

Enabling automatic compression

/en/guides/enabling-automatic-compression

Compression can help you reduce the size of your assets so traffic can flow faster. You can use Fastly to compress data automatically on our edge servers.

Much of the data delivered by Fastly can be compressed using static compression, especially text-based formats like HTML, JavaScript, and CSS. Static compression fetches

content from origin, compresses it according to the user's requested format (either Brotli or gzip), and then caches it.

Dynamic compression, on the other hand, compresses content just before responses are delivered to the client and is used on content that can't be cached. For example, dynamic compression can compress content unique to an end user.

Limitations and caveats

Keep in mind the following:

- **The API endpoint name is currently /gzip.** API documentation for automatic compression currently appears in the documentation for the gzip endpoint. The documented gzip API fully supports Brotli compression.
- **Custom VCL can override your control panel and API compression settings.** If you enable compression using custom VCL, that configuration will be used instead of the setting in the control panel.

When considering the general behavior of Fastly's compression feature, keep in mind the following:

- **Compression is only supported for content served uncompressed from your origin.** To use automatic compression, ensure your content doesn't require decompression before compression is applied.
- **Compression is currently incompatible with Segmented Caching.** To use automatic compression ensure Segmented Caching is disabled.

Enabling static compression

This section demonstrates how to use the Fastly control panel to enable and disable static compression for cacheable content. To enable compression, select a compression format and then set up a compression policy.

> ⚠ WARNING
>
> Enabling static compression or changing the compression format immediately impacts all service versions, including the active one.

Selecting a compression format

To enable compression, start by selecting a compression format using the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Scroll to the **Compression** area. From the **Select compression format** options, do one of the following:
    - Select **Use Brotli compression when available** to use Brotli compression by default for browsers that support it. Once you've enabled compression and selected Brotli as the format, we will use it by default for responses any time a client's Brotli-capable browser sends us the appropriate Accept-Encoding header. Brotli is the preferred compression format for multiple Accept-Encoding values where gzip is also an option.
    - Select **Use gzip compression only** to avoid using Brotli and only use gzip as the compression format for this service.

Setting up a compression policy

Once you've selected the compression format, you'll need to set up a compression policy. Decide whether to:

- enable the default compression policy to compress content in files with `css`, `js`, `html`, `eot`, `ico`, `otf`, `ttf`, `json`, or `svg` file extensions.
- set up an advanced compression policy to customize the content and conditions for compression and specify exactly which types of content are compressed and the conditions under which this compression occurs.

Enabling the default compression policy


To enable the default compression policy, follow these steps:

1. Click the **Default compression policy** switch to enable compression using the format you selected to compress content using the default list of file extensions.
2. Click **Activate** to deploy your configuration changes.

Setting up an advanced compression policy

To set up an advanced compression policy, follow these steps:

1. Click **Set up advanced compression**.
2. Click **Override these defaults**.



3. Fill out the **Create a compression policy** fields as follows:
    - In the **Name** field, enter a human-readable name for your new compression policy.
    - In the **Extensions** field, enter the file extension for each file type to be dynamically compressed, separated by spaces. Only enter the three- or four-letter string representing the file extension.
    - In the **Content types** field, enter the content-type for each type of content you wish to have dynamically compressed, separated by spaces. Do not use regular

expressions.

4. Click **Create**. The new compression policy appears.
5. Click **Activate** to deploy your configuration changes.

Disabling static compression

If you're currently using the default compression policy, you can disable compression by clicking the **Default compression policy** switch to display `OFF`.

If you're currently using an advanced compression policy, you can disable compression by deleting it using the trash to the right of the policy's title:



> **WARNING**
>
> Disabling static compression immediately impacts all service versions, including the active one.

Automatic normalization

Because compression is one of the most common reasons to vary output based on a request header, Fastly will normalize the value of `Accept-Encoding` on incoming requests. The modified header will be set to a single encoding type, or none, and will reflect the best compression scheme supported by the browser.

Specifically, we run the following steps on inbound requests:

1. If the `User-Agent` matches a pattern for browsers that have problems with compressed responses, remove the `Accept-Encoding` header
2. Else if the `Accept-Encoding` header includes the string `br`, set the entire value to the string `br`
3. Else if the `Accept-Encoding` header includes the string `gzip`, set the entire value to the string `gzip`

4. Else if the `Accept-Encoding` header includes the string `deflate`, set the entire value to the string `deflate`
5. Else remove the `Accept-Encoding` header

Where this normalization process has changed the header value, the original value is made available in the custom header `Fastly-Orig-Accept-Encoding`.

Enabling dynamic compression

Fastly's Dynamic Content Compression feature allows you to compress dynamic content that wouldn't benefit from caching, like video streaming manifests and dynamic content from Compute applications. Once compressed, you are also able to apply dynamic web content assembly techniques like ESI. Our guide to delivering compressed content through Fastly discusses how to enable compression using custom VCL or the Fastly API via the X-Compress-Hint header and includes workflows for compressing dynamic content.

---

* * *

📄	**Enabling HTTP/3 for Fastly services**
🔗	/en/guides/enabling-http3-for-fastly-services

This guide describes how to enable HTTP/3 for your Fastly services.

About HTTP/3

HTTP/3 uses a web transport protocol standard called QUIC that you can offer to end user clients as an optional upgrade from HTTP/1.1 and HTTP/2 connections. End user clients will initially connect to your Fastly service using an earlier version of HTTP and will only attempt to use HTTP/3 if the Fastly service offers it.

Unlike the TCP transport protocol used by earlier versions of HTTP, QUIC requires that all connections be secured and uses TLS 1.3 to secure them. Like TLS 1.3, QUIC also supports the optional 0-RTT feature to help reduce the latency of resumed connections.

Prerequisites

To use HTTP/3 on Fastly's edge cloud services, you will need:

- a Fastly user account assigned the role of superuser
- relevant domains you will be using for HTTP/3 added to a properly configured Fastly service
- access privileges to modify DNS records for the domains you will be using

Limitations and key behaviors

- Fastly currently only supports HTTP/3 for end user connections, as that is where we expect the primary benefits of these protocols will be seen. We do not support HTTP/3 between Fastly and your origin servers.
- The QUIC transport protocol used by HTTP/3 requires all connections to be secured using TLS 1.3. This means that when you configure domains to offer HTTP/3, you are also configuring them to offer TLS 1.3 to clients using HTTP/1.1 or HTTP/2.
- Due to the inherent characteristics of HTTP/3 and 0-RTT, the authenticity of client IP addresses cannot be guaranteed when using access control lists (ACLs). To mitigate the risk of ACL bypass, respond with a `425 Too Early` HTTP status code when 0-RTT early data requests match ACLs. Early data requests are identified by the presence of the `Early-Data: 1` header, as outlined in RFC8470.

Enabling HTTP/3 for Fastly services

To enable HTTP/3 for your Fastly services, start by configuring HTTP/3 on your domains and then configure your services to offer HTTP/3 on client connections.

Configuring HTTP/3 on your domains

To configure HTTP/3 on a new domain, refer to Setting up TLS 1.3 for a new domain.

To configure HTTP/3 on an existing domain, complete the following:

1. Go to **Security** > **TLS management** > **Domains**.
2. Find the domain on which you plan to offer HTTP/3 and use the **TLS configuration and DNS details** column to verify whether HTTP/3 has been enabled.
    - If the column has a value of either `HTTP/3 & TLS v1.3` or `HTTP/3 & TLS v1.3 + 0RTT`, then the domain already supports HTTP/3. Continue to the next section to offer HTTP/3 support for traffic to that domain from your service.


- If the column does not display an HTTP/3 value, follow the steps to enable TLS 1.3 for this domain before proceeding to the next section.

Offering HTTP/3 from your Fastly service

HTTP/3 is designed as an optional upgrade to end user client connections. This means that end user clients will initially connect to your Fastly service using an earlier version of HTTP and will only attempt to use HTTP/3 if the Fastly service offers it.

Use the **HTTP/3** switch to configure your service to offer HTTP/3:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Settings**.
5. Click the **HTTP/3** switch to configure your service to offer HTTP/3.



6. Click **Activate** to deploy your configuration changes.

If you are configuring your service using VCL directly (either via regular VCL snippets or custom VCL methods), you can use the following VCL in the receive (`vcl_recv`) sub-routine to configure your service to offer HTTP/3:

```
h3.alt_svc();
```

Sending your HTTP/3 traffic to Fastly

Unless you use Fastly's dedicated IP addresses, then as a final step to enabling HTTP/3, you must ensure the DNS records of your domains are routing users to the correct HTTP/3

enabled Fastly addresses:

1. Go to **Security** > **TLS management** > **Domains**.
2. Click **View details** for the domain you would like to route to Fastly. The domain's details page appears.

The CNAME records section contains the value for CNAME records. You can prefix the value with `dualstack` to enable IPv6 support (e.g., `dualstack.<letter>.sni.global.fastly.net`).

For apex domains (e.g., `example.com`), the A records section contains the global anycast IP addresses.

Testing client compatibility with your Fastly service

If you want test a browser or other client for HTTP/3 support, Fastly has created a publicly available HTTP/3 test page to verify client support. Using the client, navigate to https://http3.is and the resulting page will let you know whether or not HTTP/3 was successfully used to request the page. If the request did not use HTTP/3, the page will also let you know which IETF draft versions are currently being used by Fastly. You can use that information to update your client or client configurations to use one of those supported versions.

Keep in mind that even if correctly configured, the first request from a browser (or its first request after a time-out period set by the browser's developers) to any HTTP/3 enabled web site will always use a lower version of HTTP because it has not yet seen the HTTP/3 offer. If you don't see the HTTP/3 success page on your first request, be sure to perform a reload in the browser to give it an opportunity to use HTTP/3 for subsequent requests.

Serving HTTP/3 traffic

Once you've configured your services appropriately, requests made to the domains on those services should be capable of supporting HTTP/3 if they are being made from a client that supports these protocols.

If the QUIC connections and HTTP/3 requests are successful, the clients will continue using them for all subsequent requests and connections for those domains. Should problems occur with the QUIC connections or HTTP/3 requests, clients are expected to automatically fall back to a standard HTTP/1.1 or HTTP/2 connection over TCP. You should verify that your chosen client implements this fallback if this is a priority for you.

Monitoring your HTTP/3 traffic

You can monitor HTTP/3 requests using Fastly's Real-Time Log Streaming feature and Observability features. We have also added a number of VCL variables specifically related to HTTP/3 and QUIC.

Disabling HTTP/3

You can disable HTTP/3 support on a Fastly service by either activating a previous service version where HTTP/3 is not enabled or by creating a new service configuration version and disabling the HTTP/3 switch before activation.

---

* * *

Failure modes with large files

/en/guides/failure-modes-with-large-objects

If you haven't enabled Segmented Caching, you may encounter the following failure modes when working with large objects.

TIP

Large objects can cause inefficiencies in content distribution networks. The Segmented Caching feature can help resolve these large object inefficiencies. Fastly recommends enabling Segmented Caching on services that will be serving large objects. Without Segmented Caching enabled, object size limits for your account depend on when you become a Fastly customer:

- If you created your account on or after June 17, 2020 and haven't enabled Segmented Caching, your Fastly services have a maximum object size of 20 MB.
- If you created your account prior to June 17, 2020 and haven't enabled Segmented Caching, your Fastly services have a maximum cacheable object size of 2 GB for requests without Streaming Miss or 5 GB for requests with Streaming Miss.

Maximum object size limits

If the response from the origin has a `Content-Length` header field that exceeds the maximum object size, Fastly will generate a `503 Response object too large` response to the client. If no `Content-Length` header field is returned, Fastly will start to fetch the response body. If, while fetching the response body, we determine that the object exceeds the maximum object size, we will generate a status `503 Response object too large` response to the client.

If no `Content-Length` header field is present and the Streaming Miss feature is enabled, Fastly will stream the content back to the client. However, if while streaming the response body Fastly determines that the object exceeds the maximum cacheable object size, it will terminate the client connection abruptly. The client will detect a protocol violation, because it will see its connection close without a properly terminating 0-length chunk.

Origin read failures

If reading the response body from the origin fails or times out, the problem will be reported differently depending on whether or not you've enabled Streaming Miss to act when the object is fetched. Without Streaming Miss, a 503 response will be generated. With Streaming Miss, however, it is already too late to send an error response since the header will already have been sent. In this case, Fastly will abruptly terminate the client connection and the client will detect a protocol violation. If the response was chunked, the client will see its connection close without a properly terminating 0-length chunk. If Content-Length was known, the client will see the connection close before the number of bytes given.

---

* * *

Fastly's service status

/en/guides/fastlys-service-status

Fastly continuously monitors the performance and status of our global network. We constantly monitor the health of all its related services and post regular notices about them to customers. Any time we schedule maintenance, upgrade hardware, re-route traffic, or experience service interruptions, we post updates on our service status page at

https://www.fastlystatus.com/. A complete, filterable history of past events is also available at https://www.fastlystatus.com/incidents/.

> **IMPORTANT**
>
> If you are experiencing problems and do not see a posted status page notification or if you have subscribed to status notifications and have not received an email or an SMS message, contact Customer Support for assistance.

Managing Fastly service status notifications

Fastly provides customers and the general public with multiple options for subscribing to status notifications.

> **TIP**
>
> Fastly offers syndicated status updates at https://www.fastlystatus.com/rss/ for use with any RSS-compatible feed readers.

Subscribing to notifications

You can subscribe to notifications and directly control which systems trigger those notifications by following these steps:

1. Using any browser, navigate to https://www.fastlystatus.com/.
2. Do one of the following:
    - To subscribe to service status notifications, click **Subscribe** at the top of the browser window.
    - To subscribe to notifications about a specific incident, click the title of any current or past incident and then click **Subscribe** at the bottom of the detailed incident report that appears.
3. When the subscription window appears, decide how you would like to be notified of updates. Specifically:
    - In the **Email Address** field, enter the email address to which email notifications, if any, should be sent.
    - From the **Phone Number** menu, select your country code and enter your telephone number to which SMS notifications, if any, should be sent.

4. Click the **Subscribed to** area to select which Fastly components should trigger notifications.

> TIP
>
> Specific details about each of the components appear when you click the arrow menu at the top right of the **Subscribed to** area. Use this menu to control the level of detail about each component for which notifications could be sent. For example, you could elect to receive only notifications for Fastly's Customer Services components and specifically choose only to receive notifications related to the availability of the docs.fastly.com website.

5. *(Optional)* In the **Webhook** field, enter the URL of a custom webhook to subscribe to the Fastly status page and automate the delivery of notifications to a system you control.

6. Click **Subscribe**. Activation messages will be sent to each subscription method you select with details allowing you to confirm your subscription.

Adjusting notification preferences

You can adjust your notification preferences at any time by following these steps:

1. Click **Manage Subscription** at the bottom of any status email Fastly has sent (or your original subscription email if you still have it).

2. *(Optional)* In the **Subscribed to** area, select or deselect which Fastly components should trigger notifications, if any.

> TIP
>
> Specific details about each of the components appear when you click the arrow menu at the top right of the **Subscribed to** area. Use this menu to control the level of detail about each component for which notifications could be sent. For example, you could elect to receive only notifications for Fastly's Customer Services components and specifically choose only to receive notifications related to the availability of the docs.fastly.com website.

3. *(Optional)* In the **Notification Preferences** area, select or deselect the specific incident type for each method of contact that should trigger notifications. For example, you could elect to receive no notifications via email or webhook, only via SMS messages to a mobile phone.

4. Click **Update** to update your notification preferences.

Unsubscribing from notifications

You can unsubscribe from all notifications at once or from specific types of notifications individually.

Unsubscribing from all notification types at once

To unsubscribe from all notification types at once:

1. Click **Manage Subscription** at the bottom of any status email Fastly has sent (or your original subscription email if you still have it).
2. Click **Unsubscribe** at the bottom of the window.
3. Click **OK** to confirm your request to unsubscribe.

Unsubscribing immediately from specific types of notifications

To unsubscribe immediately from:

- email notifications, click **Unsubscribe** at the bottom of any status email.
- SMS notifications, reply **STOP** to any status message you receive.
- webhook notifications, use the process for adjusting notification preferences and specifically deselect the **Webhooks** option before clicking **Update**.

Viewing current and past status information

The main Fastly service status page includes details about the current status of Fastly's network and incidents or events, as well as summarized views of the past status and event history.

> IMPORTANT
>
> Fastly does not post current event statuses that could signal to bad actors that their attempts to negatively impact customers or Fastly directly have been successful. During suspected or confirmed events, our support team will contact you directly with details.

What the status indicators tell you

Indicator icons appear on the incident history grid and on all status page notifications that confirm the current operating status of the network and service components or various events that could be occurring at a specific time.

Status indicator icon	Status description
	**Normal.** Everything is operating normally. No events or incidents related to network or service components have been identified or announced.
	**Informational.** We've posted information for general awareness. No network and service components are impacted.
	**Maintenance.** We've scheduled or are actively performing maintenance on the Fastly global network or one of its service components.
	**Degraded.** We've identified something that has caused a degradation of a portion of the Fastly network or service component. Customer services are being delivered but at reduced capacity.
	**Unavailable.** A portion of our network or a specific service component is not currently operational or available.
	**Investigating.** We've observed or received a report of something that's impacting the performance of our network or a service component. We are actively investigating this event.
	**Identified.** An investigation identified the cause of an event or problem and a fix for it is being implemented.
	**Monitoring.** A fix has been deployed for an event or problem that is now resolved. The impacted network or service components are now stable and being monitored for continued health.

Viewing summaries of current and past events

Summary posts related to the current status of any active incidents appear at the top of the Fastly service status page. Fastly also keeps track of all past statuses, displaying the most recent of them on the main status page, which is organized into the following sections:

- **Current status.** When incidents or events are in progress, you'll see them summarized in the Current Status area. This section is hidden when all conditions are normal.
- **History Grid.** The history grid displays the individual, daily status of each of Fastly's network and service components and their sub-components for today and the previous six days using indicator icons for each date. Click the plus icon next to any component to expand the view to display indicators for all sub-components. Click the arrow icons to the right and left of the dates to view previous weeks at a glance.
- **Scheduled Maintenance.** The Scheduled Maintenance area displays summaries of active and future maintenance work. Click on a maintenance post title to view its full history and details. To review past maintenance work, click **Incident History** at the top of the page.

Older, past history for incidents and scheduled maintenance as well as full details about each specific event are available at https://www.fastlystatus.com/incidents/.

Viewing detailed information about specific events

You can display the full report details of these events by clicking on their title in any area of the service status page. Detailed event and incident reports include the current status of the event or incident, the components impacted, and the full text of all updates that have been published. Timestamps appear for every update posted.

You can subscribe to notifications about any specific incident or event, past or present, by clicking the Subscribe button at the bottom of any detailed report.

Filtering displayed history information

On the main service status page, the filter controls appear immediately below the history grid. With them you can control which components, statuses, and types of history event information to display in both the history grid and the past history summaries for incident and maintenance events.

- **Component filters.** Filter by component by selecting the specific component from the **All Components** menu. Filter specific sub-components by clicking the plus icon next to the component name and then selecting a specific sub-component from the items that appear.
- **Status filters.** Filter by status type by selecting one of them from the **Any Status** menu.

- **Event type filters.** Filter by event type by selecting one of them from the **All Types** menu.

On the full incident history page you can also filter by event date and order in addition to component, status, and event type:

- **Date filters.** Filter by date by clicking the **Date range** selector, selecting the specific date or date range for events, and then clicking **Apply**.
- **Event filters.** Filter by order by clicking the **Sort by** menu and then selecting either **Newest** or **Oldest**.

> NOTE
>
> Interested in an authenticated version of the Fastly Service Status page for your team? If you're a delivery customer with Enterprise Support and either a Technical Account Manager or Security Technical Account Manager, contact your account manager or contact support to see if your company meets the qualification criteria for this option.

* * *

HTTP/2 server push

/en/guides/http2-server-push

HTTP/2 server push allows you to set up rules that enable Fastly to pre-emptively load and then send responses to an HTTP/2-compliant client before that client requests them. You can initiate an HTTP/2 server push via a response header or VCL function.

Server push with the `link` response header

Fastly recognizes `link` headers with the preload keyword sent by an origin server and pushes the designated resource to a client. For example, this `link` response header triggers an HTTP/2 push:

```
link: </assets/jquery.js>; rel=preload; as=script
```

We support multiple `link` headers and multiple assets in one `link` header:

```
link: </assets/jquery.js>; rel=preload; as=script, </assets/base.cs
```

Additional attributes used in the `link` header can further control server push and how the header itself is handled. If no additional attributes are included, the `link` header will trigger server push and be forwarded to the client:

```
link: </assets/jquery.js>; rel=preload; as=script
```

If used with the `nopush` directive, the header will *not* trigger a push and will be passed as is to the client:

```
link: </assets/jquery.js>; rel=preload; as=script; nopush
```

If used with the `x-http2-push-only` directive, the header will trigger a server push but will be subsequently removed and not forwarded to the client:

```
link: </assets/jquery.js>; rel=preload; as=script; x-http2-push-onl
```

The attributes can be mixed and matched if needed:

```
link: </assets/jquery.js>; rel=preload; as=script, </assets/base.cs
```

Link headers and Amazon S3 buckets

If you're using an Amazon Simple Storage Service (S3) bucket as your origin server, you can still use `link` headers by applying a cache setting condition like this one:

```
set beresp.http.Link = beresp.http.x-amz-meta-Link
```

Server push with the `h2.push()` function

Server push can also be triggered with the `h2.push()` VCL function. The asset to be pushed is passed to the function as a parameter. For example:

```
sub vcl_recv {
#FASTLY recv

  if (fastly_info.is_h2 && req.url ~ "^/index.html")
  {
    h2.push("/assets/jquery.js");
  }
}

```

The `h2.push()` function triggers server push as soon as it's called, which removes the need for a `link` header to arrive with a server response. This means assets can be pushed to the client before the response for the request that triggered the push is received from the server, accelerating their delivery.

---

* * *

Making query strings agnostic

/en/guides/making-query-strings-agnostic

Under normal circumstances, Fastly would consider these URLs different objects that are cached separately:

- `http://example.com`
- `http://example.com?asdf=asdf`
- `http://example.com?asdf=zxcv`


It is possible, however, to have them all ignore the query string and return the same cached resource.

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.

3. Click **Edit configuration** and then select the option to clone the active version.

4. Click **Content**.

5. Click **Create header**.



6. Fill out the **Create a header** fields as follows:
    - In the **Name** field, enter a description for the header (e.g., `New query string name`).
    - From the **Type** menu, select **Request**, and from **Action** menu, select **Set**.
    - In the **Destination** field, enter `url`.
    - In the **Source** field, enter `req.url.path`.
    - From the **Ignore if set** menu, select **No**.
    - Set the **Priority** field to whatever priority you want.
7. Click **Create** to create the new header.
8. Click **Activate** to deploy your configuration changes.

The request will be sent to the origin as a URL without the query string.

For more information about controlling caching, see our documentation on cache freshness.

---

* * *

	Precision Path
🔗	/en/guides/precision-path

Fastly can automatically detect and, in real time, route around transient connection problems that occur when fetching content from your origin servers or when delivering content to end users from Fastly's Edge Cloud. Fastly uses different, automated techniques depending on where we observe a connection problem. This page describes two capabilities that Precision Path uses to automatically improve fetching and delivery of content to your users: origin connection rerouting and edge connection rerouting.

Origin connection rerouting

It's critical for Fastly to maintain high performance and reliable access to your origin services to fetch new or updated content when needed. The inability to do so, even

temporarily, can result in 5xx HTTP server errors being returned to end users, regardless of how resilient and performant connections may be. Based on historical observations of our worldwide network, we estimate a significant portion of 5xx errors served to end users are due to the impact of transient internet performance issues (commonly called *internet weather*) on the connections between Fastly's point of presence (POP) locations and our customers' origin services. Origin rerouting is designed to address this.

How origin connection rerouting works

Our origin connection rerouting capability monitors Fastly's connections to your origin services for signs of internet weather and, if detected, automatically attempts to route around them so they don't impact your services. The vast majority of the time you won't notice changes to those connections in your Fastly services because there will be no issues to route around. However, when the default route from one of our POPs across the internet to your origins experiences a severe enough problem, it will automatically test other available routes to your origin and, if any successful alternatives are found, will select the most viable alternative route with which to re-establish the connection. All of this will happen before TCP timeouts occur on the end user connection, thereby avoiding 5xx errors being returned to end users.

Requirements

Precision Path's origin connection rerouting only works for origin connections using TLS. If your Fastly service has not been configured to use a TLS connection between Fastly and your origin server, you can enable TLS by following the instructions in our guide on working with hosts.

No special requirements are necessary to take advantage of Fastly's origin connection rerouting. This capability is enabled by default for all Fastly services using TLS for origin and shielding connections.

Many Fastly customers protect their origin services from security threats by implementing either a firewall service or IP address access control lists (ACLs). While this is a good security practice, you could be inadvertently blocking a subset of Fastly IP addresses from accessing your origins if these configurations aren't updated regularly.

To successfully implement origin connection rerouting on your Fastly services, ensure you aren't blocking any Fastly IP addresses. Fastly provides an API for you to obtain a complete list of the IPv4 and IPv6 address ranges owned by Fastly. Any firewalls or ACLs protecting your origin services should be updated to ensure all these IP address ranges are allowed to connect to your origins.

Monitoring

Fastly's real-time log streaming feature can be used to monitor for origin connection rerouting events that may occur on your Fastly services. The following VCL variables can be used to monitor origin connection rerouting activity:

- `beresp.used_alternate_path_to_origin` - This boolean value indicates whether or not the request to origin was made over an alternate route selected by the origin connection rerouting mechanism. Counting the number of true values for this variable over any given time period in your logs will indicate how many times this origin rerouting mechanism has been triggered.
- `beresp.backend.src_ip` - This variable indicates which Fastly source IP was used to make the request to origin. For most connections, this will be one of the most frequently used Fastly server IP addresses used for default routes across the Internet. If the origin rerouting mechanism was triggered by a problem with the original connection attempt over the default route, then this value will show an alternate Fastly server IP address from a pool of IPs reserved for alternate routes between that POP and your origin.
- `beresp.backend.alternate_ips` - This variable lists all the possible source IP addresses available to the origin rerouting mechanism for the Fastly server handling this origin connection. This information can be used to identify the set of valid Fastly IP addresses from which you may see connection attempts to your origin from this Fastly server.

Edge connection rerouting

When delivering content from Fastly to your end users, Fastly tracks the health of every TCP connection. When we observe connection-impacting degradation (e.g., congestion), we automatically switch delivery to a new network path to route around the issue. This automatic mitigation is enabled by default on all of our POPs and applies to all Fastly traffic. No additional configuration is required.

No special requirements are necessary to take advantage of Fastly's edge connection rerouting. All traffic delivered from Fastly's POPs is assessed for connection issues and the fast path failover feature is applied only when necessary.

Support

For more information on Precision Path or its individual features, contact support.

* * *

Serving stale content


/en/guides/serving-stale-content

Fastly can optionally serve stale content when there is a problem with your origin server or if new content is taking a long time to fetch from your origin server. For example, if Fastly can't contact your origin server, our POPs will continue to serve cached content when users request it. These features are not enabled by default.


> **TIP**
>
> For more information on serving stale content, see our documentation on staleness and revalidation.

Serving old content while fetching new content

Certain pieces of content can take a long time to generate. Once the content is cached it will be served quickly, but the first user to try and access it will pay a penalty.



This is unavoidable if the cache is completely cold, but if this is happening when the object is in cache and its TTL is expired, then Fastly can be configured to show the stale content while the new content is fetched in the background.




Fastly builds on the behavior proposed in RFC 5861 "HTTP Cache-Control Extensions for Stale Content" by Mark Nottingham, which is under consideration for inclusion in Google's Chrome browser.

Enabling serve stale

> **NOTE**
>
> If you've already enabled serving stale content on an error via custom VCL, adding this feature via the Fastly control panel will set a different stale TTL. To avoid this, check your custom VCL and remove the `stale-if-error` statement before enabling this feature via the Fastly control panel.

To enable serving stale content on an error via the Fastly control panel for the default TTL period (43200 seconds or 12 hours), follow the steps below.

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Settings**.



5. Click the **Serve stale** switch to automatically enable serving stale content for the default TTL period of 43200 seconds (12 hours).
6. Click **Activate** to deploy your configuration changes.

Manually enabling serve stale

These instructions provide an advanced configuration that allows all three possible origin failure cases to be handled using VCL.

In the context of Varnish, there are three ways an origin can fail:

- The origin can be marked as unhealthy by failing health checks.
- If Varnish cannot contact the origin for any reason, a 503 error will be generated.
- The origin returns a valid HTTP response, but that response is not one we wish to serve to users (for instance, a 503).

The custom VCL shown below handles all three cases. If the origin is unhealthy, the default serve stale behavior is triggered by `stale-if-error`. In between the origin failing and being marked unhealthy, Varnish would normally return 503s. The custom VCL allows us to instead either serve stale if we have a stale copy, or to return a synthetic error page. The error page can be customized. The third case is handled by intercepting all 5XX errors in `vcl_fetch` and either serving stale or serving the synthetic error page.

> **WARNING**
>
> Do not purge all cached content if you are seeing 503 errors. Purge all overrides stale-if-error and increases the requests to your origin server, which could result in additional 503 errors.

Although not strictly necessary, health checks should be enabled in conjunction with this VCL. Without health checks enabled, all of the functionality will still work, but serving stale

or synthetic responses will take much longer while waiting for an origin to timeout. With health checks enabled, this problem is averted by the origin being marked as unhealthy.

The custom VCL shown below includes the Fastly standard boilerplate. Before uploading this to your service, be sure to customize or remove the following values to suit your specific needs:

- `if (beresp.status >= 500 && beresp.status < 600)` should be changed to include any HTTP response codes you wish to serve stale/synthetic for.
- `set beresp.stale_if_error = 86400s;` controls how long content will be eligible to be served stale and should be set to a meaningful amount for your configuration. If you're sending `stale_if_error` in Surrogate-Control or Cache-Control from origin, remove this entire line.
- `set beresp.stale_while_revalidate = 60s;` controls how long the `stale_while_revalidate` feature will be enabled for an object and should be set to a meaningful amount for your configuration. This feature causes Varnish to serve stale on a cache miss and fetch the newest version of the object from origin in the background. This can result in large performance gains on objects with short TTLs, and in general on any cache miss. Note that `stale_while_revalidate` overrides `stale_if_error`. That is, as long as the object is eligible to be served stale while revalidating, `stale_if_error` will have no effect. If you're sending `stale_while_revalidate` in Surrogate-Control or Cache-Control from origin, remove this entire line.
- `synthetic {"<!DOCTYPE html>Your HTML!</html>"};` is the synthetic response Varnish will return if no stale version of an object is available and should be set appropriately for your configuration. You can embed your HTML, CSS, or JS here. Use caution when referencing external CSS and JS documents. If your origin is offline they may be unavailable as well.

```
sub vcl_recv {
#FASTLY recv

  # Normally, you should consider requests other than GET and HE
  # (to this we add the special FASTLYPURGE method)
  if (req.method != "HEAD" && req.method != "GET" && req.method
    return(pass);
  }

  # If you are using image optimization, insert the code to enab
```

```
  # See https://www.fastly.com/documentation/reference/io/ for m

  return(lookup);
}

sub vcl_hash {
  set req.hash += req.url;
  set req.hash += req.http.host;
  #FASTLY hash
  return(hash);
}

sub vcl_hit {
#FASTLY hit
  return(deliver);
}


sub vcl_miss {
#FASTLY miss
  return(fetch);
}

sub vcl_pass {
#FASTLY pass
  return(pass);
}

sub vcl_fetch {
  /* handle 5XX (or any other unwanted status code) */
  if (beresp.status >= 500 && beresp.status < 600) {

    /* deliver stale if the object is available */
    if (stale.exists) {
      return(deliver_stale);
    }

    if (req.restarts < 1 && (req.method == "GET" || req.method =
      restart;
    }
```

```
  }

  /* set stale_if_error and stale_while_revalidate (customize th
  set beresp.stale_if_error = 86400s;
  set beresp.stale_while_revalidate = 60s;

#FASTLY fetch

  # Unset headers that reduce cacheability for images processed
  if (req.http.X-Fastly-Imageopto-Api) {
    unset beresp.http.Set-Cookie;
    unset beresp.http.Vary;
  }

  # Log the number of restarts for debugging purposes
  if (req.restarts > 0) {
    set beresp.http.Fastly-Restarts = req.restarts;
  }

  # If the response is setting a cookie, make sure it is not cac
  if (beresp.http.Set-Cookie) {
    return(pass);
  }


  # By default we set a TTL based on the `Cache-Control` header
  # like `private` and `no-store`. Private in particular should
  if (beresp.http.Cache-Control ~ "(?:private|no-store)") {
    return(pass);
  }

  # If no TTL has been provided in the response headers, set a d
  if (!beresp.http.Expires && !beresp.http.Surrogate-Control ~ "
    set beresp.ttl = 3600s;

    # Apply a longer default TTL for images processed using Imag
    if (req.http.X-Fastly-Imageopto-Api) {
      set beresp.ttl = 2592000s; # 30 days
      set beresp.http.Cache-Control = "max-age=2592000, public";
    }
```

```
  }

  return(deliver);
}


sub vcl_error {
#FASTLY error

  /* handle 503s */
  if (obj.status >= 500 && obj.status < 600) {

    /* deliver stale object if it is available */
    if (stale.exists) {
      return(deliver_stale);
    }

    /* otherwise, return a synthetic */

    /* include your HTML response here */
    synthetic {"<!DOCTYPE html><html>Replace this text with the
    return(deliver);
  }

}


sub vcl_deliver {
#FASTLY deliver
  return(deliver);
}

sub vcl_log {
#FASTLY log
}

```

Adding headers

After you add the custom VCL, you can finish manually enabling serving stale content by adding a `stale-while-revalidate` or `stale-if-error` directive to either the `Cache-Control` or `Surrogate-Control` headers in the response from your origin server. For example:

```
Cache-Control: max-age=600, stale-while-revalidate=30
```

will cache some content for 10 minutes and, at the end of that 10 minutes, will serve stale content for up to 30 seconds while new content is being fetched.

Similarly, this statement:

```
Surrogate-Control: max-age=3600, stale-if-error=86400
```

instructs the cache to update the content every hour (3600 seconds) but if the origin is down then show stale content for a day (86400 seconds).

Alternatively, these behaviors can be controlled from within VCL by setting the following variables in `vcl_fetch`:

```
set beresp.stale_while_revalidate = 30s;
set beresp.stale_if_error = 86400s;
```

Interaction with grace

Stale-if-error works exactly the same as Varnish's grace variable such that these two statements are equivalent:

```
set beresp.grace = 86400s;
set beresp.stale_if_error = 86400s;
```

However, if a grace statement is present in VCL it will override any `stale-if-error` statements in any Cache-Control or Surrogate-Control response headers.

Why serving stale content may not work as expected

Here are some things to consider if Fastly isn't serving stale content:

- **Cache:** Stale objects are only available for cacheable content.

- **VCL:** Setting `req.hash_always_miss` or `req.hash_ignore_busy` variable to `true` invalidates the effect of `stale-while-revalidate`.
- **Shielding:** If you don't have shielding enabled, a POP can only serve stale on errors if a request for that cacheable object was made through that POP before. We recommend enabling shielding to increase the probability that stale content on error exists. Shielding is also a good way to quickly refill the cache after performing a purge all.
- **Requests:** As traffic to your site increases, you're more likely to see stale objects available (even if shielding is disabled). It's reasonable to assume that popular assets will be cached at multiple POPs.
- **Least Recently Used (LRU):** Fastly has an LRU list, so objects are not necessarily guaranteed to stay in cache for the entirety of their TTL (time to live). But eviction is dependent on many factors, including the object's request frequency, its TTL, the POP from which it's being served. For instance, objects with a TTL of 3700s or longer get written to disk, whereas objects with shorter TTLs end up in transient, in-memory-only storage. We recommend setting your TTL to more than 3700s when possible.
- **Purges:** Whenever possible, you should purge content using our soft purge feature. Soft purge allows you to easily mark content as outdated (stale) instead of permanently deleting it from Fastly's caches. If you can't use soft purge, we recommend purging by URL or using surrogate keys instead of performing a purge all.

---

* * *

Streaming Miss

/en/guides/streaming-miss

When fetching an object from the origin, the Streaming Miss feature ensures the response is streamed back to the client immediately and is written to cache only after the whole object has been fetched. This reduces the first-byte latency (the time that the client must wait before it starts receiving the response body).

TIP

Fastly recommends enabling Segmented Caching on services that will be serving large resources. Without Segmented Caching enabled, the resource size limits for

your account depend on when you become a Fastly customer:

- If you created your account on or after June 17, 2020 and haven't enabled Segmented Caching, your Fastly services have a maximum object size of 20 MB.
- If you created your account prior to June 17, 2020 and haven't enabled Segmented Caching, your Fastly services have a maximum cacheable object size of 2 GB for requests without Streaming Miss or 5 GB for requests with Streaming Miss.


NOTE

If you enable Streaming Miss, be aware that if an error occurs while transferring the response body, Fastly cannot send an error because the headers are already sent to the client. All we can do is truncate the response.

Enable Streaming Miss by creating a VCL Snippet

Enable Streaming Miss by setting `beresp.do_stream` to `true` in `vcl_fetch` with a VCL Snippet using these steps.

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL Snippets**.
5. Click **Create your first VCL snippet**.




6. Fill out the **Create a VCL snippet** fields as follows:
    - In the **Name** field enter an appropriate name (e.g., `Enabling Streaming Miss`).
    - From the **Type (placement of the snippets)** controls, select **within subroutine**.
    - From the **Select subroutine** menu, select **fetch (`vcl_fetch`)**.
    - In the **VCL** field, add `set beresp.do_stream = true;`.
7. Click **Create** to create the snippet.
8. Click **Activate** to deploy your configuration changes.

Enable Streaming Miss by creating a Fastly header

Enable Streaming Miss by setting `beresp.do_stream` to `true` in `vcl_fetch` with a Fastly header using these steps.

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click **Create header**.



6. Fill out the Create a header fields as follows:

   - In the **Name** field, enter the name of your header rule (for example, `Enabling Streaming Miss`).
   - From the **Type** menu, select **Cache**, and from the **Action** menu, select **Set**.

- In the **Destination** field, enter `do_stream`.
- In the **Source** field, enter `true`.
- From the **Ignore if set** menu, select **No** if you want the header in the **Destination** field modified or select **Yes** if you don't want it modified.
- In the **Priority** field, enter the order the header rules execute.

7. Click **Create**.
8. Click **Activate** to deploy your configuration changes.

Streaming Miss limitations

There are several limitations to using Streaming Miss.

Streaming Miss is not available to HTTP/1.0 clients

If an HTTP/1.0 request triggers a fetch and the response header from the origin does not contain a Content-Length field, then Streaming Miss will be disabled for the fetch and the fetched object will be subject to the non-streaming-miss object size limit of 2GB. Without the client receiving the Content-Length, the client cannot distinguish the proper end of the download from an abrupt connection breakage anywhere upstream from it.

If an HTTP/1.0 request is received while a Streaming Miss for an object is in progress, the HTTP/1.0 request will wait for the response body to be downloaded before it will receive the response header and the response body, as if the object was being fetched without Streaming Miss.

Cache hits are not affected. An HTTP/1.0 client can receive a large object served from cache, just like an HTTP/1.1 client.

Streaming Miss is not compatible with on-the-fly compression of fetched objects

Streaming Miss can handle large files whether or not they are compressed. On-the-fly compression of objects not already compressed is not compatible with Streaming Miss. Specifically, if VCL sets `beresp.gzip` or `beresp.brotli` to true, Streaming Miss will be disabled.

Streaming Miss is not compatible with ESI (Edge-Side Includes)

Responses processed through ESI, which dynamically inserts content into cached pages, cannot be streamed. Responses included from an ESI template also cannot be streamed. When ESI is enabled for a response or when a response is fetched using `<esi:include>`, then Streaming Miss will be disabled and the fetched object will be subject to the non-streaming-miss object size limit of 2GB.

---

* * *

Category: Purging

These articles describe how to purge cache.

Authenticating URL purge requests via API

/en/guides/authenticating-api-purge-requests

Fastly's URL purge feature allows you to purge individual URLs on your website. By default, authentication is not required to purge a URL with the Fastly API, but you can enable API token authentication in the Fastly control panel by adding a header or by using custom VCL.

WARNING

We recommend that all customers enable authentication for URL purge requests.

NOTE

All purge requests other than URL purges require authentication by default, as indicated in the API documentation.

Limitations and considerations


The solution outlined in this guide must be implemented on every service that requires authentication of URL purge requests. To enable purge authentication at the account level, contact support.

Enabling authentication in the Fastly control panel

You can enable API token authentication for URL purge requests by adding a header and optionally attaching a condition in the Fastly control panel.

Adding the header

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click **Create header**.



6. Fill out the **Create a header** fields as follows:

   - In the **Name** field, enter the name of your header rule (for example, `Fastly Purge`).


- From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
- In the **Destination** field, enter `http.Fastly-Purge-Requires-Auth`.
- In the **Source** field, enter `"1"`.
- From the **Ignore if set** menu, select **No**.
- In the **Priority** field, enter `10`.

7. Click **Create**.

Attaching a condition

Attaching the following condition is optional. Without the condition, the header you just created will be added to all requests. With the condition, the header will be added to purge requests only.

1. On the Content page, click **Attach a condition** to the right of your new header.



2. Fill out the **Create a new request condition** fields as follows:
    - In the **Name** field, enter a descriptive name for the new condition (for example, `Purge`).
    - In the **Apply if** field, enter `req.request == "FASTLYPURGE"`.
3. Click **Save and apply to**.
4. Click **Activate** to deploy your configuration changes.

Enabling authentication with VCL Snippets

You can also enable API token authentication for URL purge requests using VCL Snippets. Refer to the developer documentation for details on setting the `Fastly-Purge-Requires-Auth` header.

Purging URLs with an API token

After you've enabled API token authentication for URL purge requests, you'll need to provide your API token in the URL purge API request:

```
$ curl -X PURGE -H Fastly-Key:FASTLY_API_TOKEN https://www.example.com/
```

which would return this response:

```
{"status": "ok", "id": "1234567890"}
```

> **WARNING**
>
> If your website is not configured to use HTTPS, do not use the Fastly API to purge URLs. Doing so could expose your API token since the data in transit will not be encrypted.

* * *

Purging a URL via the Fastly control panel

/en/guides/purging-a-url

Fastly provides several levels of cache purging. You can use the *Purge URL* option to purge a single URL via the Fastly control panel.


Before you begin

Be sure you know how to access the web interface controls before learning about each of the pages you'll encounter there.

Purging a URL

To purge a single URL, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. From the **Purge** menu, select **Purge URL**.



4. From the **Domain** menu, select the domain on which your content resides. If the domain you select is a wildcard domain (e.g., `*.example.com`) the Subdomain field will appear.

5. If the **Subdomain** field appears, enter the subdomain to purge for the wildcard domain you've selected (e.g., `www`).
6. In the **Full URL path** field, enter the path to the content you'll be purging (e.g., `/example.jpg`). The Preview field displays the URL that will be purged.
7. *(Optional)* Select the Soft purge checkbox to mark your content as outdated instead of deleting it from cache.
8. Click **Purge**.

What's next

Explore the other purging methods available with Fastly such as purging with surrogate keys and purging all content.

---

* * *

	Purging all content via the control panel
🔗	/en/guides/purging-all-content

Fastly provides several levels of cache purging. You can use the *Purge all* option to purge all content under a service.

> ⚠ WARNING
>
> Exercise caution when purging all content from cache, especially if you're seeing an increase in 503 errors. Purging all content overrides other caching-related settings that allow you to serve stale content and forces Fastly to retrieve that content again from your origin servers before it can be re-cached in Fastly POPs. This means that purging all content will temporarily cause your cache hit ratio to drop dramatically and cause an associated spike of traffic to your origin servers. Be certain your origins can handle that temporary spike in traffic until the cache repopulates.


Before you begin

Be sure you know how to access the web interface controls before learning about each of the pages you'll encounter there.

Purging all content

To instantly purge all content under your service, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. From the **Purge** menu, select **Purge all**. The Purge all window appears and displays the service name you'll be purging.



4. In the field of the **Purge all** window, confirm you want to purge all cached content on a service by entering the exact name of the service that appears (e.g., `An Example Service`).

5. Click **Purge all**.

What's next

Explore the other purging methods available with Fastly such as purging with surrogate keys and purging a URL.

---

* * *

📄	**Purging with surrogate keys**
🔗	/en/guides/purging-with-surrogate-keys

Fastly provides several levels of cache purging and choosing the right purging method is essential to keeping your website fast. While Fastly's purge all is a speedy way to invalidate your cache, it may temporarily increase your website's load time while the cache rebuilds. If you find yourself purging all cache on more than a weekly basis, consider using surrogate keys for more targeted purging.

Surrogate keys are unique identifiers that you assign to portions of content that share common traits, making them easier to process as groups in some way. Using the `Surrogate-Key` header, you can tag an object, such as an image or a blog post, with one or more keys. When you need to explicitly remove content from the Fastly edge cache, rather than allowing it to expire or to be evicted, you can use surrogate keys to purge groups of content selectively instead of purging all content.

Before you begin

This guide assumes you're already familiar with how to work with the `Surrogate-Key` header to tag related pieces of cacheable content.


Purging objects with surrogate keys

You can use the Fastly control panel to manually purge objects via key:

1. Log in to the Fastly control panel.

2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.

3. From the **Purge** menu, select **Purge key**.



4. In the **Keys** field, enter one or more surrogate keys. Use spaces to separate multiple keys.

5. *(Optional)* Select the Soft purge checkbox to mark your content as outdated instead of deleting it from cache.

6. Click **Purge**.

You can also use our Purge API to purge objects via key.

What's next

Explore the other purging methods available with Fastly such as purging a URL and purging all content.

* * *

Soft purges

/en/guides/soft-purges

Fastly provides a Soft Purge feature that allows you to mark content as outdated (*stale*). Stale objects remain available to use in some circumstances while Fastly fetches a new version from origin, unlike objects invalidated by a *hard* purge which are made immediately unusable. You can purge by URL or by surrogate key using Soft Purge.

Before using Soft Purge, we recommend you implement one of the following methods to verify a stale object should temporarily remain in cache during revalidation:

- Set up `ETag` or `Last-Modified` headers for relevant content on your origin servers.
- Configure `stale_while_revalidate` to serve stale content and fetch the newest version of the object from origin in the background. If you choose this revalidation method, you must also configure `stale_if_error` at the same time.

To enable Soft Purge, add a `Fastly-Soft-Purge` request header (such as `Fastly-Soft-Purge: 1`) to any single URL or key-based purge.

To purge the URL `www.example.com` with Soft Purge, you would issue the following command:

```
$ curl -X PURGE -H "Fastly-Soft-Purge:1" http://www.example.com
```

To purge a surrogate key with Soft Purge, you would issue the following command:

```
$ curl -X POST -H 'Fastly-Soft-Purge:1' -H 'Fastly-Key: YOUR_FASTLY_KE
```

TIP

Purge all requests cannot be done as a soft purge and will always immediately invalidate all cached content associated with the service. To do a soft purge all,

consider applying a constant surrogate key tag (e.g., `all`) to all objects.

---

* * *

	Working with surrogate keys
🔗	/en/guides/working-with-surrogate-keys

Surrogate keys are unique identifiers that you assign to groups of content for processing. While there are many use cases for surrogate keys, one of the primary way for using them with Fastly is to make purging more efficient.

Surrogate keys allow you to selectively purge related content. Using the `Surrogate-Key` header, you can "tag" content with a key term, a string of any characters you want. When you want to purge content associated with that key, you then issue a key purge request and all of the objects associated with that key will be purged. This process makes it easier to cache and purge content that changes rapidly and unpredictably without having to purge your entire cache.

Before you begin

This guide assumes you're already familiar with the way content delivery networks (CDNs) work in general, and the way Fastly's CDN works in particular. We recommend reviewing our guide on adding headers on HTTP requests and responses.

Understanding the `Surrogate-Key` header

To understand how surrogate keys work, especially in the context of content purging, you need to understand what a Surrogate-Key header is and how it behaves.

About the `Surrogate-Key` header

Any time your origin responds to a request for content, the response it sends will include bits of code called *headers* in front of the actual body of the response. Those headers are used to give additional detail and provide context for the body of the response itself. HTTP headers sent as part of a response typically look something like this:

```
HTTP/1.1 200 OK
Content-Type: text/html
Connection: keep-alive
...
```

You can control that additional information and therefore control how content is served by adding to or modifying the headers your server responds with. The `Surrogate-Key` header is one of them. It's what categorizes or "tags" the content as part of a specific group. The tag you choose is called a *key* and it describes the common trait each element of a content group shares.

For example, suppose you have a website where you publish taco recipes. You know that entire categories of recipes will need to be purged, so you thoughtfully include these recipe categories as keys in the `Surrogate-Key` header. The response your server sends might look more like this:

```
HTTP/1.1 200 OK
Surrogate-Key: veggie seasonal central-mexico
Content-Type: text/html
...
```

The addition of the Surrogate-Key header there tells you that the content is tagged with specific identifiers that categorize it for future use. This response contains three surrogate keys: `veggie`, `seasonal`, and `central-mexico`. When Fastly receives a response like this, we use the surrogate keys to create a mapping from each key to the cached content, then we strip out the `Surrogate-Key` header so it's not included in the response to your readers.

> **TIP**
>
> You can't use duplicate surrogate keys. For example, if you tried to use `foo`, `bar`, and `foo`, the two `foo`s would be collapsed into a single instance of the term.

Creating relationships between keys and objects

One of the major advantages of surrogate keys is that they allow for a many-to-many relationship between keys and objects. An origin server's response can associate multiple keys with the object and the same key can be provided in different responses. Take a look at these two requests and responses:

```
GET /blog/healthy-taco-recipes HTTP/1.1
Host: www.tacolabs.com

HTTP/1.1 200 OK Content-Type: text/html
Content-Length: 1234
Surrogate-Key: mainpage low-carb
```

```
GET /recipes/low-carb-cheese-taco-shell HTTP/1.1
Host: www.tacolabs.com

HTTP/1.1 200 OK
Content-Type: text/html
Content-Length: 2345
Surrogate-Key: low-carb cheese
```

In this example, there are two objects (`/blog/healthy-taco-recipes` and `/recipes/low-carb-cheese-taco-shell`) with three keys (`mainpage`, `low-carb`, and `cheese`). Two of the keys (`mainpage` and `cheese`) are associated with a single object and a third key (`low-carb`) is associated with both objects.

By using the `Surrogate-Key` header to associate keys with one or more objects, you can precisely control which objects are removed from cache during a purge. Consider the example presented above. Purging the `mainpage` key would remove only the `/blog/healthy-taco-recipes` object from the cache. On the other hand, purging the `low-carb` key would remove both the `/blog/healthy-taco-recipes` and `/recipes/low-carb-cheese-taco-shell` objects from the cache.


Wherever there's a relation between two different pieces of content, there might be a good reason to keep them categorized by using a surrogate key.

Generating and setting surrogate keys

There are two ways to set the `Surrogate-Key` header: by adding the header in the Fastly control panel, or by generating the keys with your own application. You can make your surrogate key associations on your own application server and include them in the HTTP response that you send to Fastly. This is the more useful method because you can assign exactly the keys that you want on every response.

However, if you want to set the `Surrogate-Key` header in the Fastly control panel you can do so following the steps below.

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click **Create header**.



6. Fill out the **Create a header** fields as follows:

    - In the **Name** field, enter a human-readable name for the header. This name is displayed in the Fastly web interface.

- From the **Type** menu, select **Cache**, and from the **Action** menu, select **Set**.
- In the **Destination** field, enter `http.Surrogate-Key`.
- In the **Source** field, enter where the content for the header comes from. For example, if you're using Amazon S3 as an origin server, you could set the field to `beresp.http.x-amz-meta-surrogate-key` to specify `x-amz-meta-surrogate-key` as the response header received from the backend.
- From the **Ignore if set** menu, select **No**.
- In the **Priority** field, enter `10`.

7. Click the **Create** button to create your header.
8. Click **Activate** to deploy your configuration changes.

Troubleshooting

You can check the surrogate keys for a URL by using the `Fastly-Debug: 1` header. See the instructions on using a Fastly-Debug header with curl for more information.

Limitations

The surrogate keys sent by your origin server can be as simple or complex as you need, subject to format limitations. Surrogate keys must be formatted as a single string without spaces. Spaces separate keys.

Surrogate keys are subject to size limitations. Individual surrogate keys may not exceed 1,024 bytes in length and `Surrogate-Key` header values (comprising one or more space-separated keys) may not exceed 16,384 bytes in length. If either of the key or key header value limits are reached while parsing a `Surrogate-Key` header, the key currently being parsed and all keys following it within the same header will be ignored.

What's next

Now that you understand how the `Surrogate-Key` header works and how to set it, learn how to purge objects with surrogate keys.

---

* * *

Category: Responses

These articles describe configuration settings and changes you can make to your response settings when setting up Fastly services.

Creating and customizing a robots.txt file


/en/guides/creating-and-customizing-a-robots-file

The robots.txt file tells web robots how to crawl webpages on your website. You can use the Fastly control panel to create and configure a robots.txt file. If you follow the instructions in this guide, Fastly will serve the robots.txt file from cache so the requests won't hit your origin.

Creating a robots.txt file

To create and configure your robots.txt file, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click the **robots.txt** switch to enable the robots.txt response.




6. In the **TXT Response** field, customize the response for the robots.txt file.
7. Click **Save** to save the response.
8. Click **Activate** to deploy your configuration changes.

Manually creating and customizing a robots.txt file

If you need to customize the robots.txt response, you can follow the steps below to manually create the synthetic response and condition:


1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click **Set up advanced response**.



6. Fill out the **Create a synthetic response** fields as follows:
    - In the **Name** field, enter an appropriate name. For example `robots.txt`.
    - Leave the **Status** menu set at its default `200 OK`.
    - In the **MIME Type** field, enter `text/plain`.
    - In the **Response** field, enter at least one User-agent string and one Disallow string. For instance, the above example tells all user agents (via the `User-agent: *` string) they are not allowed to crawl anything after `/tmp/` directory or the `/foo.html` file (via the `Disallow: /tmp/*` and `Disallow: /foo.html` strings respectively).

7. Click **Create**.

8. Click the **Attach a condition** link to the right of the newly created response.



9. Fill out the **Create a condition** fields as follows:

   - From the **Type** menu, select the desired condition (for example, `Request`).

- In the **Name** field, enter a meaningful name for your condition (e.g., `Robots`).
- In the **Apply if** field, enter the logical expression to execute in VCL to determine if the condition resolves as true or false. In this case, the logical expression would be the location of your robots.txt file (e.g., `req.url.path == "/robots.txt"`).


10. Click **Save**.
11. Click **Activate** to deploy your configuration changes.

> **NOTE**
>
> For an in-depth explanation of creating custom responses, check out our Responses Tutorial.

Why can't I customize my robots.txt file with global.prod.fastly.net?

Adding the `.global.prod.fastly.net` extension to your domain (for example, `www.example.com.global.prod.fastly.net`) via the browser or in a curl command can be used to test how your production site will perform using Fastly's services.

To prevent Google from accidentally crawling this test URL, we provide an internal robots.txt file that instructs Google's webcrawlers to ignore all pages for all hostnames that end in `.prod.fastly.net`.



This internal robots.txt file cannot be customized via the Fastly control panel until after you have set the CNAME DNS record for your domain to point to `global.prod.fastly.net`.

* * *

Creating error pages with custom responses

/en/guides/creating-error-pages-with-custom-responses

The default error responses served by Fastly can be jarring for your users, especially when using Fastly for consumer applications. To mitigate this, consider configuring your service to present them with a custom page or a synthetic response when Fastly receives an error code from your origin.

Fastly offers two quick configuration options for creating 404 and 503 error pages directly in the Fastly control panel, but you can also use create custom error pages for other status codes. If you're working with large blocks of content when styling your error pages, consider creating custom responses using VCL snippets instead.


TIP

Instead of an error message, Fastly can optionally serve stale content when there is a problem with your origin server. For more information, check out our guide on serving stale content.

Creating error pages for 404 and 503 errors

To create error pages with custom responses for 404 and 503 errors, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. To create error pages with custom responses for 404 and 503 errors, click the **404 page** and **503 page** switches.




6. In the **HTML response** fields, customize the response for the 404 and 503 error pages.
7. Click **Save** to save the responses.
8. Click **Activate** to deploy your configuration changes.

Creating error pages for other status codes

You can also create error pages for other HTTP status codes. We provide example HTML, but you can use any HTML you see fit. The response object will require that you use a condition in order for a custom error page to be served, otherwise a generic error page will be served.

To create and configure an error page for an HTTP status code other than 404 or 503, follow the steps below to create the custom response and the condition under which it should be applied using the Fastly control panel:


1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click **Set up advanced response**.



6. Fill out the **Create a synthetic response** fields as follows:
    - In the **Name** field, enter a name for the response you're creating (e.g., `Custom 404`).

- From the **Status** menu, select the appropriate status (e.g., `404 Not Found`).
- In the **MIME Type** field, specify the Content-Type of the response (e.g., `text/html`).
- In the **Response** field, enter the content to be served when delivering a response.

7. Click **Create**.
8. Click the **Attach a condition** link to the right of the name of your new response.



9. Fill out the **Create a new condition** fields as follows:
    - From the **Type** menu, select the type of condition you're creating (e.g., `Cache`).
    - In the **Name** field, enter a name for the condition you're creating (e.g., `404 Not Found`).

- In the **Apply if** field, enter the condition under which the new response occurs in the following format:

```
beresp.status == ###
```

where `###` equals the status condition you're creating the response for. For example, using the value of `beresp.status == 404` in the **Apply if** field here tells Fastly to use this response object whenever origin servers return a 404 status. (See the Conditions guides for more detailed information on conditions.)


10. Click **Save and apply to**.
11. Click **Activate** to deploy your configuration changes. Fastly will now serve your custom HTML error page when required.

Creating custom responses using VCL Snippets

To create the custom response using VCL Snippets, create two separate snippets: one to trigger the condition for an internal Fastly error and the second to create the response to that error.

Create a VCL Snippet for a condition

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL Snippets**.
5. Click **Create Snippet**.



6. In the **Name** field, enter an appropriate name (e.g., `Catch Error for Custom Response`).
7. From the **Type** controls, select **within subroutine**.
8. From the **Select subroutine** menu, select **fetch (`vcl_fetch`)**.
9. In the **VCL** field, add the following condition:

```
if (beresp.status == ###) {
  error 600 "### Custom Response"
}


```

where `###` is the status condition you're creating the response for. The error code used here, `600`, is a random number that doesn't conflict with standard HTTP error codes. Consider using custom error code numbers in the 600's or 700's to avoid confusion.

10. Click **Create** to create the snippet.

Create a VCL Snippet for a synthetic response

1. Click **VCL Snippets**.
2. Click **Create Snippet**.



3. In the **Name** field, enter an appropriate name (e.g., `Create Custom Response Synthetic`).

4. From the **Type** controls, select **within subroutine**.

5. From the **Select subroutine** menu, select **error (`vcl_error`)**.

6. In the **VCL** field, add the following condition:

```
if (obj.status == 600) {
  set obj.status = 404;
```

```
  set obj.response = "Not Found";
  synthetic {"
    <html>
      <head>
      </head>
      <body>
        <h1>Custom Response</h1>
      </body>
    </html>
  "};
  return(deliver);
}
```

replacing `Custom Response` with your custom, synthetic response. This VCL tells Fastly to respond with your custom response if a request for an object meets the condition you created in `vcl_fetch`.

> **NOTE**
>
> Synthetic responses don't have a character limit, but including them in the custom VCL file may push that file over its size limit.

7. Click **Create** to create the snippet.
8. Click **Activate** to deploy your configuration changes.

---

* * *

Redirecting apex domains, wildcard domains, and subdomains

/en/guides/redirecting-apex-domains-wildcard-domains-and-subdomains

---

You can use the **Redirect traffic to www subdomains** setting to redirect traffic for apex domains, wildcard domains, or subdomains to a www subdomain so that users always arrive

in a consistent location. For example, you could redirect requests from `example.com` and `users.example.com` to `www.example.com`.

Prerequisites

Before you redirect traffic to a www subdomain, you must add the domain to your Fastly service and update the domain's DNS records to point to Fastly. For example, to redirect `example.com` to `www.example.com`, you would add `example.com` to your Fastly service and create a DNS A record to point that domain at Fastly.

Adding the redirects

To redirect traffic for an apex domain, wildcard domain, or subdomain, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Settings**.
5. In the **Redirect traffic to www subdomains** area, click **Add apex redirect**.
6. From the **Domains** menu, select the apex domain, wildcard domain, or subdomain you want to redirect.
7. From the **Status** menu, select the HTTP status code to send when redirecting traffic from the domains you selected.
8. Click **Add**.
9. Repeat these steps for any other apex domains, wildcard domains, or subdomains you want to redirect.
10. Click **Activate** to deploy your configuration changes.

---

* * *

Responses tutorial

/en/guides/responses-tutorial

Fastly allows you to create custom HTTP responses that are served directly from the cache without storing the page on a server. Responses are commonly used to serve small static assets that seldom change and maintenance pages that are served when origins are unavailable. This tutorial shows you how to create your own responses.

> **NOTE**
>
> We assume that you already know how to edit and deploy configurations using the Fastly control panel. If you are not familiar with basic editing using the application, see our help guides to learn more.

Creating a quick response

Fastly provides features that allow you to quickly enable and configure responses for a robots.txt file and 404 and 503 errors. For more information, see our guides on creating and customizing a robots.txt file and creating error pages with custom responses.

Creating an advanced response


You can create an advanced response to specify the HTTP status code, MIME type, and content of the response. An advanced response has three basic attributes:

- Status - An HTTP status code to include in the header of the response
- Response - The content to be served when delivering the response
- Description - A human readable identifier for the response

By setting these three attributes and adding a condition to the response, you can very quickly get one up and running on your service. To create an advance response, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.

3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click **Set up advanced response**.



6. Fill out the **Create a synthetic response** fields as follows:
   - In the **Name** field, enter a human-readable name for the response (e.g., `My first response`).
   - From the **Status** menu, select the appropriate status (e.g., `200 OK`).

- In the **MIME Type** field, enter the content type of the response (e.g., `text/html`).
- In the **Response** field, enter the response you want to appear when the conditions are met.


7. Click **Create** to create your custom response.

Your new response appears in the list of responses.

Adding conditions

To add a condition, follow the steps below:

1. Click **Attach condition** to the right of the new response.



2. Fill out the **Create a new condition** fields as follows:
    - From the **Type** menu, select the type of condition you want to create.
    - In the **Name** field, enter a human-readable name for the condition so that it can be easily identified in the future.

- In the **Apply if** field, enter the condition under which the new response occurs. The condition should take the following format: `req.url ~ "^/construction/"` equals the request condition you're creating the response for.
- In the **Priority** field, enter a priority if needed. Condition priorities are only needed in "interesting" cases, and can usually be left at the default "10" for all response conditions.

3. Click **Save and apply to**.
4. Click **Activate** to deploy your configuration changes.

Fastly now serves your custom response page when the condition is met.

---

* * *

Category: Video

These articles describe setup and configuration guidelines for setting up live stream delivery or video on-demand.

Adaptive bitrate playback URL guidelines

/en/guides/adaptive-bitrate-playback-url-guidelines

Fastly's On-the-Fly Packager (OTFP) service supports any directory structure you might use to store different quality levels of a video. To construct adaptive bitrate (ABR) playback URLs for a video, make directory paths to that video unique. Ensure all the files associated with a particular video (e.g., quality levels, subtitles) exist under a single directory.

IMPORTANT

If you aren't sure how to configure OTFP, contact support before making any changes.

For example, say you had a video called Example Video. Assuming you had multiple quality levels and associated files for Example Video, the following directory structure would

provide the best start to constructing ABR playback URLs:

Directory path example	Description
`/foo/bar/example-video/`	Base folder unique to this video
`/foo/bar/example-video/480p_30fps.mp4`	Quality level 480p with 30 frames per sec with audio
`/foo/bar/example-video/720p_30fps.mp4`	Quality level 720p with audio with 30 frames per sec with audio
`/foo/bar/example-video/720p_60fps.mp4`	Quality level 720p with audio with 60 frames per sec with audio
`/foo/bar/example-video/1080p_30fps.mp4`	Quality level 1080p with audio with 30 frames per sec with audio
`/foo/bar/example-video/1080p_60fps.mp4`	Quality level 1080p with audio with 60 frames per sec with audio
`/foo/bar/example-video/4k_30fps.mp4`	Quality level 4k with audio with 30 frames per sec with audio

With this directory structure, the ABR playback URL for all videos in the base directory would follow this template:

```
http://example.com/path/to/dir/<video_id>/<quality_file1_name_wo_ex <c
```

For example, the ABR playback URLs for Example Video in every format would be:

Format	Example URL
HDS	`http://example.com/foo/bar/example-video/480p_30fps,720p_30fps,720p_60fps,1080p_30fps,1080p_60fps,`
HLS	`http://example.com/foo/bar/example-video/480p_30fps,720p_30fps,720p_60fps,1080p_30fps,1080p_60fps,`

Format	Example URL
MPEG-DASH	`http://example.com/foo/bar/example-video/480p_30fps,720p_30fps,720p_60fps,1080p_30fps,1080p_60fps,`

You can reduce the duplication in ABR playback URLs separating out the repeated prefix and suffix info as follows:

```
<filename_prefix><filename_variable><filename_suffix_wo_ext>.mp4
```

and the template would change to one of the following:

```
http://example.com/path/to/dir/<video_id>/<filename_prefix><quality_le
```

```
http://example.com/path/to/dir/<video_id>/<filename_prefix><quality_le
```

```
http://example.com/path/to/dir/<video_id>/<quality_file1_variable_na >,
```

IMPORTANT

To use token validation with ABR manifest URLs, special modifications must be made using custom VCL. Contact support for assistance.

* * *

Collecting OTFP metrics

/en/guides/collecting-otfp-metrics

Fastly allows you to collect and process On-the-Fly Packager (OTFP) service metrics for analysis using a combination of custom VCL updates and specific log streaming settings. Once you've set up OTFP metrics collection through remote log streaming you can use any of a number of third-party and open source software options to aggregate your logging data for visualization and further analysis.

> **IMPORTANT**
>
> If you aren't sure how to configure OTFP, contact support before making any changes.

Upload custom VCL

1. Before uploading custom VCL, review the caveats of mixing and matching Fastly VCL with custom VCL.
2. Add the following custom VCL to your Fastly VCL:

```
sub vcl_deliver {
  # Identify Request type
  if (req.url.ext ~ "m3u8|ts|aac|webvtt") {
    set resp.http.Otfp-Format = "HLS";
  } else if (req.url.ext ~ "mpd|m4s") {
    set resp.http.Otfp-Format = "DASH";
  } else {
    set resp.http.Otfp-Format = "OTHER";
  }

  # Extract name-value pairs Otfp Info herder
  if (resp.http.X-Fastly-Otfp-Info) {
    set resp.http.Otfp-SS = regsub(resp.http.X-Fastly-Otfp-I
    set resp.http.Otfp-SL = regsub(resp.http.X-Fastly-Otfp-I
    set resp.http.Otfp-VL = regsub(resp.http.X-Fastly-Otfp-I

    # Resolution (rs name-value) not available for audio-onl
    if (resp.http.X-Fastly-Otfp-Info ~ ".*rs=(\S+).*") {
      set resp.http.Otfp-RS = re.group.1;
    } else {
      set resp.http.Otfp-RS = "-";
    }
```

```
  }
#FASTLY deliver

  return(deliver);
}

```

Create a logging endpoint

Follow the instructions to set up remote log streaming for your account and when creating your specific logging endpoint, set the **Format String** field to the following:

```
%h now.sec %r %>s %b resp.http.Otfp-Format resp.http.Otfp-SS resp.h .C
```

Control log file timing with a logging endpoint condition

To avoid excess log files, consider attaching a condition to the logging endpoint so logs are only sent when video segments are requested so that logging specifically exclude those files sent from Fastly's Origin Shield.

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Logging**.
5. In the list of logging endpoints, find the endpoint you enabled when setting up remote log streaming, then click **Attach a condition**.
6. Fill out the **Create a new condition** window as follows:
   - In the **Name** field, enter a human-readable name for the condition.
   - In the **Apply if** field, enter `resp.http.X-Fastly-Otfp-Info && !req.http.Fastly-FF`.
7. Click **Save and apply to**.

Analyze logging data

In addition to any Varnish variable, and a variety of Fastly's extensions to VCL, log files include the following video-specific fields:

- `ss` - video segment start presentation time in seconds
- `sl` - video segment duration in seconds
- `vl` - video duration in seconds
- `rs` - video track display resolution in pixels

You can use these fields to run queries for analysis and use what you discover to refine your video delivery settings.

---

* * *

	Common OTFP errors
🔗	/en/guides/common-otfp-errors

This page lists some possible error values that Fastly's On-The-Fly Packaging service (OTFP) service will send in the `X-Fastly-Package-Error` response header when attempting to fetch video data from your origin server or when repackaging your MP4 files. For help troubleshooting, send the full URL of the response to our customer support team.

> **NOTE**
>
> There are certain cases where you may see one of these messages as a warning instead of an error.

404 responses

In a 404 response from OTFP, the following header value is returned:

`Origin 404` - This error occurs if the source MP4 does not exist on origin.

5xx responses

In a 5xx response from OTFP, header values might include the following.

500 responses

- `Service configuration error` - This error typically occurs when something is wrong with one of the cache control headers that determine the behavior of an OTFP service.
- `Incompatible or corrupt origin media` - This error typically occurs when the remote MP4 being requested is corrupt or the requested file doesn't actually use the MP4 container format.
- `Slice out of bounds` - This error occurs when the start and end markers of a video do not align with the actual duration of that video.
- `Video track has no key frames` - This error occurs when the source video MP4 file does not include an `stss` box, which has information about key frames.
- `Flapping origin entity` - This error occurs if conflicting entity tags (ETags) were seen when handling a request. It's possible that the file changed legitimately during the request, and a follow-up request should work as expected. If the problem persists, it indicates that the origin can't handle ETags correctly.
- `File is not a WebVTT` - This error occurs when Fastly is unable to parse the remote WebVTT file.
- `Unexpected EOF on origin fetch` - This error occurs because an attempt to fetch segment media failed due to the file's size being smaller than its index indicated.
- `Track media is not in order` - This error occurs if Fastly cannot handle the MP4 because the media in its media data box (`mdat` box) is out of order, as indicated by the `stco` or `co64` box, which has information about the location of data in the media track's data stream.
- `moov box is too big` - This error occurs when the index portion of the MP4 is larger than 500MiB.
- `Mp4 has too many frames` - This error occurs when the total number of samples (between both the audio and video track) exceeds 40,000,000.
- `ftyp box is too big` - This error occurs if the file type box (`ftyp`) is larger than necessary.

- `Track lacked valid track id` - This error occurs if the Track ID was not set to a value greater than 0 in the `tkhd` box.
- `Track lacks valid timescale` - This error occurs if the `timescale` field in the media header box (`mdhd` box) did not have valid settings.
- `Track lacks valid duration` - This error occurs if the `duration` field in the media header box (`mdhd` box) did not have valid settings.
- `Track XXXX and XXXX do not agree` - This error indicates that the MP4 index is corrupt.
- `Empty XXXX, missing XXXX, illegal XXXX, ....` - This error indicates that the MP4 index is corrupt.
- `Unable to unmarshal expressplay response` - This error occurs when ExpressPlay is responding unexpectedly.
- `expressplay: params unable to match expected format` - This error indicates that the `X-Fastly-Drm` header has invalid base64 encoded data after `expressplay:`.
- `Origin segment media too large` - This error indicates that the file must be repackaged.
- `Unsupported audio codec 0x<##>` - This error indicates that the video/audio is encoded with an audio codec that's not supported by OTFP. Example: `Unsupported audio codec 0x69`.
- `No audio/video samples found. Fragmented or malformed MP4 detected.` - This error indicates that the source MP4 provided is likely a fragmented MP4 (fmp4) or not an MP4.
- `HEVC in HLS transport stream is not supported` - This error indicates that you need to use fragmented MP4 segments (.fmp4) instead of transport stream (.ts) requests. (Transport stream requests are not compatible with HEVC source video files.) You can specify use of fragmented MP4 segments by including the `X-Fastly-Hls-Fragmented-Mp4: true` header in your VCL request. If, after setting that header, you are experiencing playback issues on Apple devices using HEVC, you can try changing the header value to `force-hvc1`, which will ensure that OTFP is using `hvc1` sample boxes instead of `hev1`: `X-Fastly-Hls-Fragmented-Mp4: force-hvc1`. This can sometimes fix mislabeled streams.

502 responses

- `Invalid response from origin` - This error typically occurs when the response from the server is something other than an expected 206, 404, or 5xx response. For example, returning a 403 error instead of a 404 when a file is missing.
- `Invalid Content-Range from origin` - This error occurs if the origin responded to a Range request with a Content-Range header that was illegal or did not match the request Fastly made.
- `Failed to reach origin` - This error typically indicates that a path or bucket is incorrectly set in X-Fastly-Origin.
- `Validator supplied but ignored` - This error indicates that the origin is not handling ETags correctly. Specifically, when asked If-None-Match, instead of responding with a 304 status, the origin responded with a 2xx status that had the same ETag. Check out RFC 7232, section 3.2 for details.

504 responses

`Origin timeout` - This error occurs if the OTFP was unable to connect or fetch content from origin inside of 15 seconds.

---

* * *



Streaming configuration guidelines



/en/guides/streaming-configuration-guidelines

The Fastly network can deliver live streams for any HTTP streaming technology, archived or recorded, on any public or private cloud storage service. When configuring VCL to deliver live streams, we recommend following these guidelines, which Customer Support can help you with.

Configure shielding

Configure shielding by designating a specific shield POP for your origin to ensure live streams remain highly available within the Fastly network. If your setup includes primary and alternate origins (e.g., for high profile live streams), be sure to select a shield POP close to each origin, one for each origin you define.

Configure video manifest and segment caching TTLs

In live streams, video manifests are periodically refreshed when new segments become available, specially for HLS. We recommend setting manifest file TTLs to less than half of the video segment duration, typically 1-2 seconds for 5-second video segments. For long DVRs and live-to-VOD transitions, set segment TTLs longer on shields and shorter on edge POPs such that they are served from memory (that is, less than 3600s).

The following VCL sample may help you implement different TTLs for video manifest and segments. It can also be added to your service using VCL Snippets:

```
sub vcl_fetch {
#FASTLY fetch

  # Set 1s ttls for video manifest and 3600s ttls for segments of H
  # Microsoft Smooth Streaming format manifest and segments do not
  # Look for the keywords "Manifest" and "QualityLevel" to identify
  if (req.url.ext ~ "m3u8|mpd" || req.url.path ~ "Manifest") {
    set beresp.ttl = 1s;
    return (deliver);
  }
  else {
    if (req.url.ext ~ "aac|dash|m4s|mp4|ts" || req.url.path ~ "Qual
      set beresp.ttl = 3600s;
      return (deliver);
    }
  }

  return (deliver);
}

```

Optionally, identify video manifests and segments using the MIME type.

Configure lower TTLs for errors

By default, Fastly honors the `Cache-Control` header from the origin to set TTLs for cacheable objects. However, origins may not send `Cache-Control` headers for non-200 or 206 HTTP status code responses. As a result, Fastly will only cache few status code

responses with default TTLs configured, usually 3600s, to prevent large numbers of requests from hitting the origin. Uncacheable status code responses can be enabled for caching by setting `beresp.cacheable` flag to `true`.

For live streams, new video segments are added every few seconds. Typically, live stream transcoders are configured to generate 5s segments and manifests are refreshed after each new segment is available. Frequently, video players can make requests to segments not yet available or requests can return errors like 500 or 503 status codes. In such cases, status code responses should be made cacheable and should only be cached with TTLs small enough to give sufficient time for origins to recover (around 1s).

The following VCL sample may help you implement this and can also be added to your service using VCL Snippets:

```
sub vcl_fetch {
#FASTLY fetch

  # Set 1s ttl if origin response HTTP status code is anything othe
  if (!http_status_matches(beresp.status, "200,206")) {
    set beresp.ttl = 1s;
    set beresp.cacheable = true;
    return (deliver);
  }

  return (deliver);
}
```

Configure Streaming Miss

Configure Streaming Miss to reduce the time clients (players) must wait to begin downloading streams when Fastly's edge servers must fetch content from your origin. Streaming Miss should be enabled for video or audio objects only (these are sometimes called *chunks* or *segments*).

The following VCL sample may help you implement this. It can also be added to your service using VCL Snippets:

```
sub vcl_fetch {
#FASTLY fetch

  # Enable Streaming Miss only for video or audio objects.
  # Below conditions checks for video or audio file extensions comm
  # HTTP Streaming formats.
  if (req.url.ext ~ "aac|dash|m4s|mp4|ts") {
    set beresp.do_stream = true;
  }

  return (deliver);
}

```

Configure automatic compression

Configure automatic compression for manifest files based on their file extension or content-type using the following table as a guide:

HTTP streaming format	file extension	content-type
Apple HLS	m3u8	application/x-mpegurl, application/vnd.apple.mpegurl
MPEG-DASH	mpd	application/dash+xml
Adobe HDS	f4m, bootstrap	application/f4m (for manifest), application/octet-stream (for bootstrap)
Microsoft HSS	N/A	application/vnd.ms-sstr+xml

Configure CORS

Configure a CORS header on your service to play audio or video content on a different domain. Clients can potentially send CORS pre-flight requests to determine if the main request is OK to send.

By default, OPTIONS requests will pass to origin. Instead of this, we can respond with a synthetic response from the CDN. We also have an example for handling OPTIONS specifically with a synthetic. If allowing OPTIONS requests to traverse to the origin, we recommend caching OPTIONS requests.

Configure methods

With a media origin, the requests are typically only for GET and HEAD methods, so it's worth blocking other requests that are not expected by the origin. By default, Fastly will pass on GET, HEAD, and FASTLYPURGE methods. We can block all other requests by using custom VCL to send a 405 error back to the client:

```
sub vcl_recv {
#FASTLY recv

  if (req.method != "HEAD" && req.method != "GET" && req.method !=
    error 405; # This is a `return(pass);` by default
  }

return(lookup);
}

```

NOTE

Consider the logic here carefully. The PUT/PATCH and DELETE methods are likely only required when dealing with the origin's hostname directly versus the domain used for clients. OPTIONS requests should be handled synthetically if you intend to block them from going to the origin. Failing to do so could cause failure scenarios.

Enable the experimental BBR congestion algorithm

The BBR TCP congestion control algorithm is an optional, TCP-related configuration that can help improve a client's experience. Unlike the default CUBIC congestion control algorithm, which is packet-loss-based and latency-insensitive, BBR is designed to maximize bandwidth while controlling latency.

WARNING

While expected to perform better than CUBIC (especially under transient packet losses), BBR is still a work-in-progress and implementing it may cause performance degradation for some users.

You can implement this algorithm by adding the following VCL to your service using VCL Snippets:

```
sub vcl_deliver {
#FASTLY deliver

  # set congestion algorithm for client requests
  if (!req.http.Fastly-FF && client.requests == 1) {
    set client.socket.congestion_algorithm = "bbr";
  }

  return(deliver);
}
```

TIP

TCP optimizations can be applied conditionally rather than applying them to all clients. For example, enable BBR only for clients within a specific ASN or ISP network like a mobile or wireless network.

Configure origin timeouts

Set appropriate origin timeouts to ensure new live stream segments are downloaded from origin in a timely manner. For example, for a live stream with 5s video segments, set the Origin Connect value to 1s and the First Byte and Between Bytes timeout values to 2s. Typically, these values should be configured such that Fastly can also retry another origin (if configured) before sending the appropriate response on client requests.

Consider setting up failover (fallback) origins

Consider configuring your VCL to allow your origins to failover from high-profile primary streams to alternate streams in case of encoder failures or other issues (e.g., high resource utilization).

Configure real-time log streaming

For troubleshooting and debugging live streaming delivery issues, configure real-time log streaming and include TCP connection, caching, and different time-related metrics in `vcl_log`. For example, consider including:

- `fastly_info.state` (cache hits or misses)
- `client.socket.tcpi_rtt` (client round-trip time)
- `time.to_first_byte` (time from client request to the first byte being received)
- `time.elapsed` (time since the request started, which can be used to calculate response time or time-to-last-byte for both origin and clients)
- `client.as.number` and `client.as.name` (autonomous system number and name associated with client IP)
- `client.socket.tcpi_delta_retrans` (number of packets re-transmitted to the client)
- `client.socket.tcpi_snd_mss` (maximum segment size used to send responses to client)
- `client.requests` (number of requests on a connection so far)
- `client.socket.nexthop` (network path Fastly is sending the client response)
- `req.restarts` (number of request restarts typically indicates retry attempts)
- `server.datacenter` (the Fastly POP that served the request)
- `resp.http.content-length` and `resp.body_bytes_written` (actual bytes sent to client compared to what was expected to be sent)

These metrics can help you analyze throughput and may help you determine reasons a video player might switch quality levels during ABR playback.

Take advantage of surrogate key purging

All video segments and the manifest for a live stream can be purged using a single API call by using Fastly's surrogate key feature.

Manage live-to-VOD smoothly

Most encoders generate a separate video manifest when making the same live stream available for VOD. If your VOD manifest has the same URL as the live one, purge the live stream video manifest or wait for the caches to invalidate (as they will be set with low TTLs). If your setup archives the live stream as progressive mp4s, consider delivering them using Fastly's OTFP service.

> NOTE
>
> **Wowza integrations.** When configuring your Wowza origin server, be sure to select the Live HTTP Origin application type. If you select Live Edge, Wowza will always return a unique URL for manifest requests, resulting in extremely low cache hit.

---

* * *

Getting started guides

Category: Concepts

Concepts are a collection of guides that introduce you to core ideas essential to understanding content delivery networks (CDNs) and Fastly.

	Content and its delivery
🔗	/en/guides/content-and-its-delivery

Content types delivered by Fastly

The underlying protocol used by the World Wide Web to define how content is formatted and transmitted is called the Hypertext Transfer Protocol (HTTP). Fastly's CDN Service delivers all HTTP-based file content (e.g., HTML, GIF, JPEG, PNG, JavaScript, CSS) including the following:

- Static content
- Dynamic content

- Video content

Each content type is described below.

Static content

Static content includes content that remains relatively unchanged. Fastly can control static content in two ways:

- using the time to live (TTL) method, where Fastly's cache re-validates the content after expiration of the TTL, or
- using Fastly's Instant Purge functionality, in which content remains valid until the cache receives a purge request that invalidates the content.

Examples of static content include images, CSS, and JavaScript files.

Dynamic content

Dynamic content includes content that changes at unpredictable intervals, but can still be cached for a fraction of time. We serve this dynamic content by taking advantage of Fastly's Instant Purge functionality. Using this functionality, dynamic content remains valid only until a Fastly cache receives a purge request that invalidates the content. Fastly understands that the rate of those purge requests cannot be predicted. Dynamic content may change frequently as a source application issues purge requests in rapid succession to keep the content up to date. Dynamic content can, however, remain valid for months if there are no changes requested.

Examples of dynamic content include sports scores, weather forecasts, breaking news, user-generated content, and current store item inventory.

Video content

Video content includes:

- Live video streams
- Video on Demand (VOD) content libraries

Video content can be served using standard HTTP requests. Specifically, Fastly supports HTTP Streaming standards, including HTTP Live Streaming (HLS), HTTP Dynamic Streaming (HDS), HTTP Smooth Streaming (HSS), and MPEG-DASH. For Fastly's CDN Service to deliver video, the video must be packaged.

Content sources supported by Fastly

Fastly caches deliver various types of content from many different sources. Supported sources include:

- Websites
- Internet APIs
- Internet Applications
- Live and Live Linear Video
- Video on Demand (VOD) Libraries

Regardless of the content source, the content's source server must communicate using HTTP. HTTP defines specific types of *methods* that indicate the desired action to be performed on content. The manner in which those HTTP methods are used (the standard, primary methods being GET, POST, PUT, and DELETE) can be labeled as being RESTful or not. Fastly supports RESTful HTTP by default, but also can support the use of non-RESTful HTTP as long as the method used is mapped to its appropriate cache function. Each of the content sources supported by Fastly are described in more detail below.

Websites

Websites are servers that provide content to browser applications (e.g., Google's Chrome, Apple's Safari, Microsoft's Internet Explorer, Opera Software's Opera) when end users request that content. The content contains both the requested data and the formatting or display information the browser needs to present the data visually to the end user.

With no CDN services involved, browsers request data by sending HTTP GET requests that identify the data with a uniform resource locator (URL) address to the origin server that has access to the requested data. The server retrieves the data, then constructs and sends an HTTP response to the requestor. When a CDN Service is used, however, the HTTP requests go to the CDN rather than the origin server because the customer configures it to redirect all requests for data to the CDN instead. Customers do this by adding a CNAME or alias for their origin server that points to Fastly instead.

Internet APIs

Application program interfaces (APIs) serve as a language and message format that defines exactly how a program will interact with the rest of the world. APIs reside on HTTP servers. Unlike the responses from a website, content from APIs contain only requested data and

identification information for that data; no formatting or display information is included. Typically the content serves as input to another computing process. If it must be displayed visually to an end user, a device application (such as, an iPad, Android device, or iPhone Weather application) does data display instead.

Legacy internet applications

Legacy internet applications refer to applications not originally developed for access over the internet. These applications may use HTTP in a non-RESTful manner. They can be incrementally accelerated without caching, benefiting only from the TCP Stack optimization done between edge Fastly POPs and the Shield POP, and the Shield POP to the origin. Then caching can be enabled incrementally, starting with the exchanges with the greatest user-experienced delay.

Live and live linear video streams & video on demand libraries

Live and live linear video content (for example, broadcast television) is generally delivered as a *stream* of information to users, which they either choose to watch or not during a specific broadcast time. Video on demand (VOD), on the other hand, allows end users to select and watch video content when they choose to, rather than having to watch at a specific broadcast time.

Regardless of which type of video content an end user experiences, a video player can begin playing before its entire contents have been completely transmitted. End users access the video content from a customer's servers via HTTP requests from a video player application that can be embedded as a part of a web browser. Unlike other types of website content, this content does not contain formatting or display information. The video player handles the formatting and display instead.

When the video content is requested, the customer's server sends the content as a series of pre-packaged file chunks along with a manifest file required by the player to properly present the video to the end user. The manifest lists the names of each file chunk. The video player application needs to receive the manifest file first in order to know the names of the video content chunks to request.

Pre-packaging in this context refers to the process of receiving the video contents, converting or *transcoding* the stream into segments (chunks) for presentation at a specific dimension and transmission rate, and then packaging it so a video player can identify and request the segments of the live video a user wants to view.

To request video delivery on your account, contact your Fastly Account Representative at sales@fastly.com.

* * *

Using Fastly's global POP network

/en/guides/using-fastlys-global-pop-network

Our points of presence (POPs) on the internet are strategically placed at the center of the highest density Internet Exchange Points around the world. Fastly's Network Map shows a detailed view of current and planned locations for all Fastly POPs. In addition, our data centers API endpoint provides a list of all Fastly POPs, including their latitude and longitude locations.

Geographic distribution is just one of the factors Fastly considers when building its global infrastructure. Other factors include connectivity, provider diversity, and our ability to build a scalable, performant modern network centered around internet infrastructure hubs to best support our customers' markets. Fastly's focus on automation, operational redundancy, and global delivery when building our infrastructure means our POPs often combine multiple physical sites to better serve densely populated markets.

Can Fastly host my content?

We accelerate your site by caching both static assets and dynamic content by acting as a reverse proxy to your origin server (also known as *Origin Pull*), but we do not provide services for uploading your content to our servers.

In addition to using your own servers as the source, we also support various *cloud storage* services as your origin, such as Amazon Simple Storage Service (S3), Google Cloud Storage (GCS), and Google Compute Engine (GCE) as your file origin. Our partnership with Google in particular enables us to have direct connectivity to their cloud infrastructure.

Directing your traffic through Fastly's global network

Fastly operates a domain name system (DNS) service specifically written to optimize getting your traffic to Fastly. This optimization automatically routes your traffic to the nearest Fastly POP (in terms of network proximity) on our global network and reroutes around internet outages and other disturbances.

To take advantage of Fastly's global network, use a fully qualified domain name (FQDN) when you create domains in the Fastly control panel and make sure you've properly configured your CNAME DNS records.

You can use an apex domain (e.g., `example.com` instead of `www.example.com`) as your canonical domain and still take advantage of Fastly's global network by pointing your apex DNS record at IPs on Fastly's anycast network.

Limiting traffic to a subset of POPs

Fastly allows you to configure traffic routing choices that best suit your specific needs by prioritizing a subset of POPS through which your traffic travels. For example, you can specify that Fastly prioritizes the use of only North American and European Union (EU) POPs. For more information, read about our Billing zone anycast options.

Will Fastly ever adjust POP locations or service regions? How will I be notified?

Fastly continues to grow its network footprint, adding and combining new service POPs in the process. At times, expansion may result in the addition of new billable regions to our network. We'll announce new POP locations and new billable regions in advance through our network status page at fastlystatus.com. Contact sales@fastly.com with specific contract or billing questions.

---

* * *

Category: Domains

These articles provide basic, essential information and instructions for bringing your domains to Fastly.

📄	**About domains**
🔗	/en/guides/about-domains

A domain (sometimes called a domain name) is a user-friendly address used to access websites on the internet. It serves as a readable representation of an IP address, which is the numerical identifier computers use to locate each other on the network.

Adding a domain that you own, like `www.example.com`, `blog.example.com`, or even something with wildcards such as `*.example.com` to Fastly ensures that others cannot serve requests to your domain. Additionally, by routing your domain's traffic through Fastly, you can store cached copies of important information as close to your users as possible, helping to speed up its delivery to them.

To use your domain with Fastly:

1. Add the domain name that visitors use to access your website or application to a Fastly service.
2. (Optional, but recommended) Secure your domain by configuring Fastly TLS to serve secure traffic using HTTPS.
3. Test everything to make sure things are working the way you expect.
4. Update your DNS records to route production traffic for your domain through Fastly.

Before you begin

Be sure you learn about the web interface controls and how to work with services before you start working with your domains.

Adding a domain to Fastly

Use the service configuration to add a domain to Fastly, being mindful of the following domain creation limits.

Domains can only be associated with one service at a time

If a domain is in use by another service within your account, you can delete the domain and add it to the other service. However, if a domain is used by a service in another Fastly account, it can't be used without being delegated.

If you try to create a domain that is already associated with another service, you may get error messages like:

```
Domain [domain name] is already taken by service [service name].
```

In this case, follow the steps to delete a domain from your service before creating the domain on your new service.

If you try to create a domain that is already owned by another customer, you may get error messages like:

`Domain [domain name] is taken by another customer.` `Domain [domain name] is owned by another customer.`

If you receive one of these errors when adding a domain that you rightfully should have access to, or if you need to delegate a domain to another account or customer (for example, delegating a domain from a test account to a production account), contact support to help you delegate the domain to the correct account.

Services are limited to a set number of domains

We set a limit on the number of domains you can create per service by default based on your account type and any packaged offering you've purchased.

Once you reach that limit, error messages may appear that look something like this:

```
{
  "msg": "An error occurred while connecting to the fastly API, ple
  "detail": "Exceeding max number of domains: 10"
}
```

If you're receiving a limit message and need to create more services or domains, contact support for assistance. Fastly support engineers can not only increase the number of services that you can use, they can suggest other ways to design what you are trying to achieve.

Securing domains with TLS

TLS is used to form secure server connections so traffic can be served over HTTPS. You can have Fastly procure a Fastly-managed TLS certificate using Certainly or bring your own TLS certificate.

Testing domains

Fastly won't begin serving traffic for your domain until you update your DNS records and activate your service. Before doing this, you can check to see how your service is pulled through our network and identify any DNS issues or problems with your Fastly configuration.

Updating DNS records to point to Fastly

Once you're ready to have Fastly serve production traffic for your domain, you'll need to update your DNS records to point to Fastly by setting up a CNAME record for the domain.

What's next

Once you understand how domains work and their limits, add a domain to Fastly.

---

* * *

	About the TLS dashboard
🔗	/en/guides/about-the-tls-dashboard

The TLS dashboard provides a high-level overview of the status of your Fastly-managed and self-managed TLS certificates. It alerts you to any issues with your certificates and summarizes the actions you may need to take as a result of any of those alerts.

Viewing the TLS dashboard

You can access the TLS dashboard after you set up your first Fastly-managed or self-managed certificate.

To view the TLS dashboard:

1. Log in to the Fastly control panel.
2. Go to **Security** > **TLS management** > **Dashboard**.

About the TLS certificate dashboard

The TLS certificate dashboard provides a summary of the status of your Fastly-managed certificate subscriptions and self-managed TLS certificates, depending on which certificate type you're using to secure your domains.

The Subscriptions summary displays a count of:

- the number of certificate subscriptions that Fastly was unable to renew and that are no longer securing traffic. Refer to the TLS certificate alerts for the specific certificates that failed renewal and follow the instructions to retry.
- the number of certificates Fastly is currently attempting to reverify and renew.
- the number of certificates undergoing domain verification processing.
- the number of valid certificates.

For more information on Fastly-managed certificate expiration and renewals, refer to Certificate management and renewals.

The Self-managed certificates summary gives a count of:

- the number of certificates you manage that are expired. Refer to the TLS certificate alerts for the specific certificates that expired.
- the number of certificates you manage nearing expiration.
- the number of valid certificates.

For more information on self-managed certificate expiration and renewals, refer to Certificate expirations.

About the TLS alerts

The TLS alerts section appears any time you have certificates with errors. It displays a table of all certificates that have either expired or failed to renew and contains the following specific details about those certificates:

- **Status:** the status of the certificate with the alert.
- **Certificate name:** the name of the certificate.
- **Expiration/Renewal Date:** a UTC timestamp of when the certificate expired.
- **Domains:** a list of domains associated with the expired certificate and that may no longer be serving secured traffic.

- **Alert description:** a description of the error on the certificate. Click the linked text to take steps to resolve the error.

By default, all certificate alerts appear in this section. You can limit the displayed results by selecting a filter from the **Filter** menu or by using the search field to find a specific alert by domain.

About the Clean up tasks

The Clean up tasks section contains recommended actions to take based on the certificates and keys added to your services. This section appears if you have unused certificates or unmatched private keys.

Expand the **Unused certificates** section to view details about unused certificates including when the certificates expire and which domains are associated with the certificates. Unused certificates can be safely deleted. To delete unused certificates:

1. Navigate to the row with the unused certificate you want to delete.
2. Click **Delete**. A confirmation window appears.
3. Click **Delete Certificate**. The unused certificate is deleted and is no longer listed.

Expand the **Unmatched private keys** section to view details about private keys that don't have a matching certificate uploaded. Upload a matching certificate or safely delete the key. To delete unmatched private keys:

1. Navigate to the row with the unused certificate you want to delete.
2. Click **Delete**. A confirmation window appears.
3. Click **Delete Certificate**. The unmatched private key is deleted and is no longer listed.

---

* * *

	Setting up Mutual TLS authentication
🔗	/en/guides/setting-up-mutual-tls-authentication

Mutual TLS (mTLS) is an additional layer of network connection security that is added on top of our existing TLS product. By default, the TLS protocol only requires a server to present a trusted certificate to the client. mTLS requires the client to also present a trusted certificate to the server. Instead of having to rely on traditional authentication methods like passwords or API keys, the server to client connection is secured using TLS certificates.

> **TIP**
>
> Are you looking for information on applying TLS on connections between Fastly and your origin? Refer to our Working with hosts guide.

Prerequisites

To use mTLS, be sure you have the following prerequisites in place:

- a paid account with a contract for Fastly's services.
- an existing TLS activation consisting of valid domains, a TLS configuration with the relevant domains added, and TLS certificate. The certificate may be either Fastly-managed or self-managed.
- a `.pem` file containing one or more certificates certified by a certification authority (CA). This file is used as your chain of trust to verify the client certificates for your connection.

> **NOTE**
>
> mTLS is supported on Compute services for origins configured via Dynamic Backends. To set up mTLS for Compute services with static backends, contact Fastly Support.

Important considerations

You can have multiple root or intermediate certificates as long as they are combined into one certificate bundle (`.pem` file). However, if you have multiple SANs on your server-side certificate, it's best to separate the mTLS domains from your standard TLS certificates. Otherwise, some browsers will reuse the standard TLS connection and thereby bypass mTLS.

Setting up mTLS for the first time

Setting up mutual TLS authentication consists of uploading an mTLS certificate and defining the domains you want to secure with mTLS. You can enforce an mTLS connection on all requests to your domains, denying a connection if a valid certificate isn't presented. Or, you can allow connections to proceed whether or not the mTLS connection is successful. The latter option let's you secure sensitive communications with mTLS while still allowing less sensitive data to be transmitted over non-mTLS connections, which can be useful as you transition to using mTLS.

To apply mTLS:

1. Log in to the Fastly control panel.
2. Go to **Security** > **TLS management** > **Mutual TLS**.
3. Drag and drop your certificate file into the drag and drop area to upload your certificate file. Alternately, click **Browse for certificate file** to navigate to the file on your system using the file picker. The Mutual TLS certificate details page appears.
4. In the **Mutual TLS certificate name** field, enter a name used to easily identify the certificate or certificate bundle in the Fastly control panel.
5. Do one of the following:
    - Leave the **Require mTLS** checkbox selected to enforce mTLS and only allow a connection when mTLS authentication is successful.
    - Deselect the checkbox to allow a connection to proceed even if mTLS authentication fails. Useful when transitioning to using mTLS and required to log or track requests sent without a client certificate.
6. Click **Save and next** to continue.
7. From the **Add domains** menu, select the active domains you want mTLS applied to. You can use the search box to search for domains by name, certificate, or TLS configuration.
8. Click **Done**. A card for the new mTLS configuration is added to the Mutual TLS page.

Uploading additional mTLS certificates

You can upload additional mTLS certificates to apply mutual TLS authentication to your domains.

To upload additional certificates:

1. Log in to the Fastly control panel.
2. Go to **Security** > **TLS management** > **Mutual TLS**.
3. Click **Upload mutual TLS certificate**.
4. Navigate to the `.pem` that contains the certificate or certificate bundle. This file is used as your chain of trust to verify the client certificates for your connection.
5. In the **Mutual TLS certificate name** field, enter a name used to easily identify the certificate in the web interface.
6. Leave the **Require mTLS** checkbox selected to enforce mTLS and only allow a connection when mTLS authentication is successful. Deselect the checkbox to allow a connection to proceed even if mTLS authentication fails.
7. Click **Save and next** to continue.
8. From the **Add domains** menu, select the active domains you want mTLS applied to. You can use the search box to search for domains by name, certificate, or TLS configuration.
9. Click **Done**. A card for the new mTLS configuration is added to the Mutual TLS page.

Adding and removing domains

From the mTLS certificate details page, you can edit the domains on which mTLS is enforced.

To add domains:

1. Log in to the Fastly control panel.
2. Go to **Security** > **TLS management** > **Mutual TLS**.
3. Click **View certificate details**.
4. From the **Add domains** menu, select the active domains you want mTLS applied to. You can use the search box to search for domains by name, certificate, or TLS configuration.
5. Click **Done** to save your changes.

To remove domains:

1. Log in to the Fastly control panel.

2. Go to **Security** > **TLS management** > **Mutual TLS**.
3. Click **View certificate details**.
4. Click the trash next to the domain you want to remove.
5. Click **Done** to save your changes.

Editing Mutual TLS certificate details

From the mTLS certificate details page, you can edit the authentication name and the mTLS enforcement option.

1. Log in to the Fastly control panel.
2. Go to **Security** > **TLS management** > **Mutual TLS**.
3. Click **View certificate details**.
4. Click **Back to certificate settings**.
5. In the **Mutual TLS certificate name** field, enter a name used to easily identify the certificate in the web interface.
6. Use the **Require mTLS** checkbox to determine whether mTLS is enforced. If selected, connections are only allowed when mTLS authentication is successful. If de-slected, connections proceed even if mTLS authentication fails.

Replacing an mTLS certificate

From the Mutual TLS page, you can replace the certificate used for mTLS.

To replace the certificate:

1. Log in to the Fastly control panel.
2. Go to **Security** > **TLS management** > **Mutual TLS**.
3. Click **Replace** on the card for the mTLS configuration you want to update.
4. Drag and drop your certificate file into the drag and drop area to upload your certificate file. Alternately, click **Browse for certificate file** to navigate to the file on your system using the file picker.
5. Click **Submit** to save your changes.

Deleting an mTLS authentication

To delete an mTLS configuration, you must ensure there are no active domains on the mutual authentication. If there are, edit the configuration to remove the active domains before proceeding.

To delete an mTLS configuration:

1. Log in to the Fastly control panel.
2. Go to **Security** > **TLS management** > **Mutual TLS**.
3. Click the trash on the card for the mTLS configuration you want to update.
4. Confirm that you want to delete the mutual authentication and then click **Delete**.

---

* * *

	Setting up TLS with certificates Fastly manages
🔗	/en/guides/setting-up-tls-with-certificates-fastly-manages

This guide describes how to use Fastly TLS to enable HTTPS for a domain using a certificate managed by Fastly. To serve secure traffic from Fastly using HTTPS, a website or application needs to provide clients with a valid TLS certificate signed by a trusted certification authority. TLS (Transport Level Security) and its predecessor SSL (Secure Sockets Layer) are the protocols that allow clients to form secure server connections so traffic can be served over HTTPS.

Fastly-managed certificates use the ACME protocol to procure and renew TLS certificates. You have several options for certification authorities:

- Certainly, Fastly's publicly-trusted certification authority
- Let's Encrypt, a third-party non-profit certification authority
- GlobalSign, a third-party commercial certification authority (only available for paid accounts)

Trial accounts include Fastly-managed certificates for two domains using the Certainly or Let's Encrypt certification authority. Upgrade to a paid account to use GlobalSign or secure additional domains.

> **TIP**
>
> Our TLS subscriptions API allows you to manage Fastly TLS subscriptions programmatically.

Before you begin

Before setting up TLS on your domains, be sure to review the Fastly TLS prerequisites and limitations.

Setting up TLS for a domain

Setting up TLS for a domain requires you to secure the domain by registering it with a certification authority. To start this process through the Fastly control panel (instead of programmatically) follow these steps.

To set up TLS for the first time, complete the following:

1. Log in to the Fastly control panel and select **Security** from the navigation sidebar. The Overview page appears displaying an overview of Fastly's security offerings.
2. Click **Manage certificates**.
3. Click **Get started**.
4. In the **Domain Name** field, enter the apex domain (e.g., `example.com`), subdomain (e.g., `www.example.com` or `api.example.com`), or wildcard domain (e.g., `*.example.com`) you want to secure.
5. From the **Certification Authority** menu, select one of the certification authorities to secure your certificate. Prices vary between certification authorities, sometimes significantly. Be sure to review the details about these differences on our pricing page.
6. From the **Select a TLS Configuration** menu, select the TLS configuration to apply. The configuration defines both the IPs that the certificate will be deployed to and the associated TLS settings that will be applied. The default option is **HTTP/3 & TLS v1.3 +0RTT (t.sni)**.

7. Click **Continue**. The Domains page appears displaying your domain along with detailed steps on how to verify that you own it.

After you've set up TLS for your first domain, you can secure multiple additional domains from the Domains page.

1. Go to **Security** > **TLS management** > **Domains**.
2. Click **Secure another domain**.
3. In the **Domain** field, enter one or more apex domains (e.g., `example.com`), subdomains (e.g., `www.example.com` or `api.example.com`), or a wildcard domain (e.g., `*.example.com`) and click the **Add** button. Domains you add appear in the Common name area of the page.

   If you only have one domain, the common name will be the same as the domain name. If you add more than one domain, they will appear in a menu. By default, the first domain you add will be selected for you. Select another domain from the **Common name** menu if that's not the one you want.
4. From the selection menu that appears, select **Use certificates Fastly obtains for you**. The Enter subscription details page appears.
5. From the **Select a certification authority** controls, choose one of the certification authorities to secure your certificate. Prices vary between certification authorities, sometimes significantly. Be sure to review the details about these differences on our pricing page.
6. From the **Select a TLS Configuration** menu, select the TLS configuration to apply. The configuration defines both the IPs that the certificate will be deployed to and the associated TLS settings that will be applied. The default option is **HTTP/3 & TLS v1.3 +0RTT (t.sni)**.
7. Click **Submit**. The Subscription details page appears displaying your domains along with detailed steps on how to verify you own them.

Verifying domain ownership

To begin serving HTTPS traffic, Fastly needs to verify that you control any domain you've added to the control panel. Fastly allows you to verify apex domains and subdomains via the ACME DNS challenge, the ACME HTTP challenge, or via email validation. Each requires you to make specific DNS changes. Wildcard domains require the DNS challenge or email validation challenge type.


IMPORTANT

Fastly may modify the behavior of your services and DNS to complete ACME challenges for domain verification.

The default method for verifying you control a domain being added to a Fastly managed TLS certificate uses the ACME DNS challenge type. It's suitable for all kinds of domains (apex, subdomains, and wildcards). It will only point the `_acme-challenge` subdomain at Fastly, allowing you to set up TLS first, before pointing production traffic at Fastly.

To use this verification method, create a CNAME record with a unique target for your domain. Follow the steps below to view the formats for the CNAME record and target.

1. Log in to the Fastly control panel.
2. Go to **Security** > **TLS management** > **Subscriptions**.
3. Click **View subscription details** for the subscription you want to make changes to.
4. Click **Verification options** in the **Verification** column for the domain you want to verify. The Verify domain ownership page appears with formats for the record and target.



The steps to create the CNAME record will vary depending on your DNS provider's control panel interfaces. Refer to your DNS provider's documentation for exact instructions on how to do this. Your CNAME record must use the format `_acme-challenge.DOMAIN_NAME` (e.g., `_acme-challenge.www.example.com`) and must be pointed to a unique target for your domain (e.g., `domain_token.fastly-validations.com`). Once you've pointed your DNS records at Fastly, we encourage you to keep the `_acme-challenge` subdomain CNAME in place to avoid interruptions in service.

Another method for verifying you control a domain uses the ACME HTTP challenge. This method is only suitable for apex domains and subdomains (wildcard domains can only be verified using DNS or email challenges). It will point production traffic immediately at Fastly.

> **WARNING**
>
> The ACME HTTP challenge domain verification method can potentially point all end-user traffic to Fastly before you've completed TLS setup. This means that your end users may get an insecure warning in their browser related to your website or be totally unable to access your domain. To avoid this, ensure you have a properly configured Fastly service and have disabled any forced TLS redirection before you use this verification method.

To use this verification method, follow the steps below to view the formats for the CNAME record and target.

1. Log in to the Fastly control panel.
2. Go to **Security** > **TLS management** > **Subscriptions**.
3. Click **View subscription details** for the subscription you want to make changes to.
4. Click **Verification options** in the **Verification** column for the domain you want to verify.
5. Choose the verification alternative that suits your needs for the ACME HTTP challenge:

- for a subdomain, create a CNAME record that points directly to the Fastly hostname
- for an apex domain, create A records for the domain with the noted IP addresses

Once set up using either alternative, production traffic will immediately begin flowing through Fastly.

Domain control can also be verified via email when you've chosen GlobalSign as your certification authority. (Let's Encrypt does not support email challenges for domain verification.) To use this verification method, follow the steps below.

1. Contact support to enable the setting for verifying domain control via email.
2. Log in to the Fastly control panel.
3. Go to **Security** > **TLS management** > **Subscriptions**.
4. Click **View subscription details** for the subscription you want to make changes to.
5. Click **Verification options** in the **Verification** column for the domain you want to verify.
6. In the **Email validation** section, use the menu to select the email address you want email verification sent to. When selected as the certification authority, GlobalSign will provide Fastly with a list of acceptable email addresses to which a verification email can be sent. Generally, the list will include email addresses like the following:
   - `admin@example.com`
   - `administrator@example.com`
   - `hostmaster@example.com`
   - `postmaster@example.com`
   - `webmaster@example.com`
7. Click **Get verification email**.

Fastly will then instruct GlobalSign to send a verification email to the address you specify. It will contain a link that you must click to complete the domain ownership verification process.

What happens next

It should take no more than an hour for the TLS enablement process to progress through all of the TLS statuses shown below:

TLS Status	Description
Checking domain DNS records... Step 1 of 3	Domain validation is in progress. Fastly is checking domain DNS records to verify that you control the domain being added to a certificate. To advance to the next enablement state, you must verify control of the domain by updating that domain's DNS records to complete one of the ACME challenge types.
Certificate requested. Waiting for response from CA... Step 2 of 3	Domain validation has been confirmed. Fastly has verified you control the domain and has requested a TLS certificate for it from the certification authority.
TLS enabled (certificate being deployed globally)	The certification authority has issued a TLS certificate. Newly issued certificates can take between 20 minutes to an hour to fully deploy across Fastly's global network.

NOTE

If using GlobalSign certificates, after verifying domain ownership you must monitor the DNS resolution process and ensure the domain resolves globally before the TLS certificate will validate and issue. Depending on your DNS vendor, it may take up to 72 hours for your DNS to resolve.

Troubleshooting

If more than an hour has passed and TLS enablement appears to be stalled in one of the stages of adding a domain, there is likely an issue.

Domains stuck in the Checking domain DNS records state

If the domain is stuck in the `Checking domain DNS records` state, it is likely that you have not configured your DNS records correctly in order to verify domain ownership. You can check the DNS records yourself using a `dig` command in a command line application as follows:

ACME challenge type	Command to type
HTTP	`dig www.example.com +short`

ACME challenge type	Command to type
DNS	`dig _acme-challenge.www.example.com +short`

Be sure to replace `example.com` with the hostname you used when you configured your DNS records.

If you have correctly configured your DNS records, the result from this command will include one of the CNAME or A Records required for verification as defined in the Verifying domain ownership instructions.

If you recently added or modified DNS records, you may need to wait up to 72 hours for your DNS changes to propagate across the internet. If you don't see these addresses within that time period, you may have misconfigured your DNS records.

If you are still having issues, there may be a Certification Authority Authorization (CAA) record on your domain that is blocking the certification authority from issuing certificates. This CAA record is used to specify which certification authorities (CAs) are allowed to issue certificates for a domain. If a CAA record exists, you may need to correct or remove this record in order to use a managed Fastly TLS certificate.

The following lists the CAA record value needed for each certification authority supported by Fastly TLS:

Certification authority	CAA record value
Certainly	`certainly.com`
Let's Encrypt	`letsencrypt.org`
GlobalSign	`globalsign.com`

Domains stuck in the Certificate requested state

If the domain is stuck in the `Waiting for a response from CA` state, this is likely a temporary issue with the certification authority. Be sure to allow up to an hour in this state before contacting support for assistance. If this is a new certificate request, you can also try deleting the domain and starting again.

TLS activated but certificate not deployed everywhere

If the domain displays the `Activated` state but the certificate doesn't appear to be available everywhere, the certificate is likely still in the process of being deployed

throughout the Fastly network. It can take anywhere from 20 minutes to an hour for certificates to fully deploy. Be sure to allow up to an hour in this state before contacting support for assistance.

Subscriptions listed as failed

A subscription displays the `Failed` state if it is a new subscription and fails to issue a certificate for seven days or an existing subscription that fails to renew a certificate for seven days beyond its expiration date. You will also receive an email notification about failed subscriptions.

Subscriptions typically fail if you are not pointing traffic to Fastly or if you don't have proper DNS records in place. GlobalSign subscriptions specifically may fail if the domain hasn't resolved globally, meaning it's not accessible from anywhere in the world. Use a tool like DNS Checker to ensure your domain is propagated globally.

Once you resolve these issues, you can try to re-issue the subscription using the steps below:

1. Log in to the Fastly control panel.
2. Go to **Security** > **TLS management** > **Subscriptions**.
3. Click **View subscription details** for the failed subscription.
4. Click **Retry now**.

After you retry a failed subscription, we will try to issue or renew the associated certificate for a 24-hour period. If we still cannot obtain a certificate after 24 hours, the subscription will again be marked as failed.

Pointing DNS to serve HTTPS traffic

To serve secure traffic via HTTPS once the certificate is deployed, follow these steps.

1. Ensure that the domains you've added via the TLS domains interface have been added to a properly configured Fastly service.
2. Configure your DNS records to point traffic at the newly created certificate's IP addresses. If you used the HTTP challenge method to verify domain ownership, you're already pointing traffic at the certificate. All DNS details (CNAME, A records, and optionally AAAA records) can be found by clicking **See DNS details** to view the TLS configuration associated with the domain.

For an apex domain (e.g., `example.com`), you'll need to create an A record with your DNS provider. For subdomains and wildcard domains (e.g, `www.example.com` or `*.example.com`), you'll need to create a relevant CNAME record.

Your domains and certificates can be set to use one or more TLS configurations. For more information, refer to the details on managing DNS and TLS configurations.

> **WARNING**
>
> If you point your DNS away from Fastly after the initial setup, we will be unable to terminate TLS on your behalf and we will also be unable to renew your certificate, which will expire after 90 days.

Managing TLS subscriptions


You can use the Subscriptions page to manage your TLS subscriptions and take actions such as:

- adding or removing domains
- changing the domain common name
- migrating to Certainly, Fastly's certification authority
- deactivating TLS

Managing domains on TLS subscriptions

To manage the domains on your TLS subscriptions, such as to add or remove domains or to change the domain common name, follow these steps:


1. Log in to the Fastly control panel.
2. Go to **Security** > **TLS management** > **Subscriptions**.
3. Click **View subscription details** for the subscription you want to make changes to.



4. Click **Manage Subscription**.

> **NOTE**
>
> You can only manage a subscription in `Pending`, `Issued`, and `Renewing` states.

5. From the Manage Subscription details page, you can do the following:



- **Add new domains:** In the **Domain** field, enter one or more apex domains (e.g., `example.com`), subdomains (e.g., `www.example.com` or `api.example.com`), or a wildcard domain (e.g., `*.example.com`) and click **Add**. Separate multiple domains with a comma.
- **Remove existing domains:** Click the trash in the **Actions** column on the same line as the domain you want to delete. Follow the instructions in the confirmation window to complete the deletion.
- **Change the subscription common name:** From the **Common name** menu, select the domain used to represent this subscription.

6. After making any changes to the subscription, click **Submit**. A message appears asking to confirm your changes.
7. Click **Confirm changes** to submit your changes. To return to the previous screen, click **No, review changes**.

> NOTE
>
> If you added a new domain, you must validate domain ownership after confirming the change. See Domain validation for TLS certificates.


Migrating to Certainly

If you're using the Let's Encrypt or GlobalSign certification authorities to secure your domains, you can use the Fastly control panel to migrate to Certainly, Fastly's publicly-trusted certification authority.

> NOTE
>
> To migrate from GlobalSign to Certainly, first contact Fastly Support.

To migrate to Certainly:

1. Log in to the Fastly control panel.
2. Go to **Security** > **TLS management** > **Subscriptions**.
3. Click **View subscription details** for the subscription you want to make changes to.
4. Click **Migrate to Certainly**.



5. Confirm that you want to migrate your certificate, then click **Migrate to Certainly**.

After clicking migrate, Fastly will automatically replace your certificate with a Certainly certificate and verify domain ownership without any downtime. Fastly will continue to serve your existing certificate until it is replaced by Certainly. If there were changes to your DNS records that prohibit Certainly from validating your domain and Fastly can't automatically verify the ownership, a notice will appear with instructions you'll need to make to your DNS details.

Deactivating TLS and deleting a TLS domain

Once a domain has TLS activated, you have the option to deactivate TLS via the **Deactivate TLS** button listed on each domain card on the TLS domains page. If a domain has multiple certificates, you can elect to deactivate a specific certificate by clicking **Add/Edit Activations** and clicking the **Deactivate** button next to any active configurations. If all certificates are deactivated, Fastly will no longer serve TLS traffic on the selected domain and it will become disabled. Fastly will attempt to renew a certificate for a disabled domain. To prevent this renewal process, delete the associated subscription after you disable it. Fastly will not renew certificates for deleted subscriptions.

Certificate management and renewals

Each certification authority has a separate verification and renewal time frame that Fastly follows when managing your certificates:

- **Certainly renewals.** Certainly issues certificates that are valid for 30 days. Fastly will attempt to re-verify your domain and renew your certificate after 20 days. However, if your DNS records no longer point at Fastly or if a CAA record blocks Certainly, the certificate will lapse at the end of the 30-day period.
- **Let's Encrypt renewals.** Let’s Encrypt issues certificates that are valid for 90 days. Fastly will attempt to re-verify your domain and renew your certificate after 60 days. However, if DNS records no longer point at Fastly or if a CAA record blocks Let's Encrypt, the certificate will lapse at the end of the 90-day period.

- **GlobalSign renewals.** GlobalSign issues certificates that are valid for 365 days. Fastly will attempt to re-verify your domain and renew your certificate after 275 days. However, if DNS records no longer point at Fastly, or if a CAA record blocks GlobalSign, the certificate will lapse at the end of the 365-day period. Certificates provided by GlobalSign are subject to the terms of GlobalSign's Subscriber Agreement, which can be found at https://www.globalsign.com/repository.

Fastly automatically runs a DNS check for certificate renewals within the following timeframes:

- **Certainly:** 10 days before certificates are due to expire
- **Let's Encrypt:** 30 days before certificates are due to expire
- **GlobalSign:** 90 to 120 days before certificates are due to expire

If a DNS check indicates that a renewal is failing, Fastly will automatically email all account users with TLS management permissions, notifying them of the upcoming expiration. If the renewal continues to fail, Fastly will continue to email users on the account on a schedule up until the expiry date.

In addition, you must verify domain ownership as part of the management process. If you have the correct DNS records for verifying domain ownership and there is no blocking CAA record, but you are still receiving renewal failure emails, contact support for assistance.

---

* * *

Setting up TLS with your own certificates

/en/guides/setting-up-tls-with-your-own-certificates

This guide describes how to use the Fastly TLS product to upload and deploy your own TLS certificates and private keys using the Fastly control panel.

To serve secure traffic from Fastly using HTTPS (Hypertext Transfer Protocol Secure), a website or application needs to provide clients with a valid TLS certificate signed by a trusted Certification Authority (CA). TLS (Transport Level Security) and its predecessor SSL (Secure Sockets Layer) are the protocols that allow clients to form secure server connections so traffic can be served over HTTPS.

TIP

Fastly offers an API for uploading and managing your keys and certificates used to activate TLS for your domains on Fastly.

Before you begin

- Before setting up TLS on your domains, be sure to review the Fastly TLS prerequisites and limitations.
- To use a self-signed certificate that is not publicly-trusted, reach out to support@fastly.com.

Setting up TLS for a domain

To set up TLS, you'll upload a TLS certificate and the matching private key (used to initially generate the certificate). Then, you'll apply a TLS configuration to the domain and activate TLS on the domain.

To set up TLS for the first time, complete the following:

1. Log in to the Fastly control panel and select **Security** from the navigation sidebar. The Overview page appears displaying an overview of Fastly's security offerings.
2. Click **Manage certificates**.
3. Click **Get started**.
4. Click **Upload my own private key and certificate** to continue.
5. Drag and drop the key file into the drag and drop area for key files. Alternately, click the browse link to navigate to the file on your system using the file picker. A success message appears along with a visualization of your key.

   IMPORTANT

   The key file upload tool currently only accepts 256-bit or 384-bit ECDSA keys or 2048-bit RSA keys.

6. Drag and drop the certificate file into the drag and drop area for certificate files. Alternately, click the browse link to navigate to the file on your system using the file picker.

7. Click **Continue** to move to the final steps of enabling TLS on your domain.
8. Select the checkbox next to the domain you want to activate.
9. From the **Select a TLS Configuration** menu, select the TLS configuration to apply. The configuration defines both the IPs that the certificate will be deployed to and the associated TLS settings that will be applied. The default option is **HTTP/3 & TLS v1.3 + 0RTT (t.sni)**.


   If you've purchased Regional Routing, TLS configurations will appear grouped by regional subset of our global POPs, allowing you to restrict traffic delivery from Fastly solely to those regions. Once the configuration is selected, the TLS configuration is applied to the domain. Each TLS configuration is active and available at their respective IP addresses and DNS records.
10. Click **Activate**.

After you've set up TLS for your first domain, you can upload additional TLS certificates and private keys and activate TLS on other domains.

To upload a TLS certificate and the relevant private key, follow the steps below.

> IMPORTANT
>
> The key file upload tool currently only accepts 256-bit or 384-bit ECDSA keys or 2048-bit RSA keys.

1. Log in to the Fastly control panel.
2. Go to **Security** > **TLS management** > **Self-managed certificates**.
3. From the **Upload key or certificate** menu, select **Add a new key or certificate**.



4. We recommend generating a new key for the new certificate. Drag and drop the key file into the drag and drop area for key files. Alternately, click the browse link to navigate to the file on your system using the file picker. If you have multiple private keys, you can identify each by the unique SHA1 hash.

5. Drag and drop the certificate file into the drag and drop area for certificate files. Alternately, click the browse link to navigate to the file on your system using the file picker.

6. Click **Submit**. The Certificate details page appears.

Once you upload your certificate file, you can activate TLS on a domain.

Activating TLS on a domain

Once a valid certificate and private key have been uploaded, all domains that appear as SAN entries will be listed on the Domains page with a status of TLS ready. To serve HTTPS traffic using your certificate, follow the steps below to activate TLS for the domain and point the DNS records to the certificate's location.

1. Log in to the Fastly control panel.

2. Go to **Security** > **TLS management** > **Domains**.

3. Find the card for the domain with the certificates on which you want to activate TLS. Certificates in a disabled state will have the status of `Ready to activate`.

4. Click **Add TLS activation** to the right of the certificate you want to activate.

5. Select the TLS configuration you want to apply. If the configuration is already activated for a different certificate on the domain, a notice appears. You must click **Switch to this certificate** to continue.

   If you've purchased Regional Routing, TLS configurations will appear grouped by regional subset of our global POPs, allowing you to restrict traffic delivery from Fastly solely to those regions. Once your TLS configuration is selected, Fastly deploys your TLS certificate to the entire Fastly edge network. It may take up to an hour for your certificate to become available throughout the world.

6. Click **View details** to view the DNS details for the domain. Use these details to configure your DNS records so that a TLS connection can be established using your certificate.


   - For TLS on an apex domain (e.g., `example.com`), you'll need to create an A record with your DNS provider.
   - For subdomains and wildcard domains (e.g, `www.example.com` or `*.example.com`), you'll need to create a relevant CNAME record.

IMPORTANT

It can take up to 48 hours for new DNS records to propagate across the internet.

Applying a TLS configuration to a domain

TLS configurations are a collection of TLS settings that include the supported versions of TLS and HTTP, along with networking and handshaking options that clients will use. For accounts with more than one TLS configuration, the default configuration has a label in the right corner of the card.



TIP

TLS configuration names are editable by clicking the pencil next to the name.

To override the default TLS configuration applied to a domain or to migrate a domain to use a different configuration follow these steps.

1. Log in to the Fastly control panel.
2. Go to **Security** > **TLS management** > **Domains**.
3. Find the card for the domain with the certificates on which you want to add additional TLS activations.
4. Click **View details** next to the certificate on which you want to add additional activations.
5. Click **Add TLS activation**.
6. Select the TLS configuration you want to apply to the certificate. If the configuration is already activated for a different certificate on the domain, a notice appears. You must click **Switch to this certificate** to continue.

   If you've purchased Regional Routing, TLS configurations will appear grouped by regional subset of our global POPs, allowing you to restrict traffic delivery from Fastly solely to those regions. Once the configuration is selected, the TLS configuration is applied to the domain. Each TLS configuration is active and available at their respective IP addresses and DNS records.
7. Click **View details** and use the information to configure your DNS records so that a TLS connection can be established using your certificate.

8. Confirm the new DNS records have propagated across the internet (this can take up to 48 hours), then delete the old TLS configuration by clicking the trash.

> **NOTE**
>
> For HTTP/1.1, be sure to activate TLS for each of your domains in the Fastly control panel. If you upload a certificate with multiple SANs, each domain must have TLS explicitly activated if you want to secure these domains on Fastly.
>
> Exceptions may apply in the case of HTTP/2 if your browser coalesces secure connections and has previously received a TLS certificate from an earlier handshake. In this case, some browsers may reuse an existing secure connection to Fastly if its certificate has a matching SAN entry.

Updating a certificate

Fastly allows you to update a certificate by replacing it with a new one at any time. To help identify certificates that need updating and replacing, the following alerts appear on the certificate cards on the TLS certificates page:

- **Expiring:** Indicates a certificate is nearing its expiration date.
- **Expired:** Indicates a certificate is past its expiration date.
- **Replace:** Indicates a certificate Fastly recommends you update and replace.

Updating certificates when there are no removed domains

To update a TLS certificate by replacing it with one that contains all the domains as the original (either as a superset or a matching list) follow these steps.

1. Generate a new certificate with your preferred Certification Authority.
2. Log in to the Fastly control panel.
3. Go to **Security** > **TLS management** > **Self-managed certificates**.
4. Find the card for the certificate you're replacing.
5. Click the word **Replace** in the upper right corner of the certificate's card.
6. Drag and drop the replacement certificate file into the drag and drop area for certificate files. The certificate you select should be PEM-formatted and the SAN

entries of this new certificate must contain all entries in the current certificate (i.e., it must either have an exact matching list or contain a superset). Alternately, click the browse link to navigate to the file on your system using the file picker.

7. If a new key was generated with the new certificate, drag and drop the key file into the drag and drop area for key files. Alternately, click the browse link to navigate to the file on your system using the file picker.

8. Below the drag and drop areas, verify that the certificate replacement menu is pre-selected with the certificate you want to replace with your new certificate.

9. Click **Submit**.

All domains actively serving TLS traffic on the old certificate will be automatically transitioned to the updated certificate within a matter of minutes. Any new domains will need to be manually activated by following the steps for activating TLS on a domain.

Updating certificates when there have been changes to domains

If you want to update one of your certificates that requires removing domains, you will need to procure a new certificate with the updated list of SAN entries. Follow the steps to upload this certificate as a new certificate.

1. Upload the new certificate.

2. Go to **Security** > **TLS management** > **Domains**.

3. Locate the previously existing domains that have already been activated with the certificate you're replacing.

4. Click **View details** next to the certificate on which you want to add additional activations.

5. Click **Add TLS activation**.

6. Select the TLS configuration you want to apply to the certificate. If the configuration is already activated for a different certificate on the domain, a notice appears. You must click **Switch to this certificate** to continue.

   If you've purchased Regional Routing, TLS configurations will appear grouped by regional subset of our global POPs, allowing you to restrict traffic delivery from Fastly solely to those regions. Once the configuration is selected, the TLS configuration is applied to the domain. Each TLS configuration is active and available at their respective IP addresses and DNS records.

7. Delete the old certificate.

Certificates for newly activated domains can take between 5 minutes to an hour to fully deploy across Fastly's global network. If the new certificate is not being used to serve TLS traffic within 1 hour, contact support for assistance.

Deactivating TLS and deleting certificates and private keys

Once a domain has TLS activated, you have the option to deactivate TLS via the **Deactivate TLS** button listed on the TLS domains page. If a domain has multiple certificates, you can elect to deactivate a specific certificate by clicking **Add/Edit Activations** and clicking the **Deactivate** button next to any active configurations. If all certificates are deactivated, Fastly will no longer serve TLS traffic on the selected domain and it will become disabled.

To delete a certificate from the Self-managed certificates page, be sure to disable TLS for all domains on that specific certificate. You will also need to delete all certificates before you can delete a matching private key. Private keys can only be deleted if they have no matching TLS certificate.

> TIP
>
> Unmatched and unused private keys aren't automatically deleted. To avoid reaching the maximum key limit, be sure to delete any unused keys.

Certificate expirations

Thirty days before any certificate is due to expire, the web interface will display warnings on certificates soon to expire. Fastly will also begin to periodically send automated expiration notification emails to all superusers. If the certificate is not replaced or removed, Fastly will continue to email users on the account until the certificate expires. Once expired, Fastly will no longer send automatic notifications.

---

* * *

	Testing domains using command line utilities
🔗	/en/guides/testing-domains-using-command-line-utilities

After you create a domain and activate your service configuration, we recommend testing that domain with either the Fastly control panel or command line utilities we provide to help you identify DNS issues or problems with your Fastly configuration. This guide focuses on using the command line utilities for that testing and covers how to:

1. find the IP address of a Fastly POP
2. add a domain Host entry to your hosts file
3. test the domain in a web browser

> **TIP**
>
> If you don't want to use the command line utilities to test your domain, you can use the Fastly control panel to point to Fastly and test whether or not your configuration is working.

Before you begin

This guide assumes you've created a domain.

Determining the IP address of a Fastly POP

Use the `host`, `nslookup`, or `dig` command to determine the IP address of a Fastly POP. You'll use this information to temporarily modify your hosts file in order to test things properly. We return different IP addresses depending on the location and state of the network making the request. As a result, the IP address you receive for any specific query may differ from the below examples but should result in the best performance for you.

> **TIP**
>
> For non-TLS requests, use `dualstack.nonssl.global.fastly.net` for connection over IPv6. For TLS requests, use the custom TLS CNAME record provided in the Fastly control panel or by Fastly support. For more information about the Fastly TLS service, see our guide on TLS service options.

Running `host` for your domain returns both IPv4 addresses and IPv6 addresses:

```
$ host www.example.com.
www.example.com.is an alias for dualstack.nonssl.global.fastly.net.
dualstack.nonssl.global.fastly.net has address 199.232.144.204
```

```
dualstack.nonssl.global.fastly.net has IPv6 address 2a04:4e42:64::204
```

In this example, the IPv4 address is `199.232.144.204` and the IPv6 address is `2a04:4e42:64::204`.

Running `nslookup` for `dualstack.nonssl.global.fastly.net` also returns both IPv4 addresses and IPv6 addresses:

```
$ nslookup  dualstack.nonssl.global.fastly.net.
Server:         127.0.0.53
Address:        127.0.0.53#53

Non-authoritative answer:
Name:   dualstack.nonssl.global.fastly.net
Address: 199.232.144.204
Name:   dualstack.nonssl.global.fastly.net
Address: 2a04:4e42:64::204
```

In this example, the IPv4 address is `199.232.144.204` and the IPv6 address is `2a04:4e42:64::204`.

Alternatively, you can run `dig` to determine the IP address, but you must specify an A query for IPv4 addresses or a AAAA query for IPv6 addresses.

Running `dig` for your domain with an A query returns:

```
$ dig +noall +answer -t A www.example.com.
www.example.com.        3600    IN      CNAME   dualstack.nonssl.global.
dualstack.nonssl.global.fastly.net. 30 IN A     199.232.144.204
```

The IPv4 address is `199.232.144.204`

Running `dig` for your domain with an AAAA query returns:

```
$ dig +noall +answer -t AAAA www.example.com.
www.example.com.        3600    IN      CNAME   dualstack.nonssl.global.
dualstack.nonssl.global.fastly.net. 30 IN AAAA  2a04:4e42:64::204
```

The IPv6 address is `2a04:4e42:64::204`.

Modifying your hosts file

Using the IP address determined above, temporarily add a static IP address and domain Host entry to the hosts file on your computer. Once you make this temporary change test your domain to prove that traffic is flowing the right way.

Use the following anycast IPs for testing your sites served over `dualstack.nonssl.global.fastly.net`.

IPv4	IPv6
151.101.0.204	2a04:4e42::204
151.101.64.204	2a04:4e42:200::204
151.101.128.204	2a04:4e42:400::204
151.101.192.204	2a04:4e42:600::204

For example, if the domain you are testing is `www.example.com` and you are using the anycast IPv4 example `151.101.0.204`, you would add this entry to the file and save the changes:

```
151.101.0.204 www.example.com
```

TIP

On machines running macOS or Linux, your hosts file is `/etc/hosts`. On Windows-based machines, it's `C:\Windows\System32\Drivers\etc\hosts`.

Testing your domain

Now that you've modified your host file, test your domain to make sure it's being pulled through Fastly's network. To test your domain, restart your browser then enter your domain in the address field. You should now see the updated domain in the address field indicating requests are being sent to the Fastly POP.

Alternatively, you can test the domain using a ping command to verify that your domain is being served by a Fastly POP address. In this case, `ping www.example.com` would display

the Fastly POP address `151.101.56.204`.

> **IMPORTANT**
>
> Be sure to remove the Host entry from your hosts file after you make CNAME changes to point your domain to Fastly.

What's next

When you're ready to route production traffic through Fastly, update your domain's CNAME record to begin routing client traffic through Fastly services instead of directly to your origin.

---

* * *

	Fastly TLS prerequisites and limitations
🔗	/en/guides/tls-prerequisites-and-limitations

Before getting started with Fastly-managed TLS subscriptions (managed TLS) or self-managed TLS certificates (Bring Your Own Certificates), be sure to review the following prerequisites and limitations.

Prerequisites for using Fastly TLS

In order to use Fastly TLS, you must have the following in place:

- a Fastly user account assigned the role of superuser or assigned a user role with added TLS management permission
- permission to modify the DNS records on the relevant domains that appear as SAN entries on the TLS certificate
- the relevant domains added to a properly configured Fastly service

Fastly-managed certificate limitations

Fastly-managed certificates are an option for both paid and trial accounts. When you set up TLS using Fastly-managed certificates, Fastly uses the ACME protocol to procure and renew

TLS certificates. You have several options for certification authorities:

> **NOTE**
>
> Your charges may vary based on the certification authority you select.

- Certainly, Fastly's publicly-trusted certification authority
- Let's Encrypt, a third-party non-profit certification authority
- GlobalSign, a third-party commercial certification authority (only available for paid accounts)

No matter which certification authority you select, the following limitations apply:

- Fastly managed certificates require clients to support TLS v1.2 and Server Name Indication (SNI) by default. To discuss how you can use settings other than these defaults, contact support@fastly.com.
- Fastly TLS does not support the Triple DES (3des) cipher suite.

Trial accounts are subject to the following limitations:

- Trial accounts include up to two TLS domains for free using the Certainly or Let's Encrypt certification authorities.
- Wildcard certificates are not supported on trial accounts.

Self-managed certificate prerequisites and limitations

Self-managed certificates are an option for paid accounts. When you set up TLS using self-managed TLS certificates, you upload and deploy your own TLS certificates and private keys using the Fastly control panel or API.

To use Fastly TLS with self-managed certificates, be sure you have the following prerequisites in place:

- a paid Fastly user account (not a developer's trial)
- a valid X.509 TLS certificate from a trusted certification authority (CA) and a matching 256-bit ECDSA private key (recommended) or 2048-bit RSA private key
- the relevant domains added as Subject Alternative Name (SAN) entries on the TLS certificate

In addition to these prerequisites, be sure you understand the following limitations about the certificate you upload and the CA you choose:

- Uploaded certificates require clients to support TLS v1.2 and Server Name Indication (SNI) by default. To discuss how you can use settings other than these defaults, contact support@fastly.com.
- If you're a DigiCert customer, be aware that upon making certificate changes, DigiCert will revoke your original certificate 72 hours after re-issuance. Be sure you upload your new certificate and switch all hostnames as soon as possible.

Each certificate you upload must have a matching private key. Private keys use cipher suites to encrypt communications through a set of algorithms and protocols, making them secure. Be sure you understand the following limitations about the private keys and cipher suites you use for Fastly TLS:

- Fastly TLS does not support the Triple DES (3des) cipher suite.

Supported cipher suites

Each certificate you upload must have a matching private key. Private keys use ciphers to encrypt communications through a set of algorithms and protocols, making them secure. Fastly supports the following cipher suites.

TLS 1.3

The following ciphers are supported on TLS 1.3, the default version of TLS used when setting up TLS for the first time.

For the highest level of security, we recommend using these ciphers.

RFC cipher name	`openssl` cipher name
`TLS_AES_256_GCM_SHA384`	`TLS13-AES-256-GCM-SHA384`
`TLS_CHACHA20_POLY1305_SHA256`	`TLS13-CHACHA20-POLY1305-SHA256`
`TLS_AES_128_GCM_SHA256`	`TLS13-AES-128-GCM-SHA256`

TIP

TLS 1.3 also supports key exchanges `X25519` and `X25519MLKEM768`.

TLS 1.2

The following ciphers are supported on TLS 1.2, the minimum standard version of TLS supported by Fastly.

RFC cipher name	`openssl` cipher name
`TLS_ECDHE_RSA_WITH_AES_128_GCM_SHA256`	`ECDHE-RSA-AES128-GCM-SHA256`
`TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256`	`ECDHE-ECDSA-AES128-GCM-SHA256`
`TLS_ECDHE_RSA_WITH_AES_256_GCM_SHA384`	`ECDHE-RSA-AES256-GCM-SHA384`
`TLS_ECDHE_ECDSA_WITH_AES_256_GCM_SHA384`	`ECDHE-ECDSA-AES256-GCM-SHA384`
`TLS_ECDHE_RSA_WITH_CHACHA20_POLY1305_SHA256`	`ECDHE-RSA-CHACHA20-POLY1305`
`TLS_ECDHE_ECDSA_WITH_CHACHA20_POLY1305_SHA256`	`ECDHE-ECDSA-CHACHA20-POLY1305`
`TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA256`	`ECDHE-RSA-AES128-SHA256`
`TLS_ECDHE_ECDSA_WITH_AES_128_CBC_SHA256`	`ECDHE-ECDSA-AES128-SHA256`

Legacy ciphers

The following are legacy ciphers supported only on TLS versions 1.0 - 1.1 and require a dedicated IP address to create custom cipher suites. These ciphers should only be used in edge cases, such as for compatibility with older devices. Where possible, we recommend upgrading to TLS 1.3 for the highest level of security.

RFC cipher name	`openssl` cipher name
`TLS_ECDHE_RSA_WITH_AES_128_CBC_SHA`	`ECDHE-RSA-AES128-SHA`
`TLS_ECDHE_ECDSA_WITH_AES_128_CBC_SHA`	`ECDHE-ECDSA-AES128-SHA`

RFC cipher name	`openssl` cipher name
`TLS_ECDHE_RSA_WITH_AES_256_CBC_SHA`	`ECDHE-RSA-AES256-SHA`
`TLS_RSA_WITH_AES_128_GCM_SHA256`	`AES128-GCM-SHA256`
`TLS_ECDHE_ECDSA_WITH_AES_256_CBC_SHA`	`ECDHE-ECDSA-AES256-SHA`
`TLS_RSA_WITH_AES_128_CBC_SHA`	`AES128-SHA`
`TLS_RSA_WITH_AES_256_CBC_SHA`	`AES256-SHA`
`TLS_RSA_WITH_3DES_EDE_CBC_SHA`	`DES-CBC3-SHA`

Legacy Customer-Provided TLS Certificate Hosting Service limitations

> **NOTE**
>
> Fastly maintains support for its original Customer-Provided TLS Certificate Hosting Service. For information on migrating certificates from the Customer-Provided TLS Certificate Hosting Service to our current Fastly TLS offerings, contact Support.

Fastly TLS is compatible with certificates that have been uploaded as part of the Customer-Provided TLS Certificate Hosting Service with the following limitations:

- If you update previously uploaded certificates, you can continue to use the Customer-Provided TLS Certificate Hosting Service with no changes to your bill.
- Removing a previously uploaded certificate from the Customer-Provided TLS Certificate Hosting Service and uploading a new one using Fastly TLS will result in the new certificate being counted in your bill for Fastly TLS. The old certificate will continue to be billed per any contracted term for Customer-Provided TLS Certificate Hosting Service.

Next steps

Once you've reviewed these prerequisites and limitations, you are ready to get started with TLS. Refer to our TLS quick start guide to quickly get set up using Certainly. You can also check out our guides on Setting up TLS with certificates Fastly manages and Setting up TLS with your own certificates for more in-depth instructions.

* * *

	TLS quick start
🔗	/en/guides/tls-quick-start

Welcome! This guide helps new TLS users like you get started with Fastly TLS as quickly as possible using Certainly, Fastly's publicly-trusted certification authority. By setting up TLS for a domain you've added to a Fastly service, you can deliver your origin website to your users through the Fastly CDN.

Before you begin

Keep in mind the following:

- Be sure to review the TLS prerequisites and limitations.
- This guide assumes you have a Fastly account and a service with at least one domain added. If you don't, refer to our Start here guide to quickly get set up.
- This guide includes instructions for working with subdomains, not apex or second-level domains. To work with those types of domains, refer to our guide on using Fastly with apex domains.

1. Create a TLS certificate

We'll use Fastly-managed TLS to create a TLS certificate, which means Fastly will procure the certificate for us and manage the certificate renewals. We'll have Fastly issue a certificate using Certainly.

> TIP
>
> Trial accounts include up to two TLS domains for free with Certainly, while paid accounts include five free domains using Certainly. If you want to bring your own certificates or use Fastly-managed TLS with another certification authority, refer to those specific guides.


1. Log in to the Fastly control panel and select **Security** from the navigation sidebar. The Overview page appears displaying an overview of Fastly's security offerings.

2. Click **Manage certificates**.

3. If this is your first time setting up TLS, click **Get started**. If you have a TLS certificate in your account already, click **Secure another domain** instead.

4. Enter the name of the domain you want to secure with HTTPS (e.g., `www.tacolabs.com`), and then click **Add**. Be sure this domain is present on one of your Fastly services.


5. Fastly adds your domain as the **Common name**. Select Certainly as the certificate authority and keep the default TLS configuration, then click **Submit**.



2. Verify your domain

Once you click Submit, Fastly provides the necessary information to use to confirm you own the domain. You'll need access to the DNS records for your domain - in most cases this will be wherever you purchased the domain. While the exact process may vary, the instructions below should work for most providers.

1. Click the **Verification options** for the domain and expand the menu for **ACME DNS challenge**.
2. Note the CNAME address (`_acme-challenge` followed by your domain name), which is the address to point your DNS record to. The CNAME value is a string of characters followed by `fastly-validations.com`. You'll need these later.



3. Access your DNS provider or domain registrar (wherever you registered or purchased the domain) and navigate to the Custom DNS settings.
4. Add a new CNAME record to verify the domain for the TLS certificate.
    - Set the **hostname** to the CNAME address from the TLS info that's something like `_acme-challenge` followed by your domain.


- Set the **address**, sometimes called data or content, to the CNAME value which ends in `fastly-validations.com`.

5. Save your new record then navigate back to your Fastly account. Fastly will work to verify your domain and issue the certificate, a process that typically takes 20 minutes to an hour, but can extend up to 72 hours.

3. Point your domain at Fastly

Now that the certificate has been issued, you'll add another CNAME record, this time to update your DNS records to point your domain at Fastly and begin serving traffic.

1. Locate the value for the CNAME record for your domain in Fastly by clicking **See DNS details** on the **TLS domains page**. The CNAME record value is a single letter followed by `.sni.global.fastly.net`.



In this example, the Fastly web interface says that the value for our CNAME record is `j.sni.global.fastly.net`. This value doesn't support IPv6 addresses, but you can preface `dualstack` to enable IPv6 support (i.e., `dualstack.j.sni.global.fastly.net`).

2. Navigate back to your DNS records and add another CNAME record, this time for the domain you want to point at Fastly. If you have an existing DNS record for this domain, you'll need to edit or remove it.

- Set the **hostname** to the domain you want to point at Fastly, for example, `www.tacolabs.com`.

> TIP

> If using an apex domain, refer to Using Fastly with apex domains for instruction.

- Set the **address** to `dualstack.<letter>.sni.global.fastly.net` (adjusting the single letter to match your certificate).

Give it some time for your changes to propagate. While most newly issued certificates take between 20 minutes to an hour to fully deploy across Fastly's global network, it may take up to 72 hours depending on your DNS provider and Time To Live (TTL) value, which is in seconds. Once the changes propagate, you'll see the origin site you pointed your Fastly service at when you visit the domain you registered! You can also use the following command to check the status:

```
$ dig www.tacolabs.com +short
dualstack.t.sni.global.fastly.net.
151.101.198.132
```

4. Certificate renewals

Fastly automatically handles TLS certificate renewals prior to expiration, assuming your CNAME records haven't been modified. Ten days before your certificates are due to expire, Fastly automatically runs a DNS check for certificate renewals. However, if your DNS records no longer point at Fastly or if a CAA record blocks Certainly, the certificate will lapse at the end of the 30-day period. For more information, refer to Certificate management and renewals.

---

* * *



Working with CNAME records and your DNS provider



/en/guides/working-with-cname-records-and-your-dns-provider

Once you're ready to route traffic to a Fastly service using your domain name, you must associate the domain with your Fastly service and then update your DNS records to point to Fastly by setting up a CNAME record for the domain. While the steps you follow when setting up a CNAME record for your domain will vary depending on your DNS provider, in

general you'll need to input a specific value from Fastly that communicates to your DNS provider where and how to route through Fastly's network.

This guide helps you find the information you'll need from Fastly to set up a CNAME record with your DNS provider including how to choose the right hostname value for the record.

> **IMPORTANT**
>
> Fastly is not a DNS provider. The steps you follow when setting up a CNAME record for your domain will vary depending on your DNS provider. You must have access privileges to modify DNS records for your domain.

Before you begin

Keep in mind the following CNAME configuration limitations. Specifically:

- **Shared TLS domain incompatibility.** You can't add a CNAME record for a shared TLS domain.
- **Apex domain incompatibility.** You can't use a CNAME record if you plan to use Fastly on your apex domain (e.g., `example.com` rather than `www.example.com`). Check out our guide to using Fastly with apex domains for more details.

Choosing the right Fastly hostname value for your CNAME record

When you set up your CNAME record, you'll need to enter a hostname value. This value is used to communicate to your DNS provider where and how to route through Fastly's network.

The value you choose will differ based on:

- the standard HTTPS (TLS) support requirements for your domain, including whether or not HTTP/2 is enabled.
- any custom TLS options purchased for your domain.
- whether or not you choose to limit your traffic to the North American and EU network or use Fastly's global network.

In the next sections you can find recommendations based on the most common criteria.

Non-TLS hostnames and limiting traffic

If you don't require TLS support and only need to accept HTTP (Port 80) connections, use one of the following values for the CNAME record:

Location to route traffic	CNAME record value
Fastly's entire global network	`dualstack.nonssl.global.fastly.net`
North American and EU POPs only	`dualstack.nonssl.us-eu.fastly.net`

IMPORTANT

Fastly's non-TLS hostnames refuse HTTPS connections (port 443) to prevent TLS certificate mismatch errors.

TLS-enabled hostnames

If using Fastly TLS, you must use the assigned CNAME record value provided in the Fastly web interface. Using an incorrect value may cause HTTPS (port 443) visitors to receive a TLS certificate mismatch error.

The format for the CNAME record value is `<letter>.sni.global.fastly.net`. To enable IPv6 support, prefix the value with `dualstack`.

TLS type	CNAME record value
Fastly TLS	`<letter>.sni.global.fastly.net`
Fastly TLS with IPv6 support	`dualstack.<letter>.sni.global.fastly.net`

To locate the CNAME record value:

1. Log in to the Fastly control panel.
2. Go to **Security** > **TLS Management** > **Domains**.
3. Locate the domain you would like to route to Fastly.
4. Click **View/edit** next to the appropriate certificate to view DNS details.
5. Locate the CNAME record value under the **DNS details** section.

Setting up the CNAME record with your DNS provider

Once you've determined the appropriate Fastly hostname for your domain, the next step is to set up a CNAME record for your domain. Refer to your DNS provider's documentation for exact instructions on how to create or update a CNAME record. If you run your own DNS server or are familiar with the format of BIND zone files, the CNAME record would look similar to this:

```
www.example.com.    3600    IN    CNAME    nonssl.global.fastly.net.
```

In the above example, the domain set up on Fastly is `www.example.com.`, with a time-to-live (TTL) of `3600` seconds (1 hour), the Record Type is `CNAME`, and the Fastly hostname value is `nonssl.global.fastly.net.` because TLS support isn't required and traffic will be routed through Fastly's entire global network.

Best practices when updating a DNS CNAME record

- Be sure you've added all domains you want served by Fastly to the appropriate service. If you don't and you point your domain to Fastly, an `unknown domain` error will occur.
- Make sure your service is properly configured. You can test a Fastly service on your local machine by using curl and testing setup before changing domains.
- If you have multiple hostnames on the same domain (e.g., `api.example.com`, `www.example.com`, `app.example.com`), you can use a DNS wildcard record (`*.example.com`) at your DNS provider so only a single CNAME record is created and maintained. You should also add either a matching `*.example.com` domain or the individual domains to your Fastly service.
- Before configuring a CNAME record to point to Fastly, change your service configuration to lower the CNAME's TTL to a small number (we suggest 60 seconds) and wait for the old TTL to expire. Creating a DNS CNAME record for your domain after the TTL expiration ensures you have an easy way to roll back changes if you encounter an issue. Once you confirm everything is working properly using Fastly, you can increase the TTL to its original value.

Checking your CNAME record

To check your CNAME record, run the following command in a terminal window:

```
$ dig www.example.com +short
```

Your output should appear similar to the following:

```
nonssl.global.fastly.net.
151.101.117.57
```

In most cases, the hostname displayed first will be your current Fastly hostname (in this case, `nonssl.global.fastly.net.`). If you don't see a Fastly hostname in the output or if you see an incorrect Fastly hostname, then either your CNAME isn't properly set at your DNS provider or an older CNAME record is still cached by your local DNS resolver.

You can use various online DNS query tools like OpenDNS Cache Check or whatsmydns.net to test the current DNS responses from the different DNS resolvers worldwide.

Removing CNAME records

If you deactivate a service, delete a service, or cancel your account, we strongly recommend modifying or deleting any CNAME records pointing to Fastly. Follow the instructions on your DNS provider's website. Doing so will minimize the risk of unauthorized use of your domains.

---

* * *

Working with domains

/en/guides/working-with-domains

This guide describes how to take the public name for your website or application and add it to Fastly where you can associate it with a Fastly service. You can add, edit, or remove domains from your service at any time.

TIP

You can also work with domains using the Fastly API.

Before you begin

Before you create your first domain, be sure you understand how domains are used with Fastly and domain creation limits. You'll also need to understand the Fastly web interface controls before using them to work with domains.

Creating a domain for the first time

Follow the steps below to add a domain to your service for the first time:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.



4. Fill out the domain creation fields as follows:
   - In the **Domain Name** field, enter the public domain you want users to visit.

     TIP

     We recommend using a subdomain such as `www` when you publish links to your website and redirecting your apex domain to the subdomain (e.g., redirecting the apex domain `example.com` to the subdomain `www.example.com`). You can include both versions in your service and configure your service to handle the redirect for you by setting up a `CNAME` record for the subdomain and `A` records for the apex domain in your DNS settings.

   - *(Optional)* In the **Comment** field, enter a comment that describes the domain.
5. Click the **Add** button. Your new domain appears in the list of domains.


6. Click **Activate** to deploy your configuration changes.

Once you create a domain, you'll want to test it before adding a CNAME DNS record for your domain name to begin routing traffic through Fastly.


Creating additional domains

Follow the steps below to add additional domains to your service:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.



4. Click **Create domain**.



5. Fill out the domain creation fields as follows:
    - In the **Domain Name** field, enter the public domain you want users to visit.

- *(Optional)* In the **Comment** field, enter a comment that describes the domain.

6. Click **Add**. Your new domain appears in the list of domains.
7. Click **Activate** to deploy your configuration changes.

Once you create a domain, you'll want to test it before adding a CNAME DNS record for your domain name to begin routing traffic through Fastly.


Testing a domain

After you activate your service configuration, but before you change your DNS entries to send your domain to our servers, you can check to see how your service is pulled through our network. Testing your domain can help you identify DNS issues or problems with your Fastly configuration.

You can test your domain using a link in the web interface by following the steps below. Alternatively, you can test domains using command line utilities.

To use the web interface to test your domain:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.



4. Click **Test domain** next to the domain you want to test.

5. Verify that your website appears in a new tab in your web browser.

Deleting a domain

Follow the steps below to delete a domain from your service:

1. On the Domains page, click the trash next to the domain you want to delete.
2. Click **Confirm and delete** to confirm you want to delete your domain.
3. Click **Activate** to deploy your configuration changes.

> IMPORTANT
>
> To minimize the risk of unauthorized use of your domains, we strongly recommend modifying or deleting any DNS CNAME records pointing to the Fastly hostname associated with the deleted domain. Follow the instructions on your DNS provider's website.

What's next

When you're ready to route production traffic through Fastly, update your domain's CNAME record to begin routing client traffic through Fastly services instead of directly to your origin.

You may also want to learn more about working with hosts and working with health checks as you continue to refine versions of your service configurations.

---

* * *


Category: Hosts

These articles provide basic, essential information and instructions for connecting hosts, also referred to as a backends or origins, to Fastly.


	Shielding
🔗	/en/guides/shielding

As a content delivery network, Fastly works by having any one of our global points of presence (POP) respond to requests that would otherwise be sent directly to your origin server. Because each POP acts independently, any time it doesn't have a cached version of the requested resource, it will make a request directly to your origin, even if another POP may be in the process of making the same request. You can reduce the load on your origin servers if you specify one of Fastly's POPs as an origin "shield." Designating a shield POP ensures requests to your origin will come from a single POP, thereby increasing the chances of an end user request resulting in a cache `HIT`.

For example, consider end users in three regions: Lyon (France), Washington DC (United States), and Tokyo (Japan). Each of these regions has a local Fastly POP available to them that caches information by default. If the user in Lyon requests a resource that is not cached on the Fastly Paris POP, however, that POP will make a request to the origin server, cache the resources in the response, and return the cached resource to the user.



With shielding enabled, however, the POP you designate collects all requests to your origin server instead. For example, the Fastly Virginia POP was designated as the shield for a server located in the AWS `us-east-1` region (as show in the illustration below).



In this scenario, if the user in Lyon requests a resource that isn't cached on the Fastly Paris POP, then that POP will forward the request to the shield POP, in this case in Virginia. If the resource had been previously cached on the shield POP, then it would be returned to the regional POP where it is then cached and returned to the user. Otherwise, the shield POP would make a request to the origin server for the resource, cache the response and return it to the regional POP where it is also cached before being returned to the user.

For more advanced use cases, see Advanced shielding scenarios.


Enabling shielding

> **IMPORTANT**
>
> If you are using Google Cloud Storage as your origin, you need to follow the steps in our GCS setup guide instead of the steps below.

Enable shielding with these steps:

1. Read the caveats of shielding information below for details about the implications of and potential pitfalls involved with enabling shielding for your organization.
2. Log in to the Fastly control panel.
3. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.

4. Click **Edit configuration** and then select the option to clone the active version.
5. Click **Origins**.
6. Click the name of the Host you want to edit.
7. From the **Shielding** menu, select the data center to use as your shield keeping the following in mind:
    - Generally, we recommend selecting a data center close to your backend. Doing this allows faster content delivery because we optimize requests between the shield POP you're selecting (the one close to your server) and the edge POP (the one close to the user making the request). Read our guidance on choosing a shield location for more information.
    - With multiple backends, each backend will have its own shield defined. This allows flexibility if your company has backends selected geographically and different shield POPs are desired.
8. Click **Update** to save your changes.
9. If you have changed the default Host or have added a header to change the Host, add the modified hostname to your list of domains. Do this by clicking **Domains** and checking to make sure the Host in question appears on the page. If it isn't included, add it by clicking **Create domain**.



   With shielding enabled, queries from other POPs appear as incoming requests to the shield. If the shield doesn't know about the modified hostname, it doesn't know which service to match the request to. Including the origin's hostname in the domain list eliminates this concern.
10. Click **Activate** to deploy your configuration changes.

Caveats of shielding

Shielding not only impacts traffic and hit ratios, it affects configuration and performance. When you configure shielding, be aware of the following caveats.

Inbound traffic billing

Inbound traffic to a shield will be billed as regular traffic, including requests to populate remote POPs. Enabling shielding will incur some additional Fastly bandwidth charges, but those are likely to be offset by savings of your origin bandwidth (and origin server load). Pass-through requests will not go directly to the origin, they will go through the shield first.

Global HIT ratio calculation

Global HIT ratio calculation may seem lower than the actual numbers. Shielding is not taken into account when calculating the global hit ratio. If an edge node doesn't have an object in its cache, it reports a miss. Local MISS/Shield HIT gets reported as a miss and a hit in the statistics, even though there is no call to the backend. It will also result in one request from the edge node to the shield. Local MISS/Shield MISS will result in two requests, because we will subsequently fetch the resource from your origin. For more information about caching with shielding, see our shielding developer documentation.

Shield failover

If a specified shield POP is inaccessible for a request (e.g., because of intervening network issues), that request will go directly from the edge node to your origin server, bypassing the shield.

Backends manually defined using VCL

You will be unable to manually define backends using VCL. Shielding at this level is completely dependent on backends being defined as actual objects through the Fastly control panel or API. Other custom VCL will work just fine.

Automatic load balancing

If you've selected auto load balancing, you can only select one shield total. You must use custom VCL to use multiple shields when auto load balancing is set.

Sticky load balancing

Enabling sticky load balancing and shielding at the same time requires custom VCL. Sticky load balancers use `client.identity` to choose where to send the session. The `client.identity` defaults to the IP request header. That's fine under normal circumstances, but if you enable shielding, the IP will be the original POP's IP, not the client's IP. Thus, to enable shielding and a custom sticky load balancer, you want to use the following:

```
if (req.http.fastly-ff) {
  set client.identity = req.http.Fastly-Client-IP;
}
```

Host header

You'll need to use caution when changing the Host header before it reaches the shield. Fastly matches a request with a Host header. If the Host header doesn't match to a domain within the service, an error of 500 is expected. To ensure consistent behavior of Fastly customer services and origins, we normalize the host header's value to all lowercase in the `vcl_hash` subroutine. This means that no matter how your site's domain name is capitalized in the request, the hash subroutine will behave predictably. This does not apply to any other parts of the URL, which remain case-sensitive.

Purging conflicts can occur if the Host header is changed to a domain that exists in a different service. For example, say Service A has hostname `a.example.com` and Service B has hostname `b.example.com`. If Service B changes the Host header to `a.example.com`, then the edge will think the request is for Service B but the shield will think the request is for Service A. As a precaution, you'll want to purge the object from both Service A and Service B to ensure that Fastly is retrieving the newest version on the next request. If you're changing the Host header before it reaches the shield, the object is split across both services because `a.example.com` and `b.example.com` are treated as separate objects. For information about the caveats to be aware of when you change a Host header, see our article on Specifying an override host.

VCL execution

VCL gets executed twice: once on the edge POP and again on the shield POP. Changes to `beresp` and `resp` can affect the caching of a URL on the shield and edge. Consider the following examples.

Say you want Fastly to cache an object for one hour (3600 seconds) and then ten seconds on the browser. The origin sends `Cache-Control: max-age=3600`. You unset `beresp.http.Cache-Control` and then reset `Cache-Control` to `max-age=10`. With shielding enabled, however, the result will not be what you expect. The object will have `max-age=3600` on the shield and reach the edge with `max-age=10`.

A better option in this instance would be to use `Surrogate-Control` and `Cache-Control` response headers. `Surrogate-Control` overrides `Cache-Control` and is stripped after

the edge node. The `max-age` from `Cache-Control` will then communicate with the browser. The origin response headers would look like this:

```
Surrogate-Control: max-age=3600
Cache-Control: max-age=10
```

Another common pitfall involves sending the wrong `Vary` header to an edge POP. For example, there's VCL that takes a specific value from a cookie, puts it in a header, and that header is then added to the `Vary` header. To maximize compatibility with any caches outside of your control (such as with shared proxies as commonly seen in large enterprises), the `Vary` header is updated in `vcl_deliver`, replacing the custom header with `Cookie`. The code might look like this:

```
vcl_recv {
  # Set the custom header
  if (req.http.Cookie ~ "ABtesting=B") {
    set req.http.X-ABtesting = "B";
  } else {
    set req.http.X-ABtesting = "A";
  }
  ...
}

...

sub vcl_fetch {
  # Vary on the custom header
  if (beresp.http.Vary) {
    set beresp.http.Vary = beresp.http.Vary ", X-ABtesting";
  } else {
    set beresp.http.Vary = "X-ABtesting";
  }
  ...
}

...

sub vcl_deliver {
  # Hide the existence of the header from downstream
```

```
  if (resp.http.Vary) {
    set resp.http.Vary = regsub(resp.http.Vary, "X-ABtesting", "
  }
}
```

When combined with shielding, however, the effect of the above code will be that edge POPs will have `Cookie` in the `Vary` header, and thus will have a terrible hit rate. To work around this, amend the above VCL so that `Vary` is only updated with `Cookie` when the request is not coming from another Fastly cache. The `Fastly-FF` header is a good way to tell. The code would look something like this (including the same `vcl_recv` from the above example):

```
# Same vcl_recv from above code example

sub vcl_fetch {
  # Vary on the custom header, don't add if shield POP already adde
  if (beresp.http.Vary !~ "X-ABtesting") {
    if (beresp.http.Vary) {
      set beresp.http.Vary = beresp.http.Vary ", X-ABtesting";
    } else {
      set beresp.http.Vary = "X-ABtesting";
    }
  }
  ...
}

...

sub vcl_deliver {
  # Hide the existence of the header from downstream
  if (resp.http.Vary && !req.http.Fastly-FF) {
    set resp.http.Vary = regsub(resp.http.Vary, "X-ABtesting", "Coo
  }
}
```

POP maintenance

As part of our standard maintenance procedures, Fastly may perform maintenance on a POP that you have designated as an origin shielding location. When this happens, the POP will remain in service, but we may bring individual machines within that POP in or out of service as needed. Fastly may also decommission a POP. When this happens, Fastly will move your shielding location to a neighboring data center on your behalf. Before standard maintenance starts, we will post a notification update to our service status page, but if you prefer to be individually alerted before the maintenance happens, you can open a support ticket by visiting https://support.fastly.com/, letting us know your customer ID, and requesting to be notified of upcoming shielding migrations at locations where you shield. We will then contact you via email to announce upcoming migrations. If necessary, we'll ask you to perform certain actions at a time that's convenient for you.

* * *

	Working with health checks
🔗	/en/guides/working-with-health-checks

Health checks monitor the status of your hosts. Fastly performs health checks on your origin server based on the Check frequency setting you select in the Create a new health check page and the packaged offering you may have purchased. The Check frequency setting you select specifies approximately how many requests per minute Fastly POPs are checked to see if they pass. There is roughly one health check per Fastly POP per period. Any checks that pass will be reported as "healthy."

Before you begin

Be sure you learn about the web interface controls and how to work with services before you start setting up health checks.


Limitations and considerations

When you create a health check, you have the option to create and attach a custom header value. If you elect to take advantage of this option, keep the following things in mind:

- The header value should only be used for the custom header check and should not be used for other purposes. You should always maintain appropriate security controls and secrets management procedures, including appropriate access limitations for customer header values.
- All headers combined must be less than 64KB. Each individual header must be less than 8190 bytes.
- There may not be more than 100 headers linked to an individual health check.

Creating a health check

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Origins**.



5. Click **Create health check**.

Create a health check

Learn the basics in our health checks tutorial

Name * Required

A comment that describes your health check.

Request HEAD

An HTTP verb (i.e., **HEAD, GET,** or **POST**) and path to visit on your origins when performing the check. Use a unique path. For example, use **/website-healthcheck.txt**, not **/** or **/healthcheck.**

Host header * Required

The Host header to set when making the request (e.g. **example.com**).

▸ Tips

Custom headers

Header name	Value

+ Add a custom header

Expected response 200 OK

The HTTP status code that signifies a healthy state.

Check frequency

- (•) Low
- ( ) Medium
- ( ) High
- ( ) Custom...

Set how often this health check is performed. Checking frequently will result in more origin requests. Learn more.


▸ Details of check frequency options

Threshold & Window 1 / 2 * Required

Initial 1 * Required

Number of requests to assume as passing on deploy.

Interval & Timeout (ms) 60000 5000 * Required



6. Fill out the **Create a health check** fields as follows:

    - In the **Name** field, enter a human-readable identifier for the health check (e.g., `West Coast Origin Check`).
    - From the **Request** menu, select an HTTP verb. In the **Request** field, enter the path to visit when performing the check. Use a unique path. For example, use `/website-healthcheck.txt`, not `/` or `/healthcheck`.
    - In the **Host header** field, enter the HTTP Host header to set when making the request (e.g., `example.com`).
    - In the **Custom header** field, click **Add a custom header** to add additional headers to your health check requests. You can specify up to 100 additional headers.
        - In the **Header name** column, enter a human-readable identifier for the header.
        - In the **Value** column, enter the value you want assigned to the header.

        IMPORTANT

        The header value should only be used for the custom header check and should not be used for other purposes.

    - From the **Expected response** menu, select the HTTP status code the origin servers must respond with for the check to pass (usually `200 OK`).
    - In the **Check frequency** section, select a setting to control how often the health check is performed.
        - **Low:** One request every minute from each data center, where "healthy" means 1 out of 2 must pass.
        - **Medium:** One request every 15 seconds from each data center, where "healthy" means 3 out of 5 must pass.
        - **High:** One request every 2 seconds from each data center, where "healthy" means 7 out of 10 must pass.

        - **Custom:** A custom frequency you specify.

    - In the **Threshold & Window** fields, enter the number of successes per total number health checks. For example, specifying `3/5` means 3 out of 5 checks must pass to be reported as healthy.

    - In the **Initial** field, enter the number of requests to assume as passing on deploy. For example, if the Threshold & Window field is set to `3/5` and the Initial field is set to `1`, a backend would be marked as “unhealthy” until it passed two more health checks to reach the required minimum.

    - In the **Interval & Timeout (ms)** fields, enter times. Interval represents the period of time for the requests to run. Timeout represents the wait time until request is considered failed. Both times are specified in milliseconds.

7. Click **Create**.

Your new health check now appears in the list of checks.

Assigning a health check

Health checks do nothing on their own, but they can be added as a special parameter to an origin server in your configuration.

1. Edit one of your existing origin servers by clicking the origin server's name.
2. From the **Health checks** menu, select the health check you just created.
3. Click **Update**.

Fastly will now use the health check to monitor the selected origin server.

Creating and assigning health checks using VCL

Health checks can also be created and assigned using VCL. See our developer documentation on health checks for more information.

Troubleshooting

Fastly will periodically check your origin server based on the options chosen. Pay special attention to the HTTP Host header. A common mistake is setting the wrong host. If the origin server does not receive a host it expects, it may issue a 301 or 302 redirect causing the health check to fail. Also, Varnish requires the origin server receiving the health check

requests to close the connection for each request. If the origin server does not close the connection, health checks will time out and fail.

If an origin server is marked unhealthy due to health checks, Fastly will stop attempting to send requests to it. Once all of your origin servers are marked unhealthy, Fastly will return a 503 error (service unavailable) to the client unless you tell it otherwise. You can configure Fastly to attempt to serve stale content instead until your origin servers become available again.

What's next

Learn more about working with domains and working with hosts as you continue to refine versions of your service configurations.

---

* * *

	Working with hosts
🔗	/en/guides/working-with-hosts

A *host*, also referred to as a *backend* or *origin*, is a web server or cloud service that contains the content of your website or application. For example, a host could be a physical or virtual web server, an application running on a platform as a service, a serverless function running on a serverless platform, or even a static storage bucket.

Before Fastly can cache your content, you must add a host to your Fastly service configuration by specifying its hostname or IP address. When Fastly receives a request from a user, we fetch the objects from your host and return the response to the user.

> **NOTE**
>
> To learn more about configuring third-party services for use as hosts, refer to our integration guides and our developer documentation on integrating with backend technologies.

Before you begin

Be sure you learn about the web interface controls and how to work with services before you start working with your hosts.

Adding a host

To add a host to your Fastly service configuration, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Origins**.
5. Click **Create a host**.
6. Fill out the **Hosts** field by entering the hostname or IP address of your origin server. Entering a hostname automatically enables Transport Layer Security (TLS) and assigns port 443. Entering an IP address disables TLS and assigns port 80.
7. Click **Add** to add your host.

Editing a host

After you've created your host, you can edit the settings by following the steps below:

1. In the **Hosts** area, click the pencil next to the Host you want to edit.
2. Fill out the **Edit this host** fields as follows:
   - In the **Name** field, enter the name of your server (for example, `My Origin Server`). This name is displayed in the Fastly web interface.
   - In the **Address** field, enter the IP address (or hostname) of your origin server.

     See Understanding the difference between certificate hostname and SNI hostname values for more information about hostnames.
   - In the **IP version** field, leave the checkbox selected to default to IPv6 connections when available, falling back on IPv4 only when IPv6 is not available.
3. Configure the **Transport Layer Security (TLS)** settings as follows:

- From the **Enable TLS?** options, leave the default set to **Yes** if you want to enable TLS to secure the connection between Fastly and your origin. To enable TLS, a valid SSL certificate must be installed on your origin server and port 443 (or the specified port) must be open in the firewall. You can select **No** if you do not want to use TLS.

- From the **Verify certificate?** options, leave default set to **Yes** if you want to verify the authenticity of the TLS certificate. Selecting **No** means the certificate will not be verified.

  > ⚠ WARNING
  >
  > Not verifying the certificate has serious security implications, including vulnerability to man-in-the-middle attacks. Consider uploading a CA certificate instead of disabling certificate validation.

- In the **Certificate hostname** field, enter the hostname associated with your TLS certificate. This value is matched against the certificate common name (CN) or a subject alternate name (SAN) depending on the certificate you were issued.

- *(Optional)* In the **SNI hostname** field, enter the hostname of a different certificate to be used for the request to origin if you are using Server Name Indication (SNI) to put multiple certificates on your origin. Alternatively, select the checkbox to match the SNI hostname to the Certificate hostname. This information also gets sent to the server in the TLS handshake. See our guidance on understanding the difference between certificate hostname and SNI hostname values for additional details.

- *(Optional)* In the **TLS CA certificate** field, provide a certificate in PEM format if you're using a certificate that is either self-signed or signed by a certification authority (CA) not commonly recognized by major browsers. The PEM format looks like this:

```
-----BEGIN CERTIFICATE-----
MIIDrzCCApegAwIBAgIQCDvgVpBCRrGhdWrJWZHHSjANBgkqhkiG9w0BAQUFADBh
MQswCQYDVQQGEwJVUzEVMBMGA1UEChMMRGlnaUNlcnQgSW5jMRkwFwYDVQQLExB3
d3cuZGlnaWNlcnQuY29tMSAwHgYDVQQDExdEaWdpQ2VydCBHbG9iYWwgUm9vdCBD
QTAeFw0wNjExMTAwMDAwMDBaFw0zMTExMTAwMDAwMDBaMGExCzAJBgNVBAYTAlVT
MRUwEwYDVQQKEwxEaWdpQ2VydCBJbmMxGTAXBgNVBAsTEHd3dy5kaWdpY2VydC5j
b20xIDAeBgNVBAMTF0RpZ2lDZXJ0IEdsb2JhbCBSb290IENBMIIBIjANBgkqhkiG
9w0BAQEFAAOCAQ8AMIIBCgKCAQEA4jvhEXLeqKTTo1eqUKKPC3eQyaKl7hLOllsB
CSDMAZOnTjC3U/dDxGkAV53ijSLdhwZAAIEJzs4bg7/fzTtxRuLWZscFs3YnFo97
nh6Vfe63SKMI2tavegw5BmV/Sl0fvBf4q77uKNd0f3p4mVmFaG5cIzJLv07A6Fpt
43C/dxC//AH2hdmoRBBYMql1GNXRor5H4idq9Joz+EkIYIvUX7Q6hL+hqkpMfT7P
T19sdl6gSzeRntwi5m3OFBqOasv+zbMUZBfHWymeMr/y7vrTC0LUq7dBMtoM1O/4
gdW7jVg/tRvoSSiicNoxBN33shbyTApOB6jtSj1etX+jkMOvJwIDAQABo2MwYTAO
BgNVHQ8BAf8EBAMCAYYwDwYDVR0TAQH/BAUwAwEB/zAdBgNVHQ4EFgQUA95QNVbR
TLtm8KPiGxvDl7I90VUwHwYDVR0jBBgwFoAUA95QNVbRTLtm8KPiGxvDl7I90VUw
DQYJKoZIhvcNAQEFBQADggEBAMucN6pIExIK+t1EnE9SsPTfrgT1eXkIoyQY/Esr
hMAtudXH/vTBH1jLuG2cenTnmCmrEbXjcKChzUyImZOMkXDiqw8cvpOp/2PV5Adg
06O/nVsJ8dWO41P0jmP6P6fbtGbfYmbW0W5BjfIttep3Sp+dWOIrWcBAI+0tKIJF
PnlUkiaY4IBIqDfv8NZ5YBberOgOzW6sRBc4L0na4UU+Krk2U886UAb3LujEV0ls
YSEY1QSteDwsOoBrp+uvFRTp2InBuThs4pFsiv9kuXclVzDAGySj4dzp30d8tbQk
CAUw7C29C79Fv1C5qfPrmAESrciIxpg0X40KPMbp1ZWVbd4=
-----END CERTIFICATE-----
```

4. To apply advanced TLS options, click **Advanced TLS options** and decide which of the optional fields to specify, if any. For more information about these settings, see Advanced TLS options.

5. Configure the remaining **Create a host** settings as follows:

    - *(Optional)* From the **Shielding** menu, select a POP to enable the shielding feature. For more information, see our guide on shielding.
    - *(Optional)* From the **Health check** menu, select a health check for this origin server. For more information, see our guide on working with health checks.
    - *(Optional)* From the **Auto load balance** menu, select **Yes** to enable load balancing for this origin server. For more information, see our guide on load balancing.
    - If you enabled load balancing, enter a weight in the **Weight** field.
    - *(Optional)* In the **Override host** field, enter the hostname of your override Host header based on the origin you're using. The value in this field will take precedence over anything you've set using the global override host configuration. To see example Host headers for third-party services, refer to our developer documentation on overriding the Host header.

      > **NOTE**
      >
      > To override the incoming Host header on your origin using your Fastly service, refer to the Specifying the override host guide.

6. Click **Advanced options** and decide which of the optional fields to change, if any:

    - *(Optional)* In the **Maximum connections** field, enter the maximum number of connections for your backend. The default limit is 200 connections per cache node to protect your origins from being overloaded.
    - *(Optional)* In the **Connection timeout** field, enter how long, in milliseconds, to wait for a connection timeout. The default is 1000 milliseconds.
    - *(Optional)* In the **First byte timeout** field, enter how long, in milliseconds, to wait for a first byte timeout. The default is 15000 milliseconds.
    - *(Optional)* In the **Between bytes timeout** field, enter how long, in milliseconds, to wait between bytes. The default is 10000 milliseconds.

7. Click **Update**. The new override host appears under the **Show all details** field of the **Override host** section and a code block is added to the origin definition in your VCL that will look similar to the following:

```
Backend F_Host_1 {
    .host = "..."; # IP or hostname
    .host_header = "example.com";
    .always_use_host_header = true;
     ...
}

```

8. Click **Activate** to deploy your configuration changes.

Advanced TLS options

If you enabled TLS for the connection between Fastly and your host, you can configure optional settings by clicking the **Advanced TLS options** link.

Specifying acceptable TLS protocol versions

If your origin server supports modern TLS protocol versions, you can customize the TLS protocols Fastly will use to connect to it by setting a **Minimum TLS Version** and **Maximum TLS Version**. We recommend setting both to the most up-to-date TLS protocol, currently 1.3, if your origin supports it.

Use the `openssl` command to verify your origin supports a given TLS protocol version. For example:

```
$ openssl s_client -connect origin.example.com:443 -tls1_3
```

Replace `-tls1_3` with `tls1_2`, `tls1_1` and `tls1_0` to test other protocol versions. Fastly does not support SSLv2 or SSLv3.

> **IMPORTANT**
>
> In line with security best practices, Fastly recommends enabling servers with version 1.3 of the TLS protocol by default. For backend connections from our edge nodes to customer origins, Fastly supports TLS 1.3, 1.2, 1.1, and 1.0 depending on the versions of the protocol in use on the origin server. Fastly will continue to support TLS 1.0 based on the ServerHello message as described in RFC 5246 if the server selects TLS 1.0 as the highest supported version.

Specifying acceptable TLS cipher suites

Fastly supports configuring the OpenSSL cipher suites used when connecting to your origin server. This allows you to turn specific cipher suites on or off based on security properties and origin server support. The **Ciphersuites** setting accepts an OpenSSL formatted cipher list. We recommend using the strongest cipher suite your origin will support as detailed by the Mozilla SSL Configuration Generator.

Use the `openssl` command to verify your origin supports a given cipher suite. For example:

```
$ openssl s_client -connect origin.example.com:443 -tls1_2 -cipher HE
```

Replace `-cipher ECDHE-RSA-AES128-GCM-SHA256` with the cipher suite to test.

Specifying a TLS client certificate and key

To ensure TLS connections to your origin come from Fastly and aren't random, anonymous requests, set your origin to verify the client using a client certificate. Simply paste the certificate and private key in PEM form into the **TLS client certificate** text box.

IMPORTANT

The private key must not be encrypted with a passphrase.

Then configure your backend to require client certificates and verify them against the CA cert they were signed with. Here are some ways of doing that:

- Apache
- NGINX
- IIS

Fastly also supports securing your connection to origin with mutual TLS (mTLS).

Understanding the difference between certificate hostname and SNI hostname values

The following explains the difference between a certificate and SNI hostname value:

The certificate hostname (`ssl_cert_hostname`). This hostname validates the certificate at origin. It is always required. This value should match the certificate common name (CN) or an available subject alternate name (SAN). It displays as `ssl_cert_hostname` in VCL. This doesn't affect the SNI certification. You can set this value in **Certificate hostname** field.

The SNI hostname (`ssl_sni_hostname`). This hostname determines which certificate should be used for the TLS handshake. SNI is generally only required when your origin is using shared hosting, such as Amazon S3, or when you use multiple certificates at your origin. SNI allows the origin server to know which certificate to use for the connection. This value displays as `ssl_sni_hostname` in VCL. This doesn't affect the certificate validation.

The table below shows you what happens when you set the Certificate and SNI hostname values in the TLS settings:

If Certificate hostname contains...	and SNI hostname contains...	then the Certificate Validation value will be...	and the SNI value will be...
`www.example.com`	nothing	`www.example.com`	nothing
`www.example.com`	`www.example.org`	`www.example.com`	`www.example.or`

About the `ssl_hostname` value (deprecated). The `ssl_hostname` value has been deprecated and replaced with `ssl_cert_hostname` and `ssl_sni_hostname`. Use these two values instead.

> IMPORTANT
>
> If you use an IP address for your `.host` value (i.e., by not entering a value in your certificate hostname), this will generate an error where the certificate hostname specified in your service's origin TLS settings doesn't match either the Common Name (CN) or available Subject Alternate Names (SANs).

Using a wildcard certificate

If you're using a wildcard certificate, you can use any SNI hostname that matches the wildcard certificate. The SNI hostname must be a fully-qualified domain name (FQDN), per RFC 6066.

The table below shows a variety of possible combinations of certificate and SNI hostnames that could be used with a wildcard certificate for `*.example.com`:

Certificate hostname	SNI hostname
`www.example.com`	`www.example.com`
`live.example.com`	`live.example.com`
`*.example.com`	`www.example.com`

If you set the certificate hostname to `*.example.com`, Fastly will treat it as a literal.

What's next

Learn more about working with domains and working with health checks as you continue to refine versions of your service configurations.

---

* * *

Category: Services

These articles provide basic, essential information and instructions for working with services.


About services

/en/guides/about-services

A Fastly service is a user-defined set of caching rules and behaviors for a website or application. You might create new Fastly services to do things like:

- add a new website under your control to your list of web properties
- add a new domain to your growing list of existing domains already served by Fastly
- isolate traffic metrics for specific digital assets, like a site's images

Every service tied to your account contains a unique ID that appears next to the name of your service on any page.




Once created, you can edit and activate new versions of your Fastly services that include refinements and updates to your configurations. The Fastly control panel also allows you to do other things with existing Fastly services, like compare them to each other, deactivate or reactivate them, and delete them.

Before you begin

Before you begin working with Fastly services, be sure you understand the Fastly web interface controls.


Accessing services

Once you're logged in, the **Your services** card displays the services associated with your account, defaulting to those you've designated as your favorites. Each service listed includes a clickable link to the configuration details for that service and a summary of key information about it, including the type of service (CDN or Compute), the current requests per second for it, and the most recently activated service version.



Click either **Compute services** or **CDN services** to access either the Compute services page and CDN services page and view only services of that particular type.

If you have a lot of services, you can view a condensed version of the list by clicking the icon with three lines ☰ above the list of services.



TIP

If you have a lot of services, consider clicking the star ☆ to the left of a service name to mark it as a favorite. You can view a subset of services using filters and include only your favorites.

Understanding Fastly services and versions

When you create a service, before it will do anything, you need to configure it. This configuration will tell Fastly how to handle traffic through your service. Officially, a configuration for a service is called a *version* of that service. You'll notice that your new service has a single, initial version (all new services start their existence this way). The initial version of a service is an inactive blank slate, waiting for you to configure and *activate* it.

Once you activate your first version, your service will begin handling traffic according to your configurations.

Your service can have many versions. Each version has its own status:

- **Draft** is the status that every version starts with when it's first created. This status indicates that the version hasn't been *activated* and is still being edited. Only versions with draft status can be edited.
- **Active** is the status displayed by a version after you activate it. When you activate a version, you are telling Fastly to use that configuration for your service's traffic. Only one version of a service can be active at a time. Once a service becomes active, it also becomes *locked*, so it can no longer be edited, only *deactivated* or *reactivated*.
- **Locked** is the status displayed by a version after you deactivate it. This status primarily indicates that a version can't be edited. Active versions are also locked automatically when they first become active, but they display as active, not as locked.

Eventually, your service will probably have more versions displaying the locked status than any other. At some point, you may decide that one of these locked versions has a configuration you prefer to what is currently active. In that case, you can simply reactivate that version. Or, if some aspects of that version aren't viable anymore, you can *clone* it and make changes to the clone, which will have the draft status. Fastly maintains a complete record of the version history of your service to ensure that you can always roll a service back to any version.

Service creation limits

- **Accounts are limited to a set number of services.** We set a limit on the number of services you can create per account by default based on your account type and any packaged offering you've purchased. Reach out to sales@fastly.com for details on how to increase this limit.
- **Each service is limited to a set number of domains.** We set a limit on the number of domains you can create per service by default based on your account type and any packaged offering you've purchased. However, if you contact support, we may be able to adjust this number for you by working with you to set up and fine-tune domain handling in your service.

Transferring services to other accounts

If several employees at your company independently create testing accounts when learning about Fastly products and services, you can have the services that were created on the testing accounts transferred to another account by contacting support with the following information:

- the Customer IDs of the accounts
- the names of the services to be transferred
- which account should be considered the primary account

After you contact us, we'll reach out to verify the ownership of each account. If we can confirm ownership, we'll initiate the transfer.

> **NOTE**
>
> Account API tokens can't be transferred and don't work across multiple accounts. If you use account API tokens for purging or service automation on the service that you are transferring, an engineer or superuser will need to recreate those API tokens in the account that is receiving the service.

> **TIP**
>
> Fastly's multi account user access feature allows a single user to manage multiple customer accounts. If you've been invited to more than one customer account, you can quickly switch between accounts without logging out of the Fastly control panel.

What's next

Once you understand how services and versions work and their limits, create your first CDN service or Compute service.

---

* * *

	Working with CDN services
🔗	/en/guides/working-with-cdn-services

Once you create a CDN service, you can edit and activate new versions of your Fastly services that include refinements and updates to your configurations. The Fastly control panel also allows you to do other things with existing Fastly services, like compare them to each other, deactivate or reactivate them, and delete them.

Before you begin

Before you create your first Fastly service, be sure you understand how services and versions work and service creation limits. You'll also need to understand the Fastly web interface controls before using them to work with your Fastly services.

> **TIP**
>
> This guide includes instructions for creating and interacting with CDN services. Our Compute documentation provides more information on working with services that take advantage of Compute.

Creating a new CDN service

You can create a new CDN service via the Fastly control panel. Use the steps below to quickly create a CDN service that uses standard defaults common to many customers.

> **TIP**
>
> If you're not ready to fill out all of these fields or prefer to create a draft service immediately, click **Skip and go to service configuration**. We'll automatically create a draft version of a new service, and you can choose to keep or discard any changes you've already made to the service creation fields.

To create a new service:

1. Log in to the Fastly control panel.
2. Click **Create service** at the top right of the page, just below the primary navigation controls.
3. In the **Service name** field, enter a descriptive name for your service (e.g., `My Example Website Service`).
4. In the **Domain** field, enter the name of the domain you want Fastly to use to route requests to. Our guide to working with domains provides additional details.

5. In the **Host** field, enter the name of the host you plan to use as the backend or origin for your site. Our guide to working with hosts provides additional details.

6. Review the **Recommended settings** that are enabled by default for your service and decide whether or not to disable them by clicking the appropriate setting switch to **Off**.

    - The **Override default host** setting enables host override at the origin level. Many customers creating services specify an override host at the same time, especially when using an origin that requires a specific hostname to be passed to it.

    - The **Default compression** setting enables automatic compression using a default compression policy. Automatic compression on our edge servers can help you reduce the size of your assets so traffic can flow faster.

    - The **Force TLS & HSTS** setting enables the HTTP Strict Transport Security (HSTS) security enhancement specification through Fastly and forces modern web browsers to communicate only via the TLS protocol. If you leave this default setting enabled, be sure to create a TLS certificate for use with your domains. For more information, check out our TLS documentation.

7. Finally, do one of the following to finish creating your service:

    - Click **Activate** to create your service and activate it. A new version of your service will be created and locked. You'll need to clone the service version to make additional edits to your service configurations.

    - Click **Save draft** to create your service in a draft state. You can continue editing your service configurations until you're ready to activate

8. Test your service configurations by opening `https://www.example.com.global.prod.fastly.net` in a new browser window, replacing `www.example.com` with your own website's domain name. Your website should appear, though it may take up to 60 seconds for new configuration settings to take effect. You can continue to explore various configuration settings for as long as you like before starting to serve traffic.

9. Once you've reviewed everything and are ready, complete your service setup and start serving traffic through Fastly by setting your domain's CNAME DNS record to point to Fastly.

About the Service summary and Service configuration tabs

After you create your service, you'll see two tabs: the Service summary tab and the Service configuration tab.

The **Service summary** tab lets you review general service details including the event log, duplicate (clone) service versions so you can edit them, and purge content. The Service summary tab also allows you to compare differences between two configuration versions.

The **Service configuration** tab contains the main controls for editing your service configurations. Specifically, you can:

- manage the domains used to route requests to a CDN service
- manage the hosts used as backends for a site and how they should be accessed
- manage the health checks that monitor backend hosts
- enable certain Fastly products for the service, if you are assigned the role of superuser or engineer. Note that this will result in changes to your monthly bill.
- manage various request and cache settings, headers, and responses that control how Fastly caches and serves content for a CDN service
- specify how logging should be performed and where server logs should be sent
- create custom Varnish configuration language (VCL) files
- specify how conditions are mapped and used for a service at various times (e.g., during request processing, when Fastly receives a backend response, or just before an object is potentially cached)

Editing and activating versions of services

With the appropriate permissions, you can activate configuration changes immediately and roll back those changes just as quickly should they not have the intended effect. Fastly locks versions of services you've already activated to make rollbacks safer and provide version control. You can duplicate (*clone*) any existing service version, active or inactive, and edit that cloned version. You must *activate* new versions of services to deploy their configurations. Configuration changes are never automatically activated.

To make changes to a service and activate a new version, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. From the **Edit configuration** menu, select the appropriate service configuration action:


- Select **Clone version *[version number]* (active)** to clone the active version of the service for editing.
- Select **Edit version *[version number]* (latest draft)** to edit the latest draft of the service.

4. Click **Activate**. The new version of the service is activated and appears in the event log.

Switching between services and service versions

To switch between services associated with your account, follow these steps:


1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. From the **Service summary** or **Service configuration** page, click the switcher to the right of the account name and ID.



4. Select the appropriate service from the list that appears.

To switch between versions of a specific service, follow these steps:

1. From the **Service configuration** page, click the switcher to the right of the version number.



2. Select the appropriate version from the list that appears.

Deleting a service

Fastly allows you to delete any service you create, along with all of its versions. Fastly does not offer a way to delete specific versions of a service, however. Service versions are meant to be a historic log of the changes that were made to a service. To undo changes introduced by a particular service version, you can always go back to a previous version and reactivate or clone a new service version based on any old version.

To delete any service along with all of its versions, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. From the **Options** menu, select **Deactivate**.
4. Click **Confirm and deactivate** to confirm you want to deactivate your service and acknowledge that you no longer want to serve traffic with it.
5. From the **Options** menu, select **Delete** and then click **Confirm and delete** to delete the service.

IMPORTANT

To minimize the risk of unauthorized use of your domains, we strongly recommend modifying or deleting any DNS CNAME records pointing to the Fastly hostname associated with the deleted service. Follow the instructions on your DNS provider's website.

Other things you can do

In addition to creating or editing services, you can rename them and delete them. You can also stage, deactivate, or reactivate specific versions of them.

Renaming services

To rename your service, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. From the **Options** menu, select **Edit service name**.
4. In the **Service name** field, enter a new service name.
5. Click **Apply**. The newly renamed service name appears.

Staging service versions


Our Staging documentation provides more information on testing changes to service configurations on a staging network before deploying them to production.

Adding comments to service versions


Service versions can include comments to label them (e.g., to identify reasons for changes in that version). You can add and update version comments on both locked and activated service versions.

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.

4. Click **Add comment** in the upper right corner of the web interface.




The comment window appears.



5. In the **Comment** field, enter a meaningful comment for the version.

6. Click **Save**. The truncated version of the comment appears where the Add comment link used to be.



TIP

You can view service version comments at any time by clicking the service version number to display the version selection menu or by clicking the version comment


icon to display the version comment in a separate window. Version comments also appear in the event log to help with account activity monitoring.

Comparing different service versions

To compare two versions of a service, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Diff versions**. The Diff versions page appears.

   Removals are highlighted in red and the additions and changes are highlighted in green. Any large blocks of unaffected configuration lines can be expanded and viewed or collapsed and hidden by clicking on the plus + sign to the left of the actual changes, next to the line numbers.



> **TIP**
>
> You can change the compared service versions by clicking **Switch versions** and selecting a different version number in the menu that appears.

Deactivating a service

To deactivate a service, follow the steps below:

1. Log in to the Fastly control panel.

2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. From the **Options** menu, select **Deactivate**.
4. In the **Enter service name** field, enter the exact service name to deactivate.
5. Click **Confirm and deactivate** to confirm you want to deactivate your service and acknowledge that you no longer want to serve traffic with it.

> IMPORTANT
>
> To minimize the risk of unauthorized use of your domains, we strongly recommend modifying or deleting any DNS CNAME records pointing to the Fastly hostname associated with the deactivated service. Follow the instructions on your DNS provider's website.

You can also activate or deactivate a service via the API. Did you accidentally delete a service? We can help.

Reactivating a service

To reactivate a service, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Activate**. The service is reactivated.
5. If you removed the DNS CNAME records for the service's domains when you deactivated the service, you should add new DNS CNAME records now.

Getting help with accidental service deletions

Services can be deactivated or deleted. Deactivated services can be reactivated at any time, but once they've been deleted you must contact Customer Support to have them restored. When sending your request, remember to include:

- your customer ID
- your company name

- your service ID (the name of the service you want restored)

Customer Support will notify you when your service has been restored.

What's next

Learn more about working with domains, hosts, and health checks as you continue to refine versions of your service configurations.

---

* * *

📄	**Working with Compute services**
🔗	/en/guides/working-with-compute-services

You can create a Compute service and connect it to a Compute project directly from the Fastly control panel. Once you create your service, you can make refinements and updates to your configuration through the CLI or by editing the service in the Fastly control panel, depending on the task you're trying to complete.

The Fastly control panel also allows you to do other things to manage existing Fastly services, like deactivate or reactivate them and delete them.

Before you begin

Before you create your first Fastly service, be sure you understand how services and versions work and service creation limits. You'll also need to understand the Fastly web interface controls before using them to work with your Fastly services.

Some steps require using the Fastly CLI. If you haven't already, follow the steps for creating an API token, making sure it has `global` scope. Then, download and install the Fastly CLI and use that token to authenticate your account before continuing.

Creating a new Compute service

There are several ways to create a Compute service:

- Use one of our **starter kits**, which provide the basic set up for a Compute project.

- Upload an **existing project** from your computer.
- Create an **empty service** and finish setting up things later.

Our Compute starter kits provide you with a simple project that demonstrates basic Compute behavior. When creating a Compute service from a starter kit, all you need to provide is service name and domain information before deploying your project.

1. Log in to the Fastly control panel.
2. Go to **Compute**.
3. Click **Create service** to start the Compute service setup.
4. Click **Use starter kit** to create a new Compute service from a starter kit.
5. Fill out the service name and domain information:
    - In the **Service name** field, enter a descriptive name for your service (e.g., `My Example Compute Service`).
    - *(Optional)* Fastly automatically generates a domain name for you using the `.edgecompute.app` extension. If you want Fastly to route requests to your personal domain, enter the domain in the **Domain** field. You can also add additional domains after set up.
    - *(Optional)* Leave the checkbox selected to issue a TLS certificate for the domain you entered.
6. Click **Next**.
7. Select from one of our starter kits. We recommend choosing the default starter for your chosen language. You can learn more about these languages and core feature differences in our developer guide.
8. Click **Finalize and deploy**.

   The final page of the Compute service setup includes the status of your deployment, a command to set up your local environment, information for pointing your personal domain at Fastly, and high-level service details.

Checking deployment status

It takes a few minute for your service to deploy globally in our network. Once deployed, a success message appears on the Compute service setup page. If your deployment fails,

a failure message appears along with the reason for the failure and option to re-try or re-start.

Setting up your local environment

While you wait for the service to deploy, you can set up your local development environment. This allows you to work with your Compute project. Copy the `fastly compute init` command from the Compute service setup page and run it in your terminal, making sure you're in the directory where you want to store the project. Follow the onscreen prompts to complete set up.

Pointing your domains at Fastly

If you elected to automatically issue a TLS certificate for your domain, use the provided DNS records to create records and verify domain ownership.

Viewing service details

The Service Details section provides a high-level overview of the details and status of your service creation. You can view the service name, Fastly domain, and service ID. You can also see a status indicating if you've finished deploying and connected to your local machine.

From here, you can edit your service configuration. You can also open the Fastly-assigned domain in your browser to verify your service is working.

If you already have a Compute project started on your local machine, you can use the Fastly control panel to create a new Compute service then upload your project to the service.

1. Log in to the Fastly control panel.
2. Go to **Compute**.
3. Click **Create service** to start the Compute service setup.
4. Click **Upload from my computer**.
5. Fill out the service name and domain information:
    - In the **Service name** field, enter a descriptive name for your service (e.g., `My Example Compute Service`).
    - *(Optional)* Fastly automatically generates a domain name for you using the `.edgecompute.app` extension. If you want Fastly to route requests to your

personal domain, enter the domain in the **Domain** field. You can add additional domains after set up.

- *(Optional)* Leave the checkbox selected to issue a TLS certificate for the domain you entered.

6. Click **Next: Upload your project**.
7. From the **Deploy your project** area, copy the `fastly compute publish` command containing your service ID details.
8. On your computer run the command to build and deploy your project in the directory containing your project.

Checking deployment status

It takes a few minutes for your service to deploy globally in our network. Once deployed, a success message appears on the Compute service setup page. If your deployment fails, a failure message appears along with the reason for the failure and option to retry or restart.

Pointing your domains at Fastly

If you elected to automatically issue a TLS certificate for your domain, use the provided DNS records to create records and verify domain ownership.

You can create an empty Compute service, which is a service without a project or domains attached. You can explore the different service configurations and add your Compute project and domain when ready.

1. Log in to the Fastly control panel.
2. Go to **Compute**.
3. Click **Create service** to start the Compute service setup.
4. Click **Create empty service**.

About the Service summary and Service configuration tabs

After you create your service, you'll see two tabs: the Service summary tab and the Service configuration tab.

The **Service summary** tab lets you review general service details including the event log, duplicate (clone) service versions so you can edit them, and purge content. The Service

summary tab also allows you to compare differences between two configuration versions.

The **Service configuration** tab contains the main controls for editing your service configuration to define exactly how each instance of your Compute services should behave and interact with its data sources. Specifically, you can:

- manage the domains used to route requests to a Compute service
- manage the hosts used as backends for a site and how they should be accessed
- manage the health checks that monitor backend hosts
- enable certain Fastly products for the service, if you are assigned the role of superuser or engineer. Note that this will result in changes to your monthly bill.
- specify how logging should be performed and where server logs should be sent
- upload your Compute compatible Wasm packages once you've built them with the Fastly CLI
- view the metadata of your Compute Wasm package

Editing and activating versions of services

With the appropriate permissions, you can activate configuration changes immediately and roll back those changes just as quickly should they not have the intended effect. Fastly locks versions of services you've already activated to make rollbacks safer and provide version control. You can duplicate (*clone*) any existing service version, active or inactive, and edit that cloned version. You must *activate* new versions of services to deploy their configurations. Configuration changes are never automatically activated.

To make changes to a service and activate a new version, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. From the **Edit configuration** menu, select the appropriate service configuration action:
    - Select **Clone version *[version number]* (active)** to clone the active version of the service for editing.
    - Select **Edit version *[version number]* (latest draft)** to edit the latest draft of the service.

4. Click **Activate**. The new version of the service is activated and appears in the event log.

Deleting a service

Fastly allows you to delete any service you create, along with all of its versions. Fastly does not offer a way to delete specific versions of a service, however. Service versions are meant to be a historic log of the changes that were made to a service. To undo changes introduced by a particular service version, you can always go back to a previous version and reactivate or clone a new service version based on any old version.

To delete any service along with all of its versions, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. From the **Options** menu, select **Deactivate**.
4. Click **Confirm and deactivate** to confirm you want to deactivate your service and acknowledge that you no longer want to serve traffic with it.
5. From the **Options** menu, select **Delete** and then click **Confirm and delete** to delete the service.

IMPORTANT

To minimize the risk of unauthorized use of your domains, we strongly recommend modifying or deleting any DNS CNAME records pointing to the Fastly hostname associated with the deleted service. Follow the instructions on your DNS provider's website.

Other things you can do

In addition to creating or editing services, you can rename them and delete them. You can also stage, deactivate, or reactivate specific versions of them.

Renaming services

To rename your service, follow the steps below:

1. Log in to the Fastly control panel.

2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. From the **Options** menu, select **Edit service name**.
4. In the **Service name** field, enter a new service name.
5. Click **Apply**. The newly renamed service name appears.


Staging service versions

Our Staging documentation provides more information on testing changes to service configurations on a staging network before deploying them to production.


Adding comments to service versions

Service versions can include comments to label them (e.g., to identify reasons for changes in that version). You can add and update version comments on both locked and activated service versions.


1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Add comment** in the upper right corner of the web interface.



The comment window appears.



5. In the **Comment** field, enter a meaningful comment for the version.
6. Click **Save**. The truncated version of the comment appears where the Add comment link used to be.



TIP

You can view service version comments at any time by clicking the service version number to display the version selection menu or by clicking the version comment icon to display the version comment in a separate window. Version comments also appear in the event log to help with account activity monitoring.

Comparing different service versions


To compare two versions of a service, follow the steps below:

1. Log in to the Fastly control panel.

2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.

3. Click **Diff versions**. The Diff versions page appears.

   Removals are highlighted in red and the additions and changes are highlighted in green. Any large blocks of unaffected configuration lines can be expanded and viewed or collapsed and hidden by clicking on the plus + sign to the left of the actual changes, next to the line numbers.



> **TIP**
>
> You can change the compared service versions by clicking **Switch versions** and selecting a different version number in the menu that appears.

Deactivating a service

To deactivate a service, follow the steps below:

1. Log in to the Fastly control panel.

2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.

3. From the **Options** menu, select **Deactivate**.

4. In the **Enter service name** field, enter the exact service name to deactivate.

5. Click **Confirm and deactivate** to confirm you want to deactivate your service and acknowledge that you no longer want to serve traffic with it.

IMPORTANT

To minimize the risk of unauthorized use of your domains, we strongly recommend modifying or deleting any DNS CNAME records pointing to the Fastly hostname associated with the deactivated service. Follow the instructions on your DNS provider's website.

You can also activate or deactivate a service via the API. Did you accidentally delete a service? We can help.

Reactivating a service

To reactivate a service, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Activate**. The service is reactivated.
5. If you removed the DNS CNAME records for the service's domains when you deactivated the service, you should add new DNS CNAME records now.

Getting help with accidental service deletions

Services can be deactivated or deleted. Deactivated services can be reactivated at any time, but once they've been deleted you must contact Customer Support to have them restored. When sending your request, remember to include:

- your customer ID
- your company name
- your service ID (the name of the service you want restored)

Customer Support will notify you when your service has been restored.

What's next

Learn more about working with Compute services.

* * *

	Working with staging
🔗	/en/guides/working-with-staging

Fastly's Staging feature allows you to test changes to your service configuration on a staging network before deploying them to production. To minimize differences between staging and production, staging deploys run on the same type of points of presence (POPs) as production deploys.

You don't need to make changes to your service configuration to use the Staging feature. Staging metrics are kept separate from production metrics, and you can stage a service as many times as you want.


Before you begin

You should review this feature's limitations before using it. By default, the Staging feature is automatically enabled for use in the Fastly API, CLI, and Terraform.

Enabling staging controls in the Fastly control panel

You must enable the Staging feature for use in the Fastly control panel. If you've been assigned the role of superuser, do that by following these steps:

1. Log in to the Fastly control panel.
2. From the **Home** page, select a service.
3. Click the **Opt in to Staging** button.



> **NOTE**
>
> If you previously enabled and then opted out of using the Staging feature for your account, you'll need to contact support to reenable the feature.

Preparing services that use Next-Gen WAF

> **IMPORTANT**
>
> This section only applies to Next-Gen WAF customers with access to the Next-Gen WAF control panel.

If your service is configured to use Next-Gen WAF, run the following command to update your service's delivery integration and enable support for the Staging feature:


```
$ curl -H "x-api-user:$api_user" \
  -H "x-api-token:$signalsciences_key" \
  -H "Content-Type: application/json" \
  -H "Fastly-Key: $fastly_key" https://dashboard.signalsciences.net/api/
  -X PUT -d '{"percentEnabled": 100, "activateVersion": true }'
```

Run the command once for each service configured to use Next-Gen WAF.

Staging a CDN service version

You can stage a CDN service version by using the Fastly control panel, API, CLI, or Terraform.

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Select the version of the service you want to push to staging.
4. Click **Push changes to Staging**.



You can stage a service version using the same API endpoints used for activating and deactivating a version.

```
PUT /service/<service_id>/version/<version_number>/activate/stagi
PUT /service/<service_id>/version/<version_number>/deactivate/staging
```

For example, you can stage a service version using curl in a terminal application.

```
$ curl -X PUT -H "Fastly-Key: $fastly_key" https://api.fastly.com
```

You can stage or unstage a VCL service version by using the Fastly CLI:

```
$ fastly service-version stage --service-id 123 --version 2
$ fastly service-version unstage --service-id 123 --version 2
```

These commands take the same options as the activate command.

You can make as many changes to your development version as you'd like and push them to staging without increasing the version number. When you're ready to deploy the changes to production, activate your service version.

Staging a Compute service version

You can stage a Compute service version by using the Fastly API, CLI, or Terraform.

You can stage a Compute service version using the same API endpoints used for activating and deactivating a service version.

```
PUT /service/<service_id>/version/<version_number>/activate/stagi
```

```
PUT /service/<service_id>/version/<version_number>/deactivate/stag
```

For example, you can stage a Compute service version using curl in a terminal application.

```
$ curl -X PUT -H "Fastly-Key: $fastly_key" https://api.fastly.com
```

You can stage or unstage a Compute service version by using the Fastly CLI:

1. Build the package:

   ```
   $ fastly compute build
   ```

2. Upload the new Wasm package, which will create a draft Compute service version:

   ```
   $ fastly compute update --autoclone
   ```

   This command will output a version number for the draft Compute service version.

3. Stage the draft Compute service version, replacing `<draft version number>` with the version number from the previous step:

   ```
   $ fastly service-version stage --version=<draft version numbe
   ```

As with CDN service versions, you can make as many changes to your development version as you'd like and push them to staging without increasing the version number. When you're ready to deploy the changes to production, activate your service version.


Accessing staging

You can access your service's staging environment in one of two ways. Using the provided Anycast IP address, you can temporarily modify the `hosts` file on your personal computer to test locally, or you can create a DNS A record to create a publicly-accessible domain.

Obtaining your service's staging IP address

Before you can modify the `hosts` file or create a DNS A record, you'll need to obtain the Anycast IP address for your service's staging environment.

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. In the Staging area, click **Guide to testing**. The IP address for your service's staging environment is displayed.



4. Copy the IP address and use it to update your `hosts` file or DNS A record.

> **TIP**
>
> If you don't see the IP address for your staging environment in the Fastly control panel, contact support.

You can obtain your service's staging IP address using the Fastly API endpoint used for listing your service's domains.

```
GET /service/<service_id>/version/<version_number>/domain?include
```

For example, you can obtain your service's staging IP address using curl in a terminal application.

```
$ curl -i \
  -X GET \
  -H "Fastly-Key: $fastly_key" \
  "https://api.fastly.com/service/$service_id/version/$version/domain
```

Updating your Hosts file

To access the staging version from your personal computer, open your local `hosts` file in a text editor. The exact location of the `hosts` file depends on the operating system you're using:

- Linux: `/etc/hosts`
- macOS: `/private/etc/hosts`
- Windows: `C:\Windows\System32\drivers\etc\hosts`

At the end of the file, add an entry for your staging version that includes the staging IP address and the domain name of your production service (for example, `192.0.2.0 www.example.com`). Save the changes to the file.

NOTE

If you're using macOS, flush your DNS cache by entering the following command:

```
$ sudo killall -HUP mDNSResponder
```

Now, when you visit the domain name of your production service on your personal computer (in this example, `www.example.com`), you should see your staging version.

When you've finished testing your staging version, remove the entry from your `hosts` file.

Creating a DNS A record

To access the staging version from a publicly-accessible domain, create a new DNS A record using the IP address provided as the value. Refer to your DNS provider's documentation for exact instructions on how to create or update a DNS A record.

Using variables

You can use variables to tell whether or not your code is running in a staging environment.

VCL

The following VCL variable is available.

Variable name	Description	Type	Access
`fastly.is_staging`	Returns `true` if VCL code is running in your service's staging environment.	`BOOL`	Read only

Compute

The follow Compute variable is available.

Variable name	Description
`FASTLY_IS_STAGING`	Returns `1` if Compute code is running in your service's staging environment and `0` if running in production.

Purging

You can purge cache associated with a staging environment by using the Fastly API purging endpoints. For example, you can purge cache for a staging environment using curl in a terminal application.

Purging by URL

```
$ curl -i \
  -H "Fastly-key: $fastly_key" \
  -X PURGE \
  --connect-to "::$staging_ip:443" \
  "https://$url_to_purge"
```

TIP

If you don't know your staging IP address, refer to our instructions on obtaining your service's staging IP address for more information.

Purging all cache

```
$ curl -i \
  -H "Fastly-Key: $fastly_key" \
  -H "Fastly-Purge-Environment: staging" \
  -X POST \
  "https://api.fastly.com/service/$service_id/purge_all"
```

Purging by surrogate key tag

```
$ curl -i \
  -H "Fastly-key: $fastly_key" \
  -H "Fastly-Purge-Environment: staging" \
  -X POST \
  "https://api.fastly.com/service/$service_id/purge/$surrogate_key"
```

Purging by multiple surrogate key tags

```
$ curl -i \
  -H "Fastly-key: $fastly_key" \
  -H "Fastly-Purge-Environment: staging" \
  -H "Content-type: application/json" \
  -X POST \
  -d '{"surrogate_keys":["key"]}' \
  "https://api.fastly.com/service/$service_id/purge"
```

Deactivating staging for a service version

To deactivate staging for a service version, follow the steps below:


1. Log in to the Fastly control panel.

2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Select the version of the service you want to deactivate from staging.
4. From the **Options** menu, select **Deactivate on Staging**.

Opting out of staging controls in the Fastly control panel

If you've been assigned the role of superuser, follow the steps below to hide the staging controls in the Fastly control panel:

1. Log in to the Fastly control panel.
2. From the **Home** page, select a service that you've staged.
3. In the Staging section of the page, click **Opt out**.



NOTE

You'll still be able to stage service versions using the Fastly API, CLI, and Terraform after you hide the staging controls in the Fastly control panel.

* * *

Category: Web interface

These articles describe key features of the Fastly web interface controls.

About Security

🔗 /en/guides/about-security

The Security controls give you access to the different security products Fastly has to offer. If you have the appropriate access permissions, these controls appear when you go to **Security** in the navigation sidebar.

Before you begin


Be sure you know how to access the web interface controls before learning about each of the pages you'll encounter there.

About the Security pages

When you click **Security** in the navigation sidebar, the Security Overview page appears by default. The **Overview** page provides introductions to various security offerings that can help you protect your services and links you to more information about them. If you have a Signal Sciences account, you can log in to the Next-Gen WAF control panel directly from this page.

To access additional Security pages, select one of the following options:

- **Next-Gen WAF** menu, where you can monitor traffic to your web application and configure the WAF as needed. The workspaces bar persists across the Next-Gen WAF pages. From this bar, you can change your workspace and view the protection mode and ID of a workspace.



- **DDoS Protection** menu, where you can view dashboard metrics and identified events related to DDoS attack traffic when you've enabled DDoS Protection on at least one service.
- **DDoS mitigation** page, where you can learn more about our DDoS mitigation options. Fastly's high-bandwidth globally distributed network was built with "always-on" DDoS mitigation designed to absorb DDoS attacks. You can also purchase a DDoS Protection and Mitigation Service that provides additional Fastly resources to assist you with mitigating the service and financial impacts of DDoS and related attacks.
- **TLS management** menu, where you can find controls for adding HTTPS to your domains, adding additional privacy and data security to your services. You can either

upload your own TLS certificates or have Fastly manage this for you.

- **Edge rate limiting** page, where you can implement a rate limiting policy to control the rate of requests sent to your origin servers.
- **Bot management** page, where you can review potential abusive bot activity on your network.
- **Client-Side Protection** menu, where you can inventory and control the resources (e.g., scripts, images, and fonts) that load on an end user's browser from defined areas of your web applications.

Security products note

No security product, such as a WAF or DDoS mitigation product, including those security services offered by Fastly, will detect or prevent all possible attacks or threats. As a subscriber, you should maintain appropriate security controls on all web applications and origins. The use of Fastly's security products does not relieve you of this obligation. As a subscriber, you should test and validate the effectiveness of Fastly's security services to the extent possible prior to deploying these services in production, continuously monitor their performance, and adjust these services as appropriate to address changes in your web applications, origin services, and configurations of the other aspects of your Fastly services.

What's next

Dig deeper into details about all areas of the web interface before you move on to working with services.

---

* * *

📄	**About the Dashboards page**
🔗	/en/guides/about-the-dashboards-page

IMPORTANT

This guide only applies to customers with access to the Next-Gen WAF product in the Fastly control panel. If you have access to the Next-Gen WAF control panel, check out our web interface guides for the Next-Gen WAF control panel.

The Dashboards page displays the Overview dashboard, which provides a high-level, system-generated overview of metrics related to a Next-Gen WAF workspace.

Before you begin

The Next-Gen WAF is disabled by default. To purchase and enable the product, contact sales@fastly.com. Once enabled, any user will be able to access the Dashboards page for workspaces they have access to.

Be sure you know how to access the web interface controls before learning about the details you'll encounter here.

Accessing the Dashboards page

To access the Dashboards page, follow these steps:

1. Log in to the Fastly control panel.
2. Go to **Security** > **Next-Gen WAF** > **Requests**.
3. From the workspaces bar, click the menu ⌄ to the right of the workspace name and select a workspace.

About the controls on the Dashboards page

On the Dashboards page, you can refine the metrics displayed and gain more information by:

- using the menu below the dashboard name to change the timeframe.
- hovering over any part of a graph to access a timestamp indicator that updates as you move the cursor.
- clicking the button at the bottom of a card to access information related to the metric.

About the Overview dashboard

The Overview dashboard includes the following cards:

- **Request volume:** a graph displaying the number of requests the workspace received over time.
- **OWASP Injection Attacks:** a graph displaying the most common OWASP Top 10 attacks the workspace received over time.
- **Scanners:** a graph displaying the number of commercial and open source scanning tools over time.
- **Traffic Source Anomalies:** a graph displaying the number of requests from unusual or suspicious sources over time.
- **Request Anomalies:** a graph displaying the number of anomalous behaviors within request headers over time.
- **Response Anomalies:** a graph displaying the number of client and server error codes over time.
- **Events:** a list of IP addresses that were flagged for exceeding thresholds.

What's next

Learn more about Next-Gen WAF features that can help you monitor and protect your web applications from malicious traffic.

---

* * *

	About the Events page
🔗	/en/guides/about-the-events-page

IMPORTANT

This guide only applies to customers with access to the Next-Gen WAF product in the Fastly control panel. If you have access to the Next-Gen WAF control panel, check out our web interface guides for the Next-Gen WAF control panel.

The Events page lists all IP addresses that the Next-Gen WAF flagged in the past 30 days as a result of workspace alerts.

Before you begin

The Next-Gen WAF is disabled by default. To purchase and enable the product, contact sales@fastly.com. Once enabled, any user will be able to access the Events page for workspaces they have access to.

Be sure you know how to access the web interface controls before learning about the details you'll encounter here.

Accessing the Events page

To access the Events page, follow these steps:

1. Log in to the Fastly control panel.
2. Go to **Security** > **Next-Gen WAF** > **Events**.
3. From the workspaces bar, click the menu ⌄ to the right of the workspace name and select a workspace.

About the controls on the Events page

From the Events page, you can:

- enter an IP address into the search bar to find events related to that IP address.
- filter the events list by the event's status (active or expired), by the signal the event was tagged with, and by when the event occurred.
- click **Refresh** to remove all search parameters.
- click the document icon next to an event to access the Event detail page for that event.

About the Event detail page

The Event detail page displays event-related information on three cards. You can use this information to help determine how to handle the IP address and then:

- click **Remove flag** to remove the IP address from the flag list.
- click **Convert to rule** to create a rule that is based on select characteristics of the event.

About the event overview card

The event overview card is the first card on the Event detail page and contains detailed information about the event and associated IP address, including:

- **IP:** the IP address that was flagged.
- **Status:** the status of the event, either Active or Expired.
- **Country:** the country where the request originated.
- **Action:** additional actions taken on the IP address while flagged.
- **Host:** the host where the request originated.
- **User agents:** the user agents seen from this IP address. This list may include web browsers, media players, and other plug-ins.

About the Event Timeline card

The Event Timeline card contains a timeline illustrating the actions leading up to and during the event, including:

- when the IP address was identified as suspicious.
- the number of requests received from the IP address before it was flagged.
- when the IP address was flagged.
- the number of requests that were blocked or logged.
- the current status of the IP address.

About the Sample Request card

The Sample Request card highlights a single request received during the event, including the request itself and the signals applied to it. Clicking **View this request** takes you to the Request details page for that request.

---

* * *

About the Home page

🔗 /en/guides/about-the-home-page

The Home page displays summary information about all services associated with your account. Think of it as a dashboard where you can get quick insights and basic information about your services along with some aggregate, high-level metrics about them. You can use the dashboard to view who's a user on your team and edit their roles or even invite more users to your account. The dashboard also provides links to helpful resources you may need as you navigate your way around the Fastly app.


Before you begin

Be sure you know how to access the web interface controls before learning about each of the pages you'll encounter there.

About the Home page

The Home page appears automatically when users with the appropriate access permissions log in to the Fastly control panel. You can access it by clicking **Home** in the navigation sidebar.

About the Your services card



The **Your services** card displays the services associated with your account and defaulting to those you've designated as your favorites. Each service listed includes a clickable link to the configuration details for that service and a summary of key information about it, including the type of service (CDN or Compute), the current requests per second for it, and the most recently activated service version.


You can change the displayed list of services on the card by selecting a different sort order from the menu to the right of the search field. Other filtering options besides the default **Favorites** include:

- most recently viewed

- most recently activated
- highest number of requests per second
- most recently created

Clicking the **Compute services** and **CDN services** links that appear to the right of the card's title will take you to the **Compute** and **Deliver** pages respectively where you can view all of the services of that type associated with your account and access the main controls for editing their configuration.


About the Regional account stats card



The **Regional account stats** card displays summarized, basic metrics and a map of parts of the world to help you visualize their source. Clicking **Observability** to the right of the card title takes you to the **Observability page** where you can access additional stats details for all your services.

By default, the map and summary stats displayed represent metrics globally around the world. You can select a smaller area of the world by selecting that area from the left most menu immediately below the card title. Likewise, you can select a variety of other stats to display by selecting one from the right most menu immediately below the card title.

About the aggregate account-level stats cards



The aggregate account level stats cards provide a high-level overview of metrics for all your services for the current month. Specifically, it displays four small cards summarizing current, month-to-date details about:

- **Requests:** the number of requests Fastly receives for your services
- **Hit ratio:** the percentage of content being accessed and currently cached by Fastly
- **Errors:** the number of error requests that occurred over time
- **Error ratio:** the percentage of cache errors for your services over time


It also displays three large cards with current, month-to-date graphs broken down by day and detailing:

- **Requests:** a graph displaying the total number of requests received for your site by Fastly

- **Bandwidth:** a graph displaying the bandwidth served from Fastly's servers to your website's visitors
- **Hit ratio:** a graph displaying the percentage of content being accessed that is currently cached by Fastly


To learn more about how these stats are calculated, refer to our Historical Stats API and latency documentation.

About the TLS overview card



The **TLS overview** card shows you the current state of any Fastly-managed and self-managed TLS certificates associated with your account. Click **More details** to the right of the card title to access the TLS Certificate dashboard. From this dashboard, you can manage and track additional details about certificate statuses and actions.

About the Plan usage card




The **Plan usage** card shows you the current month's details about basic usage metrics associated with the products and services you've purchased for your account. Click **More details** to the right of the card title to access your account's plan usage. There you'll be able to view your account usage metrics broken down by product and region over key, monthly timeframes.

About the Explore Fastly card

The **Explore Fastly** card provides a curated list of documentation links for key features and products of Fastly that can help you do things like speed up defeat threats and protect your website, speed up your site and optimize images, and build an observability system with streaming logs. Click the links to the right of the card title to access Fastly's complete documentation content.

About the Your Team card



The **Your team** card displays a paginated list of users associated with your account. Depending on your assigned role, each user displayed may also include an **Edit** link to the right of their name that directs superusers to the user management controls.

Click the links to the right of the card title to invite a team member or to manage all users and their accounts.

About the Helpful resources card

The **Helpful resources** card provides links to commonly accessed help and information resources that Fastly provides, including:

- a direct line of contact for support if you're stuck and need help
- a way to get in touch with our Sales experts if you need to discuss product and feature options for a tailored experience
- direct links to our main documentation site housing how-to guides and product documentation, the Fastly Community site, and the Fastly Academy site

What's next

Dig deeper into details about all areas of the web interface controls before you move on to using them to work with services.

---

* * *

About the Requests page

/en/guides/about-the-requests-page

IMPORTANT

This guide only applies to customers with access to the Next-Gen WAF product in the Fastly control panel. If you have access to the Next-Gen WAF control panel, check out our web interface guides for the Next-Gen WAF control panel.

The Requests page lists requests that were made to your web application and logged by the Next-Gen WAF.

Before you begin

The Next-Gen WAF is disabled by default. To purchase and enable the product, contact sales@fastly.com. Once enabled, any user will be able to access the Requests page for workspaces they have access to.

Be sure you know how to access the web interface controls before learning about the details you'll encounter here.

Accessing the Requests page

To access the Requests page, follow these steps:

1. Log in to the Fastly control panel.
2. Go to **Security** > **Next-Gen WAF** > **Requests**.
3. From the workspaces bar, click the menu ⌄ to the right of the workspace name and select a workspace.

About the Requests page

From the Requests page, you can:

- enter queries in the search bar and click **Search** to filter the requests list.
- use the time menu to filter the requests list by when the requests were made.

- click **Query builder** to open the query builder and construct a search query based on HTTP status codes and signals.
- click **Refresh** to remove all search parameters.
- click on signals and linked data in the table to filter the table's contents. For example, clicking on a source IP will constrain the results to all requests made by that IP.
- click the document icon to access the Request detail page for a request.

About the Request details page

The Request details page displays all logged data for an individual request. The data is organized by the following categories:

- server
- request
- request headers
- signals
- remote client
- response
- response headers

From this page, you can click **Convert to rule** to create a rule that is based on select characteristics of the request.

---

* * *

	About the search controls
	/en/guides/about-the-search-controls

Can't find exactly what you're looking for using the navigation controls? The universal search controls allow you to search globally across your account to find details about key information. Enter search terms like specific service names or user names to get

suggestions or limit your search to specific data types by using filters. You'll only see results appropriate to the roles and permissions you've been granted for your account.

Before you begin

Be sure you know how to access the web interface controls before learning about the details you'll encounter here.

Limitations and considerations

The universal search controls only appear in the Fastly control panel and aren't available in the Next-Gen WAF control panel.

Using the search controls

Use the search controls to find information globally across your account. To narrow your search results, you can use filters as part of your initial search.

> **TIP**
>
> Are the search results not showing you what you expect? Check your roles and permissions to make sure you have the appropriate access to it.

Searching for data

To search for something, display all the results, and then use those results to navigate to what you're looking for, follow these steps:

1. Log in to the Fastly control panel.
2. In the **Search** field at the top of the page, enter your search term. By default, all results will begin to appear as you type unless you've chosen to refine the results by limiting them to a specific subset using filters.
3. From the search results that appear below the field, select the appropriate result either by clicking on it directly or by using the up and down arrow keys and then pressing **Enter** when the specific result you need is highlighted.

> **TIP**
>
> Recent searches you've conducted appear below the search results.

Fine-tuning search results with filters

You can limit the results you'll receive during searches by prefacing search terms with words that have special meaning. These special words, called filters, restrict your data to a specific kind of result.

Filter	Data displayed
`services:`	Only the services your roles and permissions allow you access to.
`users:`	Only the users associated with your account. This filter is only available if you've been assigned the role of superuser.
`tlscertificates:`	Only the TLS certificates associated with your account.
`pages:`	Only navigation pages that appear in the Fastly control panel.
`docs:`	Only relevant documentation topics.

To use filters, enter the filter name (followed immediately by a colon) and the search terms of the data you're looking for directly in the search field. For example, to search for your `www.example.com` service, you would enter `services: www.example.com` in the search field.

> **TIP**
>
> Clicking the search filter buttons below the search field will enter the filter names into the search field for you automatically.

What's next

Dig deeper into details about all areas of the web interface before you move on to working with services.

---

* * *

	About the Signals page
🔗	/en/guides/about-the-signals-page

IMPORTANT

This guide only applies to customers with access to the Next-Gen WAF product in the Fastly control panel. If you have access to the Next-Gen WAF control panel, check out our web interface guides for the Next-Gen WAF control panel.

The Signals page lists the system signals that are available to a workspace. Signals are labels that the Next-Gen WAF applies to requests that contain important request properties.

Before you begin

The Next-Gen WAF is disabled by default. To purchase and enable the product, contact sales@fastly.com. Once enabled, any user will be able to access the Signals page for workspaces they have access to.

Be sure you know how to access the web interface controls before learning about the details you'll encounter here.

Accessing the Signals page

To access the Signals page, follow these steps:

1. Log in to the Fastly control panel.
2. Go to **Security** > **Next-Gen WAF** > **Signals**.
3. From the workspaces bar, click the menu ⌄ to the right of the workspace name and select a workspace.

About the Signals page

From the Signals page, you can:

- view the system signals for a site. Each signal contains a brief description, and the number of requests that have been tagged with the signal.
- enter text into the search bar to find a signal by name or description.
- use filters to narrow down the signals list. You can filter by signal status and category (e.g., OWASP attack, scanner, CVE).

- click the document icon for a signal to access a detailed overview of the signal's activity.

* * *

	About the user quick links menu
🔗	/en/guides/about-the-user-quick-links-menu


The user quick links menu provide you with direct links to account, billing, and contact information you're likely to want access to most often.

Before you begin

Be sure you know how to access the web interface controls before learning about the details you'll encounter here.

About the user quick links menu

The user quick links menu appears at the far right of the top navigation controls when you log in to the Fastly control panel:



Depending on the roles and permissions assigned to you, you can use this menu to:

- access company settings where you can update things like your company owner and company contacts, as well as enable a login IP allowlist, enable company-wide account options (e.g., two-factor authentication), and cancel your account.
- manage profile and security information about your account
- access your account's billing-related details (if you've been assigned a role with billing access)
- request help from Fastly Support
- contact Sales
- log out of the Fastly control panel
- change the theme of the Fastly control panel to light (the default) or dark

What's next

Dig deeper into details about all areas of the web interface before you move on to working with services.

---

* * *

📄	**About the web interface controls**
🔗	/en/guides/about-the-web-interface-controls

Fastly provides web interface access to all of its features and functions, which are also accessible using Fastly's application programming interface (API).

Before you begin

Before you begin learning about the Fastly web interface controls, it's useful to know the basics of content delivery.

Accessing Fastly's web interface controls


Access to Fastly's web interface controls requires you to sign up for a Fastly account. Creating an account is free. Once you've created an account, you can navigate to the controls via the Fastly login page at https://manage.fastly.com, either directly using any standard web browser or by clicking a link at the top right of almost all pages at the Fastly website.

About the web interface controls

If it's your first time logging in, the basic controls may appear a bit empty. More details will begin to appear as you start working with services.

Top navigation bar

The top navigation bar appears across the top of the Fastly web interface. It contains primary navigation elements that include the name of the company for the account you're logged into, the search field, a link you can use to give Fastly feedback, and a switcher menu ⁘ that provides direct access to both the Fastly and Next-Gen WAF control panels from a single location.



The user quick links menu appears to the right of the switcher menu . You can use the user quick links menu to access account-specific settings, billing-related details, and support links.

Navigation sidebar

The navigation sidebar provides access to:

- the **Home** page, which appears by default when you log in, where you view summarized details about all your services
- the **Observability** controls that you can use to monitor real-time and historic caching-related details about a specific service
- the **CDN** page where you define the settings that specifically control how cached content should behave and be delivered
- the **Compute** page where you define how each instance of your Wasm services should behave and interact with its data sources
- the **Security** controls that you can use to access the different security products Fastly has to offer
- the **Resources** controls that you can use to access data stores shared by your services
- the **Account** controls that you can use to access account-specific settings, personal profile information, and billing-related details

TIP

Check with a superuser on your account if you don't have access to the links you expect to. The roles and permissions assigned by whoever manages your company's account can change which of the navigation links you have access to.

Changing the control panel theme

You can change the theme of the Fastly control panel by logging in to your account and clicking the **Dark theme** switch in the user quick links menu to **On** or **Off** as appropriate.

Browser requirements and recommendations

To access the Fastly web interface, your web browser must be configured to support cookies, JavaScript, and site data (also referred to as local storage or web storage).

We support a minimum display width of 768 pixels on the latest version of the following browsers:

- Google Chrome
- Firefox
- Safari

If you aren't using one of these browsers, then some visual styling may not be correct when using the Fastly web interface.

We strongly recommend updating your browser before beginning any debugging of Fastly services and before reporting problems to Fastly Customer Support. You can find the latest, downloadable versions of all major browsers online. The list at Browse Happy may help you.

What's next

Dig deeper into details about all areas of the web interface before you move on to working with services.

---

* * *

Integrations guides

Category: Streaming logs

These articles describe how we support real-time log streaming of data that passes through Fastly.

About Fastly's real-time log streaming features

🔗 /en/guides/about-fastlys-realtime-log-streaming-features

To help you tune the performance of your Fastly services, we support real-time log streaming of data that passes through Fastly. We support a number of protocols that allow you to stream logs to a variety of locations, including third-party services, for storage and analysis.

Supported protocols and logging providers

Fastly supports a variety of syslog-compatible logging providers, such as Sumo Logic and Papertrail. In addition, we provide a syslog endpoint specifically for sending log files to other syslog-based software (for example, to Logstash, part of the ELK stack, which supports input via syslog).

We also support other methods of sending logs besides the syslog protocol. We allow pushing of log files to Amazon S3 buckets as well as any S3-compatible providers (such as DreamHost's DreamObjects). And we support FTP uploading.

As part of our third-party integrations, Fastly offers a number of endpoints to which you can stream logs. If the logging endpoint you're looking for isn't here, contact support for suggestions on another endpoint that might provide the same functionality.

Supported log streaming features

Fastly's real-time log streaming supports the following specific features:

- **TLS support.** Fastly allows logging configuration information to be sent over TLS (Transport Layer Security) for certain endpoints. This means that logging information can be encrypted while in transit, which allows you to send potentially sensitive information to log files without exposing data.
- **Encryption.** Fastly allows you to encrypt log files for certain endpoints before they are written to disk. We encrypt files using OpenPGP (Pretty Good Privacy). For our Amazon S3 endpoint in particular, we also support server-side encryption.
- **Customized log formats.** Fastly allows you to change the format of your logs by providing variables compatible with the Apache Common Log Format (NCSA Common log format).

- **Log file locations.** Fastly provides two different ways for you to change where your log files are written for certain endpoints. You can change a log file's timestamp format (for example, if you wanted to remove characters from the log file name) and you can control the specific path to which those files are written.
- **Multiple endpoints.** Fastly allows you to send logs to multiple endpoints.
- **Allowlisting.** Fastly's publicly available list of IP ranges allows you to enable Fastly-only access to your logging servers through your firewall.

How real-time log streaming works

Varnish sends all streaming log records to a log aggregator, which streams them in near-real-time to the logging endpoint you configure.

---

* * *

	Changing log compression formats
🔗	/en/guides/changing-log-compression-options

Fastly's Real-Time Log Streaming feature allows you to specify compression format and options for file-based logging endpoints. These include the Azure Blob, FTP, Google Cloud Storage, Kafka, OpenStack, Amazon S3, SFTP, Digital Ocean, and Cloud Files logging endpoints.

Available log compression formats

Although the default is to use no compression, we allow you to choose one of several compression mechanisms:


- **Zstandard**, a compression algorithm defined by RFC 8478
- **Snappy**, a compression and decompression library used by many Google products as referenced in the Snappy compressed format description
- **Gzip**, a compression utility as defined in RFC 1952 and RFC 1951

Using a different compression format

> **IMPORTANT**
>
> If you're using Gzip compression, the Fastly control panel defaults to a Gzip compression level of 3 and can only be changed using the Logging API. If the Gzip compression level has been set to a value other than `3` via an API call, then that level is displayed as a read-only value.

Follow these instructions to update a file-based logging endpoint's compression format using the Fastly control panel:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Logging**.
5. Click the name of a file-based logging endpoint you want to edit.
6. Click **Advanced options** near the bottom of the page.
7. In the **Compression** section, select a compression format for the logging endpoint.



8. Click **Update**.
9. Click **Activate** to deploy your configuration changes.

You can use the Logging API for any file-based logging endpoint to update the compression format.

The API provides two fields for specifying log file compression options: `compression_codec` and `gzip_level`.

- `compression_codec` is a string that specifies the codec used to compress your logs. One of the following:
  - `zstd` Use Zstandard compression.
  - `snappy` Use Snappy compression.
  - `gzip` Use Gzip. Defaults to gzip compression level 3.
- `gzip_level` is an integer in the range of 0, signifying no compression, to 9, signifying maximum compression.

> **NOTE**
>
> Use of `compression_codec` is recommended over use of `gzip_level` unless you need to set the gzip compression level to a value other than 3.

Keep in mind the following with respect to the request payload:

- Only one of `compression_codec` or `gzip_level` should be included in a request payload. Specifying both will result in an error.
- If `compression_codec` is set to "gzip", `gzip_level` will default to 3.
- If `compression_codec` is not specified in the request payload and a non-zero value for `gzip_level` is set, then `compression_codec` will default to "gzip".
- If neither `compression_codec` nor `gzip_level` is specified in the request, no compression is applied to log files and `compression_codec` will default to `null`.

For example, to update the compression format for a service's SFTP logging endpoint to use the Snappy compression codec, the curl command would look something like this:

```
$ curl -X PUT -H "Fastly-Key: YOUR_FASTLY_TOKEN"  -H "Accept:
```

To apply gzip compression to an Azure Blob Storage logging endpoint using the `compression_codec` field, the curl command would look like this:

```
$ curl -X PUT -H "Fastly-Key: YOUR_FASTLY_TOKEN"  -H "Accept: app
```

To update a Google Cloud Storage logging endpoint's compression format to 1 using the `gzip_level` field, the curl command would look like this:

```
$ curl -X PUT -H "Fastly-Key: YOUR_FASTLY_TOKEN"  -H "Accept: app
```

* * *



Changing log line formats



/en/guides/changing-log-line-formats

Fastly's Real-Time Log Streaming feature allows you to change the format that your log messages are delivered in on select logging endpoints. We allow you to choose one of several formats:

- **Blank** is the default. There's no prefix — just your log message. This is useful when writing to JSON and CSV files.
- **Classic** is a legacy format based on RFC 3164. Read Classic Format for more information.
- **Loggly** is a structured syslog prefix format based on RFC 5424.
- **Logplex** is a Heroku-style prefixed syslog format.

Using a different log line format

A number of logging endpoints can be updated to use a message format other than the default via either the Fastly control panel or the API.

Follow these instructions to update a logging endpoint using the Fastly control panel:

1. Log in to the Fastly control panel.

2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Logging**.
5. Click the name of a logging endpoint you want to edit.
6. Click **Advanced options** near the bottom of the page.
7. In the **Select a log line format** section, select a log line format for the logging endpoint.
8. Click **Update**.
9. Click **Activate** to deploy your configuration changes.

Run the following command to update a logging endpoint using the API:

```
$ curl -X PUT -H 'Fastly-Key: FASTLY_API_TOKEN' -H 'Content-Type:
```

Keep in mind that the `message_type` field is a per-object field. Updating it on one logging object *will not* change it on any other objects.

For example, to update a Google Cloud Storage logging endpoint named `GCS Test` to use the `blank` message type, the curl command would look something like this:

```
$ curl -X PUT -H 'Fastly-Key: FASTLY_API_TOKEN' -H 'Content-Type:
```

> **NOTE**
>
> The `log name` included a space that needed to be URL encoded (the space into `%20`).

Classic Format

Classic is a legacy format based on the RFC 3164 protocol. It is not, however, strictly compliant with RFC 3164. To make logging easier to synchronize across a global network,

classic uses timestamps based on the RFC 3339 protocol, which specifies that timestamps include a time zone. RFC 3164, on the other hand, specifies local time without any time zone data.

The following example shows a message in the classic log format.

```
<134>2016-07-04T22:37:26Z cache-sjc3128 LogTest[62959]: <your log m ag
```

The prefix begins with the message priority (always `<134>`, which means `Facility=Local0, Severity=Informational`), followed by the date and time the log was sent (`2016-07-04T22:37:26Z`), the cache node it came from (in this case, `cache-sjc3128`), the name of your log (`LogTest`) and the ID of the process sending it (`62959`).

---

* * *

📄	**Changing log placement**
🔗	/en/guides/changing-log-placement

Fastly's Real-Time Log Streaming feature allows you to specify where the logging call should be placed in the generated VCL.

Available log placement options


You can choose one of the following log placement options:

- **Format Version Default** puts the log statement in `vcl_log` if the logging endpoint is using version 2 log format. If the logging endpoint is using version 1 log format, puts the log statement in `vcl_deliver`.
- **None** prevents the log statement from being rendered in VCL. Use this option if you intend to write a log statement manually in custom VCL.

Changing log placement

Follow these instructions to update a logging endpoint's VCL placement using the Fastly control panel:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Logging**.
5. Click the name of the logging endpoint you want to edit.
6. In the **Placement** section, select a placement for the logging endpoint.



7. Click **Update**.
8. Click **Activate** to deploy your configuration changes.

You can use the API to update a logging endpoint's VCL placement. The API provides a `placement` field for specifying where in the generated VCL the logging call should be placed. It can be one of the following:

- `""` uses the default version placement when not set. Logging endpoints using version 2 log format are placed in `vcl_log`. Logging endpoints using version 1 log format are placed in `vcl_deliver`.
- `none` prevents the log statement from being rendered in VCL. Use this option if you intend to write a log statement manually in custom VCL.

  For example, to update the logging placement to `none`, the curl command would look like this:

```
$ curl -X PUT -H 'Fastly-Key: FASTLY_API_TOKEN' -H 'Content-T
```

* * *

Changing where log files are written

/en/guides/changing-where-log-files-are-written

For supported logging endpoints that write files to remote services, Fastly uses a combination of factors to ensure log files aren't overwritten, including:

- Using the file creation timestamp.
- Generating a unique ID.
- If a file with the same timestamp and UID combination exists, incrementing a counter and adding that to the end of the filename.

To change where log files are written, you can modify the `path` and `timestamp_format` variables on select endpoints. The logging system combines the `path`, `timestamp_format`, and `uid` variables to create the file name:

```
<path><timestamp>-<uid>.log<suffixes>
```

This guide explains how to use the `path` and `timestamp_format` variables to control where log files are written.

Timestamp format

You may want to consider changing the timestamp format to remove characters from the log filenames. For example, if you're working with Elastic MapReduce, you might need to remove the colons in the filename.

The `timestamp_format` variable is provided as a strftime compatible format. The default format is ISO 8601 Combined Date/Time Format:

```
%Y-%m-%dT%H:%M:%S.000
```

The variables are expanded when the file is created. For example, `%Y` will be replaced by the current year and `%m` by the current month number:

```
<year>-<2 digit month number>-<2 digit day number>T<hour>:<minute>:
```

The timestamp for a file created at midnight on January 1st, 1970 would be `1970-01-01T00:00:00.000`.

Path

File-based (e.g., SFTP) and object-based (e.g., S3) endpoints use the `path` variable in different ways. File-based endpoints use `path` to create directories and files in the logging endpoint's storage. Directories will be created automatically if possible. Object-based endpoints use `path` plus the file name to create the key in an object store. No actual directories are created by object-based endpoints because they don't use directory structures in their storage.

File-based and object-based endpoints both look for `/` characters in `path`. If `path` ends in a trailing `/`, then `path` is treated as a directory by a file-based endpoint and as a *folder* (the logical equivalent of a directory) by an object-based endpoint. For example, if the value of `path` were `my_logs/`, then log files would be written to the directory (or *folder*) `my_logs`. However, if the value of `path` were `my_logs`, without the trailing `/`, then log files would be written to the top-level directory and would be prefixed with the string `my_logs`. Furthermore, if the value of `path` were `my_logs/foo`, then log files would be written to the `my_logs` directory and would be prefixed with the string `foo`.

> **TIP**
>
> The path can also be a `strftime` compatible string. For example, if the variable is set to `%Y/%m/%d`, the files are written to a directory based on the year, month, and date.

Suffixes

Fastly's logging system automatically adds suffixes to files as appropriate.

Suffix	File type
.log	Plain log file
.log.gz	Gzipped log file
.log.gpg	PGP encrypted log file
.log.gz.gpg	PGP encrypted, Gzipped log file

* * *

Configuring Google IAM service account impersonation to avoid storing keys on Fastly logging

/en/guides/configuring-google-iam-service-account-impersonation-for-fastly-logging

When adding Google Cloud Storage, BigQuery, or Pub/Sub logging endpoints, we recommend configuring Google IAM role-based service account impersonation to avoid storing secrets by using temporary credentials instead.

To configure role-based service account impersonation through the Google Cloud Console, follow the steps below:

1. Log in to the Google Cloud Console.
2. Navigate to the IAM & Admin page.
3. Review the project name to the left of the search field on the main toolbar and make sure this is the project configured for the Fastly Google endpoint. If not, use this project selection menu to select the correct project as necessary.
4. From the left navigation, click **Service Accounts**.
5. Click the email address of the service account you intend to use for the Logging endpoint.

6. Click **Permissions**.
7. Click **Grant Access**.
8. In the **New principals** field, enter:

```
fastly-logging@datalog-bulleit-9e86.iam.gserviceaccount.com
```

9. Click the **Role** menu to expose the Filter field.
10. In the **Filter** field, enter `Service Account Token Creator` and then select it from the list of roles that appears.
11. Click **Save**.

Once you've configured your Google IAM settings for role-based service account impersonation, make a note of the service account's name and its associated project ID. You'll need this information when adding GCS as your logging endpoint. The service account ID comes before the `@` in the service account email and the project ID immediately after. For example, if your service account email is `my-name@projectid.iam.gserviceaccount.com`, the service account ID is `my-name` and the project ID is `projectid`.

> **TIP**
>
> Check out Google's docs for details on how to configure role-based service account impersonation through the command line interface.

* * *

Creating an AWS IAM role for Fastly logging

/en/guides/creating-an-aws-iam-role-for-fastly-logging

Before adding Amazon S3 or Amazon Kinesis as a logging endpoint for Fastly services, we recommend creating an Identity and Access Management (IAM) role in AWS specifically for Fastly. Using your Fastly customer account ID and the Fastly AWS account number, you can set up a role to give Fastly access to your S3 bucket or Kinesis data stream for log delivery

using temporary credentials instead of long-term credentials like an access key and secret key pair.

You can do this through the AWS Management Console or the AWS CLI.

Creating an IAM role through the AWS Management Console

Follow the steps below to create an IAM role through the AWS Management Console.

1. Log in to the AWS Management Console and open the IAM console.
2. Create a permission policy that gives Fastly permission to write objects to AWS. Click **Create policy**.
3. Click **JSON**. Copy and paste one of the following templates, replacing the name in the resource field with the Amazon Resource Name (ARN) of the Amazon S3 bucket or Kinesis data stream you want Fastly to write logs to.

Amazon S3 template — json

```
{
      "Version": "2012-10-17",
      "Statement": {
          "Effect": "Allow",
          "Action": [
             "s3:PutObject",
             "s3:AbortMultipartUpload"
          ],
          "Resource": "arn:aws:s3:::YourS3BucketName/*"
      }
 }
```

Amazon Kinesis template — json

```
{
      "Version": "2012-10-17",
      "Statement": {
          "Effect": "Allow",
      "Action": [
```

```
            "kinesis:PutRecords",
            "kinesis:ListShards"
            ],
        "Resource": "arn:aws:kinesis:::YourKinesisStreamName"
        }
    }

```

4. Click **Create policy**.
5. Create a role with the trust and permissions policies attached. Select **Roles** from the navigation panel, and then click **Create role**.
6. For **Select type of trusted entity**, select **Another AWS account**.
7. For **Account ID**, enter the Fastly AWS account ID (`717331877981`).
8. Select **Require external ID**.
9. In the **External ID** field, enter your Fastly customer account ID.
10. Click **Next: Permissions**.
11. Select the checkbox next to the permission policy you created above.
12. Click **Next: Tags**.
13. *(Optional)* Add metadata to the role by attaching tags as key–value pairs. For more information about using tags in IAM, check out Amazon's documentation on tagging IAM resources.
14. Click **Next: Review**. Complete the following fields:
    - In the **Role name** field, enter a name for your role. Role names must be unique within your AWS account. They are not distinguished by case. Because other AWS resources might reference the role, you can't edit the name of the role after it has been created.
    - *(Optional)* In the **Role description** field, enter a description for the new role.
15. Review the role and then click **Create role**. The role you created appears in the list of roles on the **Roles** tab.

16. Follow the instructions in Enabling Regional Tokens to ensure your AWS account is set up to allow tokens using regional STS endpoints.

After you create your new role, select the role from the **Roles** tab to view details about the role, including the Role ARN. You will need this ARN to create your logging endpoint.

Creating an IAM role through the AWS CLI

Follow the steps below to create an IAM role through the AWS CLI:

1. Create a trust policy in JSON using your Fastly customer account ID and the Fastly AWS account number using one of the following templates. Copy the template to a text editor and replace `FastlyCustomerAccountID` with your customer account ID and `Sid` with the name of your policy. Save the file to your file system.

Amazon S3 template — json

```
{
        "Version": "2012-10-17",
        "Statement": {
            "Condition": {
                "StringEquals": {
                    "sts:ExternalId": "FastlyCustomerAccountID"
                }
            },
            "Action": "sts:AssumeRole",
            "Principal": {
                "AWS": "717331877981"
            },
            "Effect": "Allow",
            "Sid": "S3LoggingTrustPolicy"
        }
    }
```

Amazon Kinesis template — json

```
{
        "Version": "2012-10-17",
        "Statement": {
```

```
            "Condition": {
                "StringEquals": {
                    "sts:ExternalId": "FastlyCustomerAccount
                }
            },
            "Action": "sts:AssumeRole",
            "Principal": {
                "AWS": "717331877981"
            },
            "Effect": "Allow",
            "Sid": "KinesisLoggingTrustPolicy"
        }
    }

```

2. Create a permission policy in JSON using the Amazon Resource Name (ARN) of the S3 bucket or Kinesis data stream you want Fastly to write logs to. Copy the template to a text editor and replace the name in the resource field with the name of the S3 bucket or Kinesis data stream. Save the file to your file system.

Amazon S3 template json

```
{
    "Version": "2012-10-17",
    "Statement": {
        "Effect": "Allow",
        "Action": [
           "s3:PutObject",
           "s3:AbortMultipartUpload"
        ],
        "Resource": "arn:aws:s3:::YourS3BucketName/*"
    }
 }

```

Amazon Kinesis template json

```
{
     "Version": "2012-10-17",
     "Statement": {
         "Effect": "Allow",
         "Action": [
                    "kinesis:PutRecords",
                    "kinesis:ListShards"
                ],
         "Resource": "arn:aws:kinesis:::YourKinesisStreamName"
     }
 }

```

3. From the command line, create a role and attach the trust policy to the role. Replace `YourRoleName` with the name of your role and `file://trust-policy-file.json` with the name and location of the file in which you created your trust policy.

```
$ aws --profile personal iam create-role --role-name YourRoleNa --
```

Here's what the successful response to this command looks like:

```
{
    "Role": {
        "Path": "/",
        "RoleName": "YourRoleName",
        "RoleId": "ABCD1234ZHHQGKDRUMGFH",
        "Arn": "arn:aws:iam::AmazonResourceName:role/YourRol
        "CreateDate": "2021-03-19T23:14:27+00:00",
        "AssumeRolePolicyDocument": {
            "Version": "2012-10-17",
            "Statement": {
                "Condition": {
                    "StringEquals": {
                        "sts:ExternalId": "abc12345-defg-678
                    }
                },
```

```
                "Action": "sts:AssumeRole",
                "Principal": {
                    "AWS": "717331877981"
                },
                "Effect": "Allow",
                "Sid": "RoleForS3"
                }
            }
        }
    }

```

> **NOTE**
>
> Take note of the value in the `Arn` field. This is the ARN for the role, which you will need to create your logging endpoint.

4. Create the permission policy. Replace `YourPolicyName` with the name of your policy and `file://permission-policy-file.json` with the name and location of the file in which you created your trust policy.

```
$ aws --profile personal iam create-policy --policy-name YourPo
```

Here's what the successful response to this command looks like:

```
{
"Policy": {
    "PolicyName": "YourPolicyName",
    "PolicyId": "ABCDJH5Z123CTIKFWXYZ",
    "Arn": "arn:aws:iam::AmazonResourceName:policy/YourPolic
    "Path": "/",
    "DefaultVersionId": "v1",
    "AttachmentCount": 0,
    "PermissionsBoundaryUsageCount": 0,
    "IsAttachable": true,
    "CreateDate": "2021-03-19T23:17:42+00:00",
    "UpdateDate": "2021-03-19T23:17:42+00:00"
```

```
12        }
13    }
14
```

5. Attach the permissions policy to the role. Replace `YourRoleName` with the name of your role and the value after `--policy-arn` with the ARN of your permission policy.

```
$ aws --profile personal iam attach-role-policy --role-name You
```

6. Follow the instructions in Enabling Regional Tokens to ensure your AWS account is set up to allow tokens using regional STS endpoints.

Enabling Regional Tokens

Fastly uses the AWS Security Token Service API to request temporary credentials to write logs to AWS endpoints like S3 and Kinesis. Tokens can be requested from a single, global endpoint or from regional endpoints, though AWS recommends the use of Regional STS endpoints for reduced latency and improved redundancy.

Regardless of where your AWS S3 bucket or Kinesis stream is located, you must enable all of the Regional endpoints that Fastly uses to acquire tokens to provide the highest level of redundancy and token validity. For example, even though your S3 bucket may be located in `us-west-1`, Fastly may acquire the token to write to your bucket from a different region (e.g., `us-east-2`).

Follow the instructions in Activating and deactivating AWS STS in an AWS Region to activate all of the following regional endpoints that may be used by Fastly to acquire tokens.

- US East (N. Virginia) *Always active*: `https://sts.us-east-1.amazonaws.com`
- US East (Ohio): `https://sts.us-east-2.amazonaws.com`
- US West (N. California): `https://sts.us-west-1.amazonaws.com`
- US West (Oregon): `https://sts.us-west-2.amazonaws.com`

What's next

Use the IAM role you created to add Amazon S3 or Amazon Kinesis as a logging endpoint.

* * *

Custom log formats

/en/guides/custom-log-formats

Fastly provides two versions of custom log formats for use when you set up remote log streaming. All new logging endpoints use the version 2 custom log format by default. You can upgrade version 1 logging endpoints to the version 2 custom log format. You can also make version 2 look like version 1 for the sake of continuity. We've described the key advantages of the version 2 custom log format below.

Version 2 log format

This table details version 2 of Fastly's custom log formats. All variables should be prefixed by a percent sign (`%`), as indicated in the table.

Format String	Description
`%%`	The percent sign.
`%a`	The client IP address of the request. Equivalent to `req.http.Fastly-Client-IP`.
`%A`	The local IP address. Equivalent to `server-ip`.
`%B`	The size of response in bytes, excluding HTTP headers. Equivalent to `resp.body_bytes_written`.
`%b`	The size of response in bytes, excluding HTTP headers. In Common Log Format (CLF), that means a `"-"` rather than a `0` when no bytes are sent.
`%{Foobar}C`	The contents of cookie `Foobar` in the request sent to the server.
`%D`	The time taken to serve the request, in microseconds. Equivalent to `time.elapsed.usec`.

Format String	Description
`%{FOOBAR}e`	Not supported. Always returns `"-"`.
`%f`	The filename. Equivalent to `req.url` with any query string removed, because Varnish has no notion of a file being served.
`%h`	The remote IP address. Equivalent to `req.http.Fastly-Client-IP`.
`%H`	The request protocol. Equivalent to `req.proto`.
`%{Foobar}i`	The contents of `Foobar:` header lines in the request sent to the server.
`%I`	Bytes received, including request and headers. Cannot be zero Equivalent to `req.bytes_read`.
`%k`	The number of keepalive requests handled on this connection. Always returns `0`.
`%l`	Not supported. Always returns `"-"`.
`%m`	The request method. Equivalent to `req.request`.
`%{Foobar}n`	Not supported. Always returns `"-"`.
`%{Foobar}o`	The contents of `Foobar:` header lines in the reply.
`%O`	Bytes sent, including headers. Cannot be zero. Equivalent to `resp.bytes_written`.
`%p`	The canonical port of the server serving the request. Always returns `80`. Equivalent to `server.port`.
`%{format}p`	The canonical port of the server serving the request. Valid formats are `canonical`, `local`, or `remote`. Returns `80` for HTTP requests and `443` for HTTPS requests.
`%P`	Not supported. Always returns `"-"`.
`%{format}P`	Not supported. Always returns `"-"`.
`%q`	The query string (prepended with a `?` if a query string exists, otherwise an empty string). Equivalent to `req.url`.

Format String	Description
`%r`	The first line of the request.
`%R`	Not supported. Always returns `"-"`.
`%s`	The status. For requests that got internally redirected, this is the status of the *original* request. Use `%>s` for the final status. Equivalent to `resp.status`.
`%t`	The time the request was received, in Standard English format (e.g., `01/Jan/1970:00:00:00 -0700`). The last number indicates the time zone offset from GMT.
`%{format}t`	The time, in the form given by `format`, which should be in `strftime(3)` format (potentially localized). If the format starts with `begin:` (the default) the time is taken at the beginning of the request processing. If it starts with `end:` it is the time when the log entry gets written, close to the end of the request processing. In addition to the formats supported by `strftime(3)`, the following format tokens are supported: `sec` (number of seconds since the Epoch), `msec` (number of milliseconds since the Epoch), `usec` (number of microseconds since the Epoch), `msec_frac` (millisecond fraction), and `usec_frac` (microsecond fraction). Equivalent to `time.start`.
`%T`	The time taken to serve the request, in seconds. Equivalent to `time.elapsed.sec`.
`%u`	Not supported. Always returns `"-"`.
`%U`	The URL path requested, not including any query string. Equivalent to `req.url.path`.
`%v`	The domain name of the request. Equivalent to `req.http.host`.
`%V`	The same as `%v`. Equivalent to `req.http.host`.
`%{vcl}V`	The literal VCL to include without quoting. This can be used to write VCL variables to your logs (e.g., `%{client.geo.country_code}V` or `%{tls.client.cipher}V`). This %-directive is a Fastly extension and is not found in Apache.

Format String	Description
`%X`	The connection status when response is completed. Always set as `+` (connection may be kept alive after the response is sent).

Version 1 log format

This table details version 1 of Fastly's custom log formats. All variables should be prefixed by a percent sign (`%`), as indicated in the table.

Format String	Description
`%b`	The content size of the response, calculated using the `Content-Length` header rather than actually checking the length of the response (and may therefore be wrong).
`%h`	The remote IP address.
`%l`	The remote log name. Always returns the hardcoded value `"-"`.
`%r`	The HTTP verb and request path (e.g., `GET /index.html`). Unlike Apache and version 2 log formats, the protocol version is not included.
`%>s`	The status of the last request.
`%t`	The time the request was received, in Unix `ctime` format (e.g., `Thu, 01 Jan 1970 00:00:00 GMT`) rather than Apache's Standard English format (e.g., `01/Jan/1970:00:00:00 -0700`).
`%u`	Always returns `"-"`.

Upgrading endpoints to use version 2 log format

> **WARNING**
>
> Upgrading is a permanent change. Logging objects using version 2 formatting cannot be downgraded to version 1.


Follow these instructions to upgrade a logging endpoint to the version 2 custom log format:

1. Log in to the Fastly control panel.


2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.

3. Click **Edit configuration** and then select the option to clone the active version.


4. Click **Logging**.



5. Click the name of a logging endpoint you want to edit.



6. Click **Convert to Log Format Version 2**.



7. Select an output format:
    - **Use compatible output** is the recommended setting. This setting won't modify your timestamp format string, but your logs will be formatted differently. The new format will be compatible with Apache's log format.
    - **Maintain legacy output** uses the version 2 parser, but the generated log string will be the same. This means that any instances of `%t` need to be turned into `%{now}V`, any instances of `%r` need to be turned into `%{req.url}V`, and any instances of `%b` need to be turned into `%{resp.http.Content-Length}V`.
8. Click **Select**.
9. Click **Update** to upgrade the logging endpoint to the version 2 custom log format.
10. Click **Activate** to deploy your configuration changes.

Using the API to upgrade

To upgrade a logging endpoint using the Fastly API, either clone the active version of the service you need upgraded or choose a version of the service that is unlocked and not

active, then run the following command on that in development version:

```
$ curl -X PUT -H 'Fastly-Key: FASTLY_API_TOKEN' -H 'Content-Type: a
```

Keep in mind that the `format_version` field is a per-object field. Updating it on one logging object will *not* change it on any other objects.

For example, to update a Google Cloud Storage logging endpoint named "GCS Test," the curl command would look something like this:

```
$ curl -X PUT -H 'Fastly-Key: FASTLY_API_TOKEN' -H 'Content-Type: a
```

> **NOTE**
>
> The `log name` included a space that needed to be URL encoded (the space into `%20`).

Determining which logging version is being used

To determine which logging version your service currently uses, issue the following curl command:

```
$ curl -X GET -H 'Fastly-Key: FASTLY_API_TOKEN'  'https://api.fastly
```

The curl command will produce JSON output detailing the configuration of your service version. For example:


```
{
    "address": "logs.papertrailapp.com",
    "created_at": "2016-04-01T15:37:30+00:00",
    "deleted_at": null,
    "format": "time.start.msec time.to_first_byte time.elapsed r
    "format_version": "2",
    "hostname": "logs.papertrailapp.com",
```

```
    "name": "fastly",
    "port": "11111",
    "public_key": null,
    "response_condition": "LOG /",
    "service_id": "1a2b3c4d5e6f7g8h9j0k",
    "updated_at": "2016-04-01T19:47:47+00:00",
    "version": "123"
}
```

The `format_version` field displays either a `1` or a `2` as appropriate for the custom log format being used.

Advantages of using the version 2 custom log format

The key advantages of using the version 2 custom log format include the following:

- Log lines are generated in `vcl_log` instead of `vcl_deliver` to allow us to accurately set the various size variables because `vcl_log` is run after the object has been delivered to the browser.
- The `%t` time directive is compatible with Apache log format. In version 1, we used a non-standard time format.
- The `%r` "first line of request" directive is compatible with Apache log format. In version 1, we incorrectly left off the protocol.
- When using the `%b` directive, which represents the size of a response in bytes, excluding HTTP headers is more accurate. In version 1, we used the reported Content-Length from the origin, which could be inaccurate (especially with ESI).
- We've added all Apache logging directives that make sense. In version 1, we used a smaller subset.

Making version 2 logs look like version 1

The default logging format for version 1 is as follows:

```
%h %l %u %t %r %>s
```

Most of the directives in version 2 are exactly the same - only `%t` and `%r` are different. After you upgrade to version 2 log formats, you can recreate the appearance of version 1 logs using the new `%{...}V` directive, which allows you to specifically include VCL in logging directives:

```
%h %l %u %{now}V %{req.method}V %{req.url}V %>s
```

In addition, if you are using the `%b` directive in version 1, then you can use this directive instead:

```
%{resp.http.Content-Length}V
```

* * *



Encrypting logs



/en/guides/encrypting-logs

For supported logging endpoints, Fastly allows you to encrypt your log files before they are written to disk. The files are encrypted using OpenPGP (Pretty Good Privacy).



IMPORTANT

Be sure to take into account security, privacy, and compliance requirements when making configuration and endpoint decisions for the data you intend to include in streamed logs.

Generating a PGP key pair

To use this feature, you'll need to use a PGP implementation (such as GPG) to generate a public and private PGP key pair. Typically, this involves running the following command in a terminal application on your personal computer:

```
$ gpg --gen-key
```

Follow the instructions shown in your terminal application. Enter your email address and set a passphrase when prompted. Remember the values you enter.

> **WARNING**
>
> Keep your private key safe! If you lose it, your encrypted log files will be permanently unreadable.

Exporting the PGP public key

After you generate the PGP key pair, you'll need to export your public key. Typically, this involves running the following command in a terminal application on your personal computer:


```
$ gpg --armor --export <your email>
```

The output will be in PEM (Privacy-Enhanced Mail) format and will look similar to the following:

```
-----BEGIN PGP PUBLIC KEY BLOCK-----
mQGiBFciSsYRBAC9aHsraEzLmzfuQLx+BZmGTCOQFsPGpiPaEKrulRbrcBvtt3Bl
zajFP9iVzSm3+Zyqge/1AtHllSnPHTqG2EoBCsWtXL/JnZcPjx8c5r8G5IuBGrh8
snP3KTJ64zCS7PUvrWy5RWcJ6Rs+6wiJ7zPOtU5wMEPuMbflh/soy50zrwCg74XN
[...REDACTED...]
-----END PGP PUBLIC KEY BLOCK-----
```

Enabling log encryption

To enable PGP encryption for a logging endpoint that supports it, copy and paste your public PGP key into the **PGP public key** field in the Fastly control panel when creating or editing a supported logging endpoint.



Decrypting log files

To read an encrypted log file, you'll need to download and decrypt it. Typically, this involves running the following command in a terminal application on your personal computer:

```
$ gpg --decrypt <encrypted log file>
```

Enter your passphrase to decrypt the log file.

---

* * *

Setting up remote log streaming for Compute

/en/guides/setting-up-remote-log-streaming-for-compute

Logs provide an important resource for troubleshooting connectivity problems, pinpointing configuration areas that could use performance tuning, and identifying the causes of service

disruptions. We recommend setting up remote log streaming when you start using Fastly services.

Compute gives you multiple options for streaming logs. The quickest way to get started with logging is to use our log tailing feature, which lets you stream custom log messages from your Compute application to your local console. You can also configure Fastly's Real-Time Log Streaming feature to automatically save logs to a third-party service for storage and analysis. You can take advantage of these logging options separately or together.

> NOTE
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

> IMPORTANT
>
> Be sure to take into account security, privacy, and compliance requirements when making configuration and endpoint decisions for the data you intend to include in streamed logs.

How logs are streamed

Fastly uses several different log-server aggregation points and each will send logs files, none of which contain duplicate entries. These log files are created as soon as streaming starts and they're written to over the entire time period you specify (or the default). Once that time has passed, the files aren't touched any more and the logging process creates a new batch of files.

The number of log-server aggregation points may change over time in line with our capacity requirements. If you're sending logs to a storage endpoint and are concerned about the number of log files that will be created on your disk, consider choosing a logging endpoint that supports real-time ingestion, which will eliminate a need for pre-processing log files.

Configuring logging via log-tailing

The quickest way to try out logging with Compute is to use our log-tailing feature. Log tailing can be used to display output from `stdout` and `stderr` directly on your local console and doesn't require any third-party integrations or endpoints. This is useful for testing and debugging your code.

Testing and debugging on Compute has instructions on how to live-tail a service using one of our Compute starter kits.


Configuring logging via third-party endpoints

Another way to configure logging on Compute is to configure one or more third-party logging endpoints. Before setting up remote log streaming, keep the following in mind:

- Be sure to double-check the delivery formats required by your logging provider and what you're delivering to them. Some providers have strict formatting requirements for the formats they allow (e.g., JSON).
- If you configure multiple logging endpoints for your service, logs will be sent to all of the logging endpoints.

Follow these instructions to access the logging settings:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Logging**. If you've already added a logging endpoint, click **Create Endpoint**. The list of available logging endpoints appears.



5. Follow the instructions in one of our logging endpoint guides to complete the set up process and deploy your changes.

Once you've clicked Activate to deploy your changes, events will begin being logged immediately. The logs may take a few moments to appear on your log server.

Advanced logging configuration

Depending on the starter kit you're using, there may be advanced configuration capabilities to give you more precise control of your log data. For example, the `log_fastly` crate in Rust has an option to integrate log tailing with your third-party logging endpoint, define a default endpoint for different logging levels, and support multiple logging endpoints. Advanced configuration capabilities are also possible with JavaScript and GO.

An example using Rust

The following example demonstrates how to format log data as JSON to send to a third party endpoint. It is based on the default starter kit for Rust.

In this example, we have configured an endpoint named `my_endpoint` that expects a JSON object like:

```
{
   "client_ip": "127.0.0.1",
   "host": "firstly-coral-feather",
   "request_method": "GET",
   "timestamp": "2022-09-22 17:30:17.225185 UTC",
   "trace_id": "cffc6f9a6b0645ad89adc569c99e91aa",
   "url": "https://firstly-coral-feather/"
}
```

To format log data as JSON, we add `serde_json` as a dependency in the **Cargo.toml** file along with Chrono for timestamp data.

```
[dependencies]
fastly = "0.8.7"
log-fastly = "0.8.7"
log = "0.4.17"
chrono = "0.4"
serde_json = "1.0.85"
```

Then, we modify the `src/main.rs` file from the starter kit:

```
//! Compute logging demo
use fastly::http::{header, Method, StatusCode};
use fastly::{mime, Error, Request, Response};
use serde_json::json;
#[fastly::main]
fn main(req: Request) -> Result<Response, Error> {
   // Filter request methods...
   match req.get_method() {
      // Allow GET and HEAD requests.
      &Method::GET | &Method::HEAD => (),
      // Deny anything else.
      _ => {
            return Ok(Response::from_status(StatusCode::METHOD_N
```

```
                .with_header(header::ALLOW, "GET, HEAD")
                .with_body_text_plain("This method is not allowed
        }
    };
    // Pattern match on the path...
    match req.get_path() {
        // If request is to the `/` path...
        "/" => {
              // Initialize the logger with the one endpoint
              // Notice we are echoing to stdout, so we don't need
              log_fastly::Logger::builder()
                 .max_level(log::LevelFilter::Info)
                 .default_endpoint("my_endpoint")
                 .echo_stdout(true)
                 .init();
              // Get some request data to log
              let ts = chrono::Utc::now();
              let record = json!({
                 "timestamp": ts.format("%F %T%.6f %Z").to_string(
                 "trace_id": std::env::var("FASTLY_TRACE_ID").unwr
                 "client_ip": req.get_client_ip_addr().unwrap().to
                 "host": req.get_header_str("Host"),
                 "request_method": req.get_method_str(),
                 "url": req.get_url_str(),
              });
              // Send the logs
              // note we didn't specify a target so it goes to `my
              // We could have also specified the target log::info
              log::info!("{}", record.to_string());
              // Send a default synthetic response.
              Ok(Response::from_status(StatusCode::OK)
                 .with_content_type(mime::TEXT_HTML_UTF_8)
                 .with_body(include_str!("welcome-to-compute@edge.
        }
        // Catch all other requests and return a 404.
        _ => Ok(Response::from_status(StatusCode::NOT_FOUND)
              .with_body_text_plain("The page you requested could
    }
}


```

Once ready, build and deploy the service and tail the service to see the logging output in your developer console.

Troubleshooting common logging errors

Logging errors fall into two general categories: configuration errors and formatting errors.

Configuration errors may include things like incorrect bucket names or authentication information. Configuration errors generally show up in the details of an error message displayed in the web interface.



To resolve configuration errors, confirm that your bucket name and authentication keys are accurate and spelled correctly.

Formatting errors may include things like invalid JSON, a schema mismatch, or missing vendor-specific fields. These cause errors because some remote endpoints have specific formats for the ingested data, while others may be more flexible in what they allow.

If log messages are not showing up in your remote endpoint but are displayed in the log tail (assuming you have configured your logging endpoint for use with log tailing), check the format of the JSON in the log message. Verify that it is valid JSON and matches the format your provider expects.

Receiving logs

If an error in the Fastly web interface suggests that your logging configuration appears to be broken for the currently activated service version but you're still receiving some logs, not all of Fastly's log aggregators may be able to connect to your endpoint's server. It's likely the maximum number of concurrent connections has been reached. Try configuring your logging endpoint's server to allow a higher maximum number of inbound connections and then see if the error clears up after a couple of hours.

* * *

Setting up remote log streaming

/en/guides/setting-up-remote-log-streaming

Fastly's Real-Time Log Streaming feature allows you to automatically save logs to a third-party service for storage and analysis. Logs provide an important resource for troubleshooting connectivity problems, pinpointing configuration areas that could use performance tuning, and identifying the causes of service disruptions. We recommend setting up remote log streaming when you start using Fastly services.

NOTE

Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Before you begin

Before setting up remote log streaming, keep the following in mind:

- Be sure to double-check the delivery formats required by your logging provider and what you're delivering to them. Some providers have strict formatting requirements for the formats they allow (e.g., JSON).
- If you configure multiple logging endpoints for your service, logs will be sent to all of the logging endpoints.


IMPORTANT

Be sure to take into account security, privacy, and compliance requirements when making configuration and endpoint decisions for the data you intend to include in streamed logs.

Configuring logging endpoints

You can configure one or more logging endpoints for Fastly services. Follow these instructions to access the logging settings:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Logging**. The logging endpoints page appears. If you've already added a logging endpoint, click **Create Endpoint**.



5. Follow the instructions in one of our logging endpoint guides to complete the set up process and deploy your changes.

Once you've clicked Activate to deploy your changes, events will begin being logged immediately. The logs may take a few moments to appear on your log server.

How, when, and where logs are streamed

To control log streaming, Fastly provides two versions of custom log formats, each of which uses Apache-style logging directives. The logging format strings in each of these versions

are based on the Common Log Format (CLF).

Logs are streamed over TCP, not UDP, optionally using TLS for security with supported endpoints. Additionally, if you are using custom VCL be sure to include the `#FASTLY log` macro in your `vcl_log` handler.

By default, logs are placed in your root directory every hour using the file naming format `YYYY-mm-ddThh:mm:ss-<uid>`. You can change both the frequency and path of these files. Our guide on changing where log files are written provides more information.

If you've configured multiple logging endpoints for your service, the logs will be sent to all of the logging endpoints.

Fastly uses several different log-server aggregation points and each will send logs files, none of which contain duplicate entries. These log files are created as soon as streaming starts and they're written to over the entire time period you specify (or the default). Once that time has passed, the files aren't touched any more and the logging process creates a new batch of files.

The number of log-server aggregation points may change over time in line with our capacity requirements. If you're sending logs to a storage endpoint and are concerned about the number of log files that will be created on your disk, consider choosing a logging endpoint that supports real-time ingestion, which will eliminate a need for pre-processing log files.

Escaping characters in logs

Logs respond to VCL like any other object. For example, the following code can escape quotes from User-Agent your log stream:


```
log {"syslog serviceid endpointname :: "} {"""} cstr_escape(req.htt se
```

Preventing duplicate log entries when using custom VCL

If you use custom VCL commands for logging, you may notice duplicate entries in your logs. This happens because logs are being generated by both Fastly and the custom VCL logging commands. You can eliminate the duplicate entries by following these steps:

1. On the Logging endpoints page, click the name of the logging endpoint you want to edit.

2. From the **Placement** menu, select **None**.



3. Click **Update**.

4. Click **Activate** to deploy your configuration changes.

Fastly will stop generating log entries, and your logs will only contain entries generated by the custom VCL logging commands.

Troubleshooting common logging errors

The Fastly web interface displays errors with your logging configuration. You can also use the `logging_status` API endpoint to troubleshoot problems with your service's logging configuration:

```
$ curl -sg -H "Fastly-Key:$token" \
  "https://api.fastly.com/service/:SERVICE_ID/logging_status"
```

The output will indicate whether Fastly has detected an error. If `BrokenNow` is set to `false`, Fastly hasn't detected a problem with your logging configuration:

```
{"1234567890ABCDEF/my-service":{"LastErrorTime":null,"LastError":nu
```

If an error in the Fastly web interface suggests that your logging configuration appears to be broken for the currently activated service version but you're still receiving some logs, not all of Fastly's log aggregators may be able to connect to your endpoint's server. It's likely the maximum number of concurrent connections has been reached. Try configuring your logging endpoint's server to allow a higher maximum number of inbound connections and then see if the error clears up after a couple of hours.

* * *

Useful conditions for logging

/en/guides/useful-conditions-for-logging

In addition to the standard logging directives, the following conditions can be used for logging when you set up remote log streaming.

IMPORTANT

Be sure to take into account security, privacy, and compliance requirements when making configuration and endpoint decisions for the data you intend to include in streamed logs.

Logging errors only

You can log errors only if you want a general purpose log that catches everything and a more detailed log if there's an error:

```
fastly_info.state == "ERROR"
```

You can also log only 500 errors:

```
resp.status >= 500 && resp.status < 600`
```

Logging only specific URLs using a dictionary

Using a dictionary (e.g., `urls_to_log`), you can log specific URLs having issues:

```
table.lookup(urls_to_log, req.url.path) == "log"
```

If a URL becomes a problem, you can start logging it by using the API to add the URL's path to the dictionary as a key with the value "log".

Logging samples

If you have a high-volume service, you might want to log only a proportion of requests by using the `randombool` VCL function in a condition. The following example will log only one percent of all requests:

```
randombool(1,100)
```

You could combine that with a dictionary to change the percentage of requests logged without having to deploy a new version of your service. The following example uses a dictionary named `service_variables`:

```
randombool(std.atoi(table.lookup(service_variables, "logging_percen e"
```

In the example above, if the key `logging_percentage` doesn't exist, nothing will be logged.

Using `false` to construct a log string in custom VCL

To construct a log string in custom VCL, you can use the `false` condition. This condition makes sure nothing is sent to Fastly logging objects.

---

* * *

Useful log formats

/en/guides/useful-log-formats

Different systems have standardized on different logging formats over time. Fastly believes logging should be as customizable as possible, working with whichever infrastructure you already have in place. This guide details some of the more complicated examples and custom logging strings (e.g., JSON, Key/Value, CSV, and URL-encoded) you can use to implement the logging formats mentioned in the Apache logging module.

NOTE

Fastly provides two versions of custom log formats. The version 2 logging formats, used by default when you create a new logging endpoint, improve compatibility with Apache's logging directives.

IMPORTANT

Be sure to take into account security, privacy, and compliance requirements when making configuration and endpoint decisions for the data you intend to include in streamed logs.

TIP

You can log any Varnish variable or Fastly's extensions to VCL. Consider reading our guide to useful variables to log.

Common Log Format (CLF)

```
%h %l %u %t "%r" %>s %b
```

This is the default for many of our logging providers.

Common Log Format with Virtual Host

```
%v %h %l %u %t "%r" %>s %b
```

NCSA extended/combined log format

```
%h %l %u %t "%r" %>s %b "%{Referer}i" "%{User-agent}i"
```

Referer log format

```
%{Referer}i -> %U
```

Agent (Browser) log format

```
%{User-agent}i
```

Custom Tags to Loggly or RFC 5424 to another provider

You'll have to create a regular Syslog logging object pointing at your RFC 5424 compatible endpoint. For example, to send custom tags to Loggly, create a new Syslog object and set `hostname` to `logs-01.loggly.com`, `port` to `6514`, `use_tls` to `true`, and the `message format` field to `blank`. You should also make sure the `token` field is blank. Then, in the `format` field, you would put the following:

```
<134>1 %{%Y-%m-%dT%TZ}t %{server.datacenter}V <log name> - - [<token <P
```

The various fields you need to replace are:

- *log name* - this can be whatever you want but we recommend using the same name as you've used for the logging object in Fastly.
- *token* - the private token for your RFC5424 endpoint (if sending to Loggly this is your Customer Token).
- *PEN* - this is a Private Enterprise Number. For example the Loggly PEN (Private Enterprise Number) is 41058. If you want to send to another provider then you can look up their PEN on the IANA registry and use that.
- *tags* - these can be any key/value pairs you want. Two appear in the above example: `fastly` and `other-tag`. Valid tag values include all alpha-numeric characters, the dash (`-`), the period (`.`), and the underscore (`_`). Tag values with spaces aren't valid and will be dropped by many logging providers such as Loggly. Additional information about tags, their restrictions, and details about how Loggly parses tags, can be found in the Loggly documentation but is useful information for sending data to all RFC 5424 compatible endpoints.
- *regular format string* - this is regular Fastly logging directives, put whatever you want here (for example: the Common Log Format mentioned above).

Structured data

The examples below demonstrate different representations of the same variables and variable types:

Name	VCL Value	Type	Description
Protocol	`req.protocol`	string	The HTTP protocol version.
Epoch Seconds	`time.start.sec`	number	The time at the start of the request in seconds.
Start Time	`begin:%Y-%m-%dT%H:%M:%S%z`	time	The time at the start of the request in ISO 8601. format
User Agent	`req.http.User-Agent`	escaped string	The User-Agent request header.
Is IPv6	`req.is_ipv6`	boolean	Whether the request was made over IPv6 or not.
ID	`deadbeef`	literal string	A generic ID.
Some String	`dwayne "the rock" johnson`	escaped literal string	A string with quotation marks in it.
Version	`1.1`	literal number	A generic version number.

JSON

This example JSON may need to be adjusted for your specific logging endpoint. Be sure to check your logging endpoint provider's documentation for the exact format needed.

```
{
  "protocol" : "%H",
  "epoch_seconds" : %{time.start.sec}V,
  "time_start" : "%{begin:%Y-%m-%dT%H:%M:%S%z}t",
  "user_agent" : "%{User-Agent}i",
  "is_ipv6" : %{if(req.is_ipv6, "true", "false")}V,
  "some_string":"%{json.escape(\{"dwayne "the rock" johnson"\})}
  "id" : "deadbeef",
  "version" : 1.1
}
```

```
10
```

CSV

```
%H, %{time.start.sec}V, %{begin:%Y-%m-%dT%H:%M:%S%z}t, %{regsub(req tp
```

Key/Value

```
protocol:%H, epoch_seconds:%{time.start.sec}V, time_start:%{begin:%' m-
```

URL Encoded

```
protocol=%H&epoch_seconds=%{time.start.sec}V&time_start=%{begin:%Y-' %d
```

---

* * *

Useful variables to log

/en/guides/useful-variables-to-log

In addition to the standard logging directives, the following request and response variables can be used for logging when you set up remote log streaming. You can also log any Varnish variable. Consider taking advantage of some of Fastly's extensions to VCL as well.

NOTE

All variables should be prefixed by a percent sign (`%`). For more information about string formatting, check out our guide to custom log formats.

IMPORTANT

Be sure to take into account security, privacy, and compliance requirements when making configuration and endpoint decisions for the data you intend to include in streamed logs.

Time-related logging variables

These are the time-related variables that can be used for logging.

Variable	Description
`%{begin:%Y-%m-%dT%H:%M:%S%z}t`	The time of the start of the request in ISO 8601 format.
`%{end:%Y-%m-%dT%H:%M:%S%z}t`	The time of the end of the request in ISO 8601 format.
`%{time.elapsed.usec}V`	How long the request took in microseconds.
`%{time.start.sec}V`	When the request started in Epoch seconds.

Connection-related logging variables

These are the connection-related variables that can be used for logging.

Variable	Description
`%{if(req.is_ipv6, "true", "false")}V`	Whether the request was over IPv6 or not.
`%{if(req.is_ssl, "true", "false")}V`	Whether the request was over HTTPS or not.
`%{cstr_escape(tls.client.protocol)}V`	Which version of TLS was used by the client.
`%{cstr_escape(tls.client.servername)}V`	Which SNI server name the client sent.
`%{cstr_escape(tls.client.cipher)}V`	Which cipher the TLS request used.

Variable	Description
`%{cstr_escape(tls.client.ciphers_sha)}V`	Which cipher the TLS request used.
`%{cstr_escape(tls.client.tlsexts_sha)}V`	A SHA of the TLS extension identifiers sent from the client as part of the TLS handshake, represented in Base64.
`%{if(fastly_info.is_h2, "true", "false")}V`	Whether or not this was an HTTP/2 request.
`%{if(fastly_info.h2.is_push, "true", "false")}V`	Whether or not this was an HTTP/2 Push response.
`%{fastly_info.h2.stream_id}V`	What the HTTP/2 Stream ID was.

Request- and response-related logging variables

These are the request- and response-related variables that can be used for logging.

Variable	Description
`%{Fastly-Orig-Host}i`	The original Host requested if a Host header override is present.
`%{Host}i`	The current Host request header (because it could have been modified to send to the origin).
`%{Referer}i`	The Referer request header. Specifically, which URL linked to this page.
`%{User-Agent}i`	The User-Agent request header. Specifically, which browser requested this page.
`%{Accept}i`	The Accept request header. Specifically, the types of content the client can accept.
`%{Accept-Language}i`	The Accept-Language request header. Specifically, the human languages the client can respond with.

Variable	Description
`%{Accept-Encoding}i`	The Accept-Encoding request header. Specifically, the content encoding the client is able to understand.
`%{Accept-Charset}i`	The Accept-Charset request header. Specifically, the character set encodings the client accepts.
`%{Connection}i`	The Connection request header. Specifically, whether or not the client can do keep-alive connections.
`%{DNT}i`	The DNT request header. Specifically, whether or not the client is sending a "Do Not Track" header.
`%{Forwarded}i`	The Forwarded request header. Specifically, the originating IP address of a request if this request is proxied.
`%{Via}i`	The Via request header. Specifically, the intermediate protocols and recipients between the user agent and the server on proxied requests.
`%{X-Requested-With}i`	The X-Requested-With request header. Generally used to identify Ajax requests that will send the value XMLHttpRequest.
`%{X-Requested-For}i`	The X-Requested-For request header. Specifically, the originating IP address of a request if this request is proxied.
`%{X-ATT-DeviceId}i`	The X-ATT-DeviceId request header. Specifically, the make, mode, or firmware of AT&T devices.
`%{Content-Type}o`	The Content-Type response header. Specifically, the MIME type of the content.
`%{TSV}o`	The TSV response header. Specifically, the Tracking Status Value suggested for sending in response to a DNT request.

Cache-related logging variables

These are the cache-related variables that can be used for logging.

Variable	Description
`%{If-Modified-Since}i`	The If-Modified-Since request header. Specifically, the server will send back the requested resource, with a 200 status, only if it has been last modified after the given date.
`%{If-None-Match}i`	The If-None-Match request header. Specifically, the server will send back the requested resource, with a 200 status, only if it doesn't have an ETag matching the given ones.
`%{Cache-Control}o`	The Cache-Control response header. Specifically, whether or not all caching mechanisms from server to client may cache this object in seconds.
`%{Age}o`	The Age response header. Specifically, the age the object has been in a proxy cache in seconds.
`%{Expires}o`	The Expires response header. Specifically, the date and time after which the response is considered stale in "HTTP-date" format as defined by RFC 7231.
`%{Last-Modified}o`	The Last-Modified response header. Specifically, the last modified date for the requested object in "HTTP-date" format as defined by RFC 7231. Used in conjunction with the If-Modified-Since request header.
`%{ETag}o`	The ETag response header. Specifically, an identifier for a specific version of a resource. Used in conjunction with the If-None-Match Request header.
`%{obj.hits}V`	The number of hits this object has (cache specific).
`%{obj.lastuse}V`	The last time this object was used (cache specific).
`"cache_status":"%{fastly_info.state}V"`	(Fastly-specific) State of the request, with optional suffixes describing special cases.

Geographic logging variables

These are the geographic variables that can be used for logging.

Variable	Description
`%{server.datacenter}V`	Which Fastly data center this request hit.
`%{client.geo.city}V`	Which city Fastly thinks the request originated from.
`%{client.geo.city.ascii}V`	An alias of `client.geo.city`.
`%{client.geo.city.utf8}V`	The city or town name associated with the IP address, encoded using the UTF-8 character encoding.
`%{client.geo.country_code}V`	Which country Fastly thinks the request originated from.
`%{client.geo.continent_code}V`	Which continent Fastly thinks the request originated from.
`%{client.geo.region}V`	Which region Fastly thinks the request originated from.

Size-related logging variables

These are the size-related variables that can be used for logging.

Variable	Description
`%{req.header_bytes_read}V`	The size of the request headers.
`%{req.body_bytes_read}V`	The size of the request body.
`%{resp.header_bytes_written}V`	The size of the response headers.
`%{resp.body_bytes_written}V`	The size of the response body.

Socket-related logging variables

These are the socket-related variables that can be used for logging.

Variable	Description
`%{client.socket.cwnd}V`	The client socket congestion window.
`%{client.socket.nexthop}V`	The IP address of the next gateway.
`%{client.socket.tcpi_rcv_mss}V`	The client socket max segment size for receiving.
`%{client.socket.tcpi_snd_mss}V`	The client socket max segment size for sending.
`%{client.socket.tcpi_rtt}V`	The client socket smoothed round-trip time in microseconds.
`%{client.socket.tcpi_rttvar}V`	The client socket round-trip time variance in microseconds.
`%{client.socket.tcpi_rcv_rtt}V`	The client socket receiver-side estimation of round-trip time in microseconds.
`%{client.socket.tcpi_rcv_space}V`	The current buffer space available for receiving data.
`%{client.socket.tcpi_last_data_sent}V`	The time since last data sent on client socket in microseconds.
`%{client.socket.tcpi_total_retrans}V`	The total number of packet retransmissions on the client socket.
`%{client.socket.tcpi_delta_retrans}V`	The change in number of packet retransmissions on the client socket.
`%{client.socket.ploss}V`	The client socket packet loss.

* * *

Category: Logging endpoints

These articles describe Fastly's support for protocols that allow you to stream logs to a variety of locations, including third-party services, for storage and analysis.



Log streaming: Amazon Kinesis Data Streams



/en/guides/log-streaming-amazon-kinesis-data-streams

Fastly's Real-Time Log Streaming feature can send log files to Amazon Kinesis Data Streams. Amazon Kinesis Data Streams (KDS) is a real-time data streaming service that can continuously capture data from a variety of sources.



NOTE

Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

How Amazon Kinesis Data Streams work with Fastly log streaming

Amazon KDS sends data records to a *stream*. Each stream comprises one or more shards. A shard represents a fixed amount of processing capacity and the total processing capacity of a stream is determined by the number of shards. The number of shards may be increased or decreased over the lifetime of a stream. This is important because the Fastly Kinesis logging endpoint monitors the number of shards and attempts to uniformly distribute the log data records across the available shards. When the number of shards for a stream changes, the Fastly Kinesis logging endpoint automatically adjusts in response. The goal is to make the best use of the throughput capability of the stream while minimizing the configuration overhead required for our customers.

If the log volume exceeds the throughput capacity of the stream, Amazon KDS will return errors to our system that indicate that the stream is being throttled and that may prevent some logs from being delivered. AWS CloudWatch provides a metric for Kinesis Data Streams, `WriteProvisionedThroughputExceeded`, that can be used to monitor this so that adjustments to the stream capacity can be made as necessary.



TIP

For more information about working with Amazon KDS and understanding the capacity limits, refer to the Kinesis Developer Guide.

Prerequisites

Before adding Amazon KDS as a logging endpoint for Fastly services, we recommend creating Identity and Access Management (IAM) credentials in your AWS account specifically for Fastly. Our recommended way for doing this is by creating an AWS IAM role, which lets you grant temporary credentials. For more information, see Creating an AWS IAM Role for Fastly Logging. Alternatively, create an IAM user and grant the user `kinesis:PutRecords` and `kinesis:ListShards` permissions for the logging stream. For more information, see Amazon's guidance on understanding and getting your AWS credentials.

Adding Amazon Kinesis as a logging endpoint

After you've registered for an AWS account and created an IAM user in Amazon Kinesis, follow these instructions to add Amazon KDS as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the Amazon Kinesis Data Streams area, click **Create endpoint**.
3. Fill out the **Create an Amazon Kinesis Data Streams endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
    - In the **Access method** field, select either **User Credentials** or **IAM Role**.
    - If you select **User Credentials**, enter the access key and secret key associated with the IAM user you created in your AWS account specifically for Fastly. Check out Amazon's documentation on security credentials for more information.

> **NOTE**
>
> Password management software may mistakenly treat the **Secret Key** field as a password field because of the way your web browser works. As such, that software may try to auto-fill this field with your Fastly account password. If this happens to you, the AWS integration with Fastly services won't work and you will need to enter **Secret Key** manually instead.

- If you select **IAM Role**, enter the Amazon Resource Name (ARN) for the IAM role granting Fastly access to KDS. For more information, check out Creating an AWS IAM Role for Fastly Logging.
- In the **Stream name** field, enter the name of the Kinesis stream to which log data will be sent.
- From the **Region** menu, select the region to stream logs to. This must match the region where you created your Kinesis stream.

4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

Example format

The following is an example format string for sending data to Amazon KDS. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.sta
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Ori
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(res
  "response_body_size": %{resp.body_bytes_written}V,
```

```
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0, '
}

```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.
2. In the Amazon Kinesis Data Streams area, click **Create endpoint**.
3. Fill out the **Create an Amazon Kinesis Data Streams endpoint** fields as follows:
    - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
    - In the **Access method** field, select either **User Credentials** or **IAM Role**.
    - If you select **User Credentials**, enter the access key and secret key associated with the IAM user you created in your AWS account specifically for Fastly. Check out Amazon's documentation on security credentials for more information.

> **NOTE**
>
> Password management software may mistakenly treat the **Secret Key** field as a password field because of the way your web browser works. As such, that software may try to auto-fill this field with your Fastly account password. If this happens to you, the AWS integration with Fastly services won't work and you will need to enter **Secret Key** manually instead.

    - If you select **IAM Role**, enter the Amazon Resource Name (ARN) for the IAM role granting Fastly access to KDS. For more information, check out Creating an AWS IAM Role for Fastly Logging.
    - In the **Stream name** field, enter the name of the Kinesis stream to which log data will be sent.
    - From the **Region** menu, select the region to stream logs to. This must match the region where you created your Kinesis stream.

4. Click **Create** to create the new logging endpoint.

5. Click **Activate** to deploy your configuration changes.

---

* * *

	Log streaming: Amazon S3
	/en/guides/log-streaming-amazon-s3

Fastly's Real-Time Log Streaming feature can send log files to Amazon Simple Storage Service (Amazon S3). Amazon S3 is a static file storage service used by developers and IT teams. You can also use the instructions in this guide to configure log streaming to another S3-compatible service.

> NOTE
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

Before adding Amazon S3 as a logging endpoint for Fastly services, we recommend creating Identity and Access Management (IAM) credentials in your AWS account specifically for Fastly. Our recommended way for doing this is by creating an AWS IAM role, which lets you grant temporary credentials. For more information, see Creating an AWS IAM Role for Fastly Logging. Alternatively, create an IAM user and grant the user `s3:PutObject` and `s3:AbortMultipartUpload` permissions for the logging stream. For more information, see Amazon's guidance on understanding and getting your AWS credentials.

Adding Amazon S3 as a logging endpoint

After you've registered for an Amazon S3 account and created an IAM user in Amazon S3, follow these instructions to add Amazon S3 as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.

2. In the Amazon Web Services S3 area, click **Create endpoint**.

3. Fill out the **Create an Amazon S3 endpoint** fields as follows:

    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
    - *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.
    - In the **Bucket name** field, enter the name of the Amazon S3 bucket in which to store the logs.
    - *(Optional)* In the **Domain** field, enter the domain of the Amazon S3 endpoint. If your Amazon S3 bucket was not created in the US Standard region, you must set the domain to match the appropriate endpoint URL. Use the table in the S3 section of the Regions and Endpoints Amazon S3 documentation page. To use an S3-compatible storage system (such as DreamHost's DreamObjects), set the domain to match the domain name for that service (for example, in the case of DreamObjects, the domain name would be `objects.dreamhost.com`).
    - In the **Access method** field, select either **User Credentials** or **IAM Role**.
    - If you select **User Credentials**, enter the access key and secret key associated with the IAM user you created in your AWS account specifically for Fastly. Check out Amazon's documentation on security credentials for more information.

> **NOTE**
>
> Password management software may mistakenly treat the **Secret Key** field as a password field because of the way your web browser works. As such, that software may try to auto-fill this field with your Fastly account password. If this happens to you, the AWS integration with Fastly services won't work and you will need to enter **Secret Key** manually instead.

- If you select **IAM Role**, enter the Amazon Resource Name (ARN) for the IAM role granting Fastly access to S3. For more information, see Creating an AWS IAM Role for Fastly Logging.

- *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds. Use the **Period** setting in conjunction with a known average log rate to approximate S3 log file objects of a preferred, uncompressed size. Size may fluctuate depending on actual log volume.

4. Click **Advanced options** and fill out the fields as follows:

    - *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be saved in the bucket's root path. Our guide on changing where log files are written provides more information.

    - *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.

    - In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.

    - *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.

    - From the **Redundancy level** menu, select a setting. This value defaults to **Standard**. Amazon's Using Reduced Redundancy Storage Guide provides more information on using reduced redundancy storage.

    - *(Optional)* From the **ACL** menu, select an access control header. See Amazon's Access Control List (ACL) Specific Request Headers for more information.

    - *(Optional)* **Server side encryption** area, select an encryption method to protect files that Fastly writes to your Amazon S3 bucket. Valid values are **None**, **AES-256**, and **AWS Key Management Service**. If you select **AWS Key Management Service**, you'll have to provide an AWS KMS Key ID. See

Amazon's guide on protecting data using server-side encryption for more information.

- *(Optional)* In the **Maximum bytes** field, enter the maximum file size in bytes. This value caps the file size and overrides any configured period if the size threshold is exceeded prior to the end of the period. If set to 0, no maximum is set and the file size will not be capped.

> **NOTE**
>
> The minimum file size is 1048576 bytes (1 MiB).

5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

> **NOTE**
>
> Although Fastly continuously streams logs into Amazon S3, the Amazon S3 website and API do not make files available for access until after their upload is complete.

Example format

The following is an example format string for sending data to Amazon S3. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.sta
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Ori
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(res
  "response_body_size": %{resp.body_bytes_written}V,
```

```
15    "fastly_server": "%{json.escape(server.identity)}V",
16    "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0, "
17  }
18
```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.
2. In the Amazon Web Services S3 area, click **Create endpoint**.
3. Fill out the **Create an Amazon S3 endpoint** fields as follows:
    - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
    - *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.
    - In the **Bucket name** field, enter the name of the Amazon S3 bucket in which to store the logs.
    - *(Optional)* In the **Domain** field, enter the domain of the Amazon S3 endpoint. If your Amazon S3 bucket was not created in the US Standard region, you must set the domain to match the appropriate endpoint URL. Use the table in the S3 section of the Regions and Endpoints Amazon S3 documentation page. To use an S3-compatible storage system (such as DreamHost's DreamObjects), set the domain to match the domain name for that service (for example, in the case of DreamObjects, the domain name would be `objects.dreamhost.com`).
    - In the **Access method** field, select either **User Credentials** or **IAM Role**.
    - If you select **User Credentials**, enter the access key and secret key associated with the IAM user you created in your AWS account specifically for Fastly. Check out Amazon's documentation on security credentials for more information.

NOTE

> Password management software may mistakenly treat the **Secret Key** field as a password field because of the way your web browser works. As such, that software may try to auto-fill this field with your Fastly account password. If this happens to you, the AWS integration with Fastly services won't work and you will need to enter **Secret Key** manually instead.

- If you select **IAM Role**, enter the Amazon Resource Name (ARN) for the IAM role granting Fastly access to S3. For more information, check out Creating an AWS IAM Role for Fastly Logging.
- *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds. Use the **Period** setting in conjunction with a known average log rate to approximate S3 log file objects of a preferred, uncompressed size. Size may fluctuate depending on actual log volume.

4. Click **Advanced options** and fill out the fields as follows:

   - *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be saved in the bucket's root path. Our guide on changing where log files are written provides more information.
   - *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.
   - In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
   - *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.
   - From the **Redundancy level** menu, select a setting. This value defaults to **Standard**. Amazon's Using Reduced Redundancy Storage Guide provides more information on using reduced redundancy storage.

- *(Optional)* From the **ACL** menu, select an access control header. See Amazon's Access Control List (ACL) Specific Request Headers for more information.
- *(Optional)* In the **Server side encryption** area, select an encryption method to protect files that Fastly writes to your Amazon S3 bucket. Valid values are **None**, **AES-256**, and **AWS Key Management Service**. If you select **AWS Key Management Service**, you'll have to provide an AWS KMS Key ID. See Amazon's guide on protecting data using server-side encryption for more information.
- *(Optional)* In the **Maximum bytes** field, enter the maximum file size in bytes. This value caps the file size and overrides any configured period if the size threshold is exceeded prior to the end of the period. If set to 0, no maximum is set and the file size will not be capped.

> NOTE
>
> The minimum file size is 1048576 bytes (1 MiB).

5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

> NOTE
>
> Although Fastly continuously streams logs into Amazon S3, the Amazon S3 website and API do not make files available for access until after their upload is complete.

Recommended log format

Log messages can take on any format you choose as long as they can be processed from Amazon S3.

---

* * *

Log streaming: Microsoft Azure Blob Storage

/en/guides/log-streaming-azure-blob-storage

Fastly's Real-Time Log Streaming feature can send log files to Microsoft Azure Blob Storage (Blob Storage). Blob Storage is a static file storage service used to control arbitrarily large amounts of unstructured data and serve them to users over HTTP and HTTPS.

> **NOTE**
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

Before adding Blob Storage as a logging endpoint for Fastly services, create an Azure storage account in the Azure portal. For help creating the account, check out Microsoft's account creation documentation.

We recommend creating a Shared Access Signature (SAS) user specifically for Fastly. For more information, check out Microsoft's shared access signatures (SAS) documentation. Fastly supports the following types of shared access signatures:

- User delegation SAS
- Service SAS
- Account SAS

Here is an example of a SAS token that provides write permissions to a blob:

```
sv=2018-04-05&ss=b&st=2018-04-29T22%3A18%3A26Z&sr=b&se=2020-04-30T02%3A23%3A26Z&sp=w&sig=Z%2FRHIX5Xcg0Mq2rqI3OlWTjEg2tYkboXr1P9ZUXDtkk%3D
```

Refer to the Microsoft documentation above for details on the SAS token elements to use when configuring your SAS token.

Adding Blob Storage as a logging endpoint

After you've registered for an Azure account and created a SAS token, follow these instructions to add Blob Storage as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the Azure Blob Storage area, click **Create endpoint**.
3. Fill out the **Create a Microsoft Azure Blob Storage endpoint** fields as follows:

- In the **Name** field, enter a human-readable name for the endpoint.
- In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
- In the **Log format** field, enter a string formatted as a comma-separated value (CSV) to use for log formatting. See Ingesting data for Azure Data Explorer for more information.
- In the **Storage account name** field, enter the unique Azure namespace in which your data objects will be stored.
- In the **Container** field, enter the name of the Blob Storage container to store logs in. Check out Microsoft's Blob storage page for more information.
- In the **SAS token** field, enter the token associated with the container.

> TIP
>
> Ensure you update your token before it expires otherwise the logging functionality will not work.

- *(Optional)* In the **Maximum bytes** field, enter the maximum file size in bytes.
- *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds.
- *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.

4. Click **Advanced options** and fill out the fields as follows:

- *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be saved in the bucket's root path. Our guide on changing where log files are written provides more information.
- *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key

should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.

- In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
- *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.

5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

> **NOTE**
>
> Although Fastly continuously streams logs into Azure Blob Storage, the storage portal and API do not make files available for access until after their upload is complete.

Ingesting data for Azure Data Explorer

Azure Data Explorer is a data exploration service for log and telemetry data. To ingest your data correctly, Data Explorer requires your logs to be formatted as comma-separated values (CSVs). When creating your logging endpoint:

- Set the **Log format** to a CSV string (`%H,%{time.start.sec}V,%{regsub(req.http.User-Agent, \{"""\}, \{"""\})}V`).
- Specify **blank** when you **Select a log line format** in the **Advanced options**.

Our guide on changing log line formats provides more information.

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.
2. In the Azure Blob Storage area, click **Create endpoint**.
3. Fill out the **Create a Microsoft Azure Blob Storage endpoint** fields as follows:
   - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.

- In the **Storage account name** field, enter the unique Azure namespace in which your data objects will be stored.
- In the **Container** field, enter the name of the Blob Storage container to store logs in. See Microsoft's Blob storage page for more information.
- In the **SAS token** field, enter the token associated with the container.

> **TIP**
>
> Ensure you update your token before it expires otherwise the logging functionality will not work.

- *(Optional)* In the **Maximum bytes** field, enter the maximum file size in bytes.
- *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds.
- *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.

4. Click **Advanced options** and fill out the fields as follows:

- *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be saved in the bucket's root path. Our guide on changing where log files are written provides more information.
- *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.
- In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
- *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.

5. Click **Create** to create the new logging endpoint.

6. Click **Activate** to deploy your configuration changes.

> NOTE
>
> Although Fastly continuously streams logs into Azure Blob Storage, the storage portal and API do not make files available for access until after their upload is complete.

Recommended log format

Log messages can take on any format you choose as long as they can be processed from Azure Blob Storage.

Ingesting data for Azure Data Explorer

Azure Data Explorer is a data exploration service for log and telemetry data. To ingest your data correctly, Data Explorer requires your logs to be formatted as comma-separated values (CSVs). When creating your logging endpoint:

- Set the log format to a CSV string (`${time_start_sec},"${req_http_user_agent}","${log_message}"`). In this example, `${time_start_sec}`, `${req_http_user_agent}`, and `${log_message}` are placeholders for variables in your Compute service code.
- Specify **blank** when you **Select a log line format** in the **Advanced options**.

Our guide on changing log line formats provides more information.

---

* * *

Log streaming: Cloud Files

/en/guides/log-streaming-cloudfiles

Fastly's Real-Time Log Streaming feature can send log file to Cloud Files. Operated by Rackspace, Cloud Files is a file storage service used by developers and IT teams.

> NOTE

> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

If you don't already have a Rackspace Cloud account, you'll need to register for one. Follow the instructions on Rackspace's website.

Creating a Cloud Files user and container

Start by creating a Cloud Files user with restricted permissions via Rackspace's cloud control panel.

1. Log in to Rackspace's cloud control panel.
2. From the user account menu, select **User Management**.
3. Click **Create User** and fill in all appropriate details.
4. In the **Product Access** section, set **User Role** to **Custom**.
5. Review the **Product Access** list. For all items in the **Product** column, set **Role** to **No Access** except the **Files** item.
6. Set the **Files** item **Role** to **Admin**. This will allow you to create the files to store the logs in, but not access any other services.

Next, find the API key for your Cloud Files account. You'll use this later to authenticate using the Cloud Files API.

1. From the user account menu, select **Account Settings**.
2. Show the API key in the **Login details** and make a note of it.

Now that you've created the Cloud Files user and found the API key, you can set up a Cloud Files container.

1. From the **Storage** menu, select **Files**.
2. Click **Create Container**.
3. Assign the container a meaningful name like `Fastly logs - my service`.
4. Choose a region to keep the files in and make sure the container is private.

5. Click **Create Container**.

Adding a Cloud Files logging endpoint

Once you have created the Cloud Files user and container, follow these instructions to add Cloud Files as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the Rackspace Cloud Files area, click **Create endpoint**.
3. Fill out the **Create a Cloud Files endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
    - *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.
    - In the **Bucket name** field, enter the name of the Cloud Files container in which to store the logs.
    - In the **User** field, enter the username of the Cloud Files user you created above.
    - In the **Access key** field, enter the API key of your Cloud Files account.
    - *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds.
    - From the **Region** menu, select the region to stream logs to.
4. Click **Advanced options** and fill out the fields as follows:
    - *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be

saved in the bucket's root path. Our guide on changing where log files are written provides more information.

- *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.
- In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
- *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.

5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

Example format

The following is an example format string for sending data to Cloud Files. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.sta
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Ori
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(res
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0,
```

```
17  }
18
```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.

2. In the Rackspace Cloud Files area, click **Create endpoint**.

3. Fill out the **Create a Cloud Files endpoint** fields as follows:
    - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
    - *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.
    - In the **Bucket name** field, enter the name of the Cloud Files container in which to store the logs.
    - In the **User** field, enter the username of the Cloud Files user you created above.
    - In the **Access key** field, enter the API key of your Cloud Files account.
    - *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds.

4. Click **Advanced options** and fill out the fields as follows:
    - *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be saved in the bucket's root path. Our guide on changing where log files are written provides more information.
    - *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.

- In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
- From the **Region** menu, select the region to stream logs to.
- *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.

5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

---

* * *

Log streaming: Coralogix

/en/guides/log-streaming-coralogix

Fastly's Real-Time Log Streaming feature can send log files to Coralogix. Coralogix provides an analytics platform that allows you to detect abnormal behavior via dynamic alerts, ratio alerts, flow anomaly detection, and threat discovery.

NOTE

Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

If you don't already have a Coralogix account, you'll need to register for one by following the signup instructions on the Coralogix website. Once you've signed up, navigate to the **Send Your Logs** area in the **Settings** section of your Coralogix dashboard and make note of your unique private key. Coralogix uses this to associate data you send them with your account. You'll need it when you set up your endpoint with Fastly.

TIP

Consider reading Coralogix's documentation on integrating with Fastly.

Adding Coralogix as a logging endpoint

Follow these instructions to add Coralogix as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the HTTPS area, click **Create endpoint**.
3. Fill out the **Create an HTTPS endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, replace the placeholder log format and make the appropriate changes as shown in our log format and recommendations section below.
    - In the **URL** field, enter the Coralogix REST API Singles Endpoint for your Coralogix Domain. For example, you could use `https://ingress.coralogix.us/logs/v1/singles` for the `coralogix.us` domain.
    - In the **Maximum logs** field, leave the default value of `0`.
    - In the **Maximum bytes** field, enter `2000000`.
4. Click **Advanced options** and fill out the fields as follows:
    - In the **Content type** field, enter `application/json`.
    - In the **Custom header name** field, enter `Authorization`.
    - In the **Custom header value** field, enter `Bearer <your Coralogix private key>`.
    - From the **Method** controls, select **POST**.
    - From the **JSON log entry format** controls, select **Array of JSON**.
    - Leave the **Select a log line format** controls set to the defaults.
    - Leave the remaining fields blank.
5. Click **Create** to create the new logging endpoint.

6. Click **Activate** to deploy your configuration changes.

> **NOTE**
>
> For Coralogix, you do not need to configure anything to satisfy the HTTPS Proof of domain ownership requirement, and you can safely ignore any warning about it.

Log format and field setting recommendations

Use the following log format:

```
{
  "timestamp":%{time.start.msec}V,
  "applicationName":"fastly",
  "subsystemName":"%{req.service_id}V",
  "severity": 3,
  "json": {
    "time": {
        "start":"%{begin:%Y-%m-%dT%H:%M:%S%Z}t",
        "end":"%{end:%Y-%m-%dT%H:%M:%S%Z}t",
        "elapsed":%D
    },
    "cdn_server": {
        "ip_ipaddr":"%A",
        "code":"%{server.datacenter}V",
        "hostname":"%{server.hostname}V",
        "region_code":"%{server.region}V",
        "response_state":"%{fastly_info.state}V",
        "is_h2":%{if(fastly_info.is_h2, "true", "false")}V,
        "is_h2_push":%{if(fastly_info.h2.is_push, "true", "fa
        "h2_stream_id":"%{fastly_info.h2.stream_id}V"
    },
    "client": {
        "city_name":"%{client.geo.city.utf8}V",
        "country_code":"%{client.geo.country_code}V",
        "country_name":"%{client.geo.country_name}V",
        "continent_code":"%{client.geo.continent_code}V",
        "region":"%{client.geo.region}V",
        "ip_ipaddr":"%h",
        "name":"%{client.as.name}V",
```

```
        "number":"%{client.as.number}V",
        "connection_speed":"%{client.geo.conn_speed}V",
        "location_geopoint": {
            "lat":%{client.geo.latitude}V,
            "lon":%{client.geo.longitude}V
        }
    },
    "response": {
        "status":%>s,
        "content_type":"%{Content-Type}o",
        "age":"%{Age}o",
        "cache_control":"%{Cache-Control}o",
        "expires":"%{Expires}o",
        "last_modified":"%{Last-Modified}o",
        "tsv":"%{TSV}o",
        "header_size":%{resp.header_bytes_written}V,
        "body_size":%B
    },
    "request": {
        "host":"%{req.http.host}V",
        "is_ipv6":%{if(req.is_ipv6, "true", "false")}V,
        "backend":"%{req.backend}V",
        "service_id":"%{req.service_id}V",
        "url":"%{cstr_escape(req.url)}V",
        "url_ext":"%{req.url.ext}V",
        "header_size":%{req.header_bytes_read}V,
        "body_size":%{req.body_bytes_read}V,
        "method":"%m",
        "protocol":"%H",
        "referer":"%{Referer}i",
        "user_agent":"%{User-Agent}i",
        "accept_content":"%{Accept}i",
        "accept_language":"%{Accept-Language}i",
        "accept_encoding":"%{Accept-Encoding}i",
        "accept_charset":"%{Accept-Charset}i",
        "connection":"%{Connection}i",
        "dnt":"%{DNT}i",
        "forwarded":"%{Forwarded}i",
        "via":"%{Via}i",
        "cache_control":"%{Cache-Control}i",
```

```
        "x_requested_with":"%{X-Requested-With}i",
        "x_att_device_id":"%{X-ATT-Device-Id}i",
        "x_forwarded_for":"%{X-Forwarded-For}i"
    },
    "socket": {
        "cwnd":%{client.socket.cwnd}V,
        "pace":%{client.socket.pace}V,
        "nexthop":"%{client.socket.nexthop}V",
        "tcpi_rcv_mss":%{client.socket.tcpi_rcv_mss}V,
        "tcpi_snd_mss":%{client.socket.tcpi_snd_mss}V,
        "tcpi_rtt":%{client.socket.tcpi_rtt}V,
        "tcpi_rttvar":%{client.socket.tcpi_rttvar}V,
        "tcpi_rcv_rtt":%{client.socket.tcpi_rcv_rtt}V,
        "tcpi_rcv_space":%{client.socket.tcpi_rcv_space}V,
        "tcpi_last_data_sent":%{client.socket.tcpi_last_data_s
        "tcpi_total_retrans":%{client.socket.tcpi_total_retrar
        "tcpi_delta_retrans":%{client.socket.tcpi_delta_retrar
        "ploss":%{client.socket.ploss}V
    }
  }
}


```

The first five fields of the recommended format are required:

- `timestamp`: Leave the format of this field unchanged.
- `applicationName`: Enter the name of the application in this field.
- `subsystemName`: Enter the name of the subsystem in this field. This is used to separate components. We use `req.service_id` in the example, which isn't particularly human readable. Use whatever subsystem name makes sense that helps you identify the subsystem.
- `severity`: Specify the severity and apply it to all logs using the following choices: 1 (debug), 2 (verbose), 3 (info), 4 (warning), 5 (error), 6 (critical). This can be changed later using an extract rule as described below.
- `json (object)`: Add or remove fields as necessary. Static fields can be added. Nested JSON formats are supported including any fields described in the Fastly VCL reference.

Specifying a nested `response.status` field is a useful way to identify the status for servicing the request. Using the Coralogix parsing rules, you can set a JSON Extract rule to use the status code value from the log to populate the severity field in the Coralogix interface. Specifically, you can automatically map an HTTP status code to a severity value. For example, status code `2xx` will set the Coralogix severity as "**INFO**" and status code `4xx` will set Coralogix severity as "**ERROR**".

In the Coralogix web interface, it will look like this:



1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.

2. In the HTTPS area, click **Create endpoint**.

3. Fill out the **Create an HTTPS endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **URL** field, enter the Coralogix REST API Singles Endpoint for your Coralogix Domain. For example, you could use `https://ingress.coralogix.us/logs/v1/singles` for the `coralogix.us` domain.

- In the **Maximum logs** field, leave the default of `0`.
- In the **Maximum bytes** field, enter `2000000`.

4. Click **Advanced options** and fill out the fields as follows:
   - In the **Content type** field, enter `application/json`.
   - In the **Custom header name** field, enter `private_key`.
   - In the **Custom header value** field, enter your Coralogix private key.
   - From the **Method** controls, select **POST**.
   - From the **JSON log entry format** controls, select **Array of JSON**.
   - Leave the **Select a log line format** controls set to the defaults.
   - Leave the **TLS hostname**, **TLS CA certificate**, **TLS client certificate**, and **TLS client key** fields blank.
5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

> NOTE
>
> For Coralogix, you do not need to configure anything explicitly to satisfy the HTTPS Proof of domain ownership requirement, and you can safely ignore any warning about it.

Recommended log format

Data sent to Coralogix must be serialized in a way conforming to Coralogix's expectations. If your logs are not formatted properly, attempts at processing your logs by your Coralogix endpoint may fail. Here's an example format string for sending data to Coralogix:

```
{
    "timestamp": 1653088964764,
    "applicationName": "fastly",
    "subsystemName": "wasm",
    "severity": 3,
    "json": {
        "message": "Request happened",
```

```
        "response": {
          "status":200
        }
    }
}


```

You can follow the general JSON structure above regardless of the chosen language for your Compute service. The following fields are required:

- `timestamp`: The format of this field is in milliseconds.
- `applicationName`: Enter the name of the application.
- `subsystemName`: Enter the name of the subsystem. This field is used to separate components. Use whatever subsystem name makes sense that helps you identify the subsystem.
- `severity`: The severity of the log. You can specify the severity to all logs using the following choices: 1 (debug), 2 (verbose), 3 (info), 4 (warning), 5 (error), 6 (critical). This can be changed later using an extraction rule as described in the field below.
- `json (object)`: Used to specify additional log details as necessary. Nested JSON formats are supported.

  Specifying a nested `response.status` field is a useful way to identify the status for servicing the request. Using the Coralogix parsing rules, you can set a JSON Extract rule to use the status code value from the log to populate the severity field in the Coralogix interface. Specifically, you can automatically map an HTTP status code to a severity value. For example, status code `2xx` will set the Coralogix severity as "**INFO**" and status code `4xx` will set Coralogix severity as "**ERROR**".

  In the Coralogix web interface, it will look like this:



Configuring Coralogix dashboards and alerting

Coralogix provides tutorials for integrating their service with Fastly via dashboards and alerting. This includes examples of data dashboards created using Fastly data, including one for a general service overview, a visitor summary, and quality of service.

Their tutorials also describe how to set up user-defined alerts for situations like no logs being received from Fastly, outages at your origin, elevated error ratios and cache misses, unusual or suspicious requests of various types, as well as potential website defacement attempts.

---

* * *

	Log streaming: Datadog
🔗	/en/guides/log-streaming-datadog


Fastly's Real-Time Log Streaming feature can be configured to send logs in a format readable by Datadog. Datadog is a cloud-based monitoring and analytics solution that allows you to see inside applications within your stack and aggregate the results.

> **NOTE**
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

Before adding Datadog as a logging endpoint for Fastly services, you will need to:

- **Register for a Datadog account.** You can sign up for a Datadog account on their site. A free plan exists that has some restrictions or you can upgrade for more features. Where you register your Datadog setup, either in the United States (US), the European Union (EU), or Japan will affect which commands you use during logging endpoint setup at Fastly.
- **Get your Datadog API key from your settings page on Datadog.** In the Datadog interface, navigate to Integrations → APIs where you'll be able to create or retrieve an API key.



This example displays the key `decafbaddeadbeef`. Your API key will be different. Make a note of this key somewhere.

Adding Datadog as a logging endpoint

After you've created a Datadog account and noted your Datadog API key, follow the steps below to add Datadog as a logging endpoint for Fastly services.

1. Review the information in our guide to setting up remote log streaming.
2. In the Datadog area, click **Create endpoint**.
3. Fill out the **Create a Datadog endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, enter the data to send to Datadog. We've described the use of this format below with additional suggestions.
    - From the **Region** menu, select the region to stream logs to.
    - In the **API key** field, enter the API key of your Datadog account.
4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

Logs should begin appearing in your Datadog account a few seconds after you've created the endpoint and deployed your service changes. These logs can then be accessed via the Datadog Log Explorer on your Datadog account.

Using the JSON logging format

Data sent to Datadog must be serialized as a JSON object. Datadog automatically parses log files created as JSON, and is able to recognize several reserved fields, such as `service`, `host`, and `date`.

> **NOTE**
>
> The JSON in this example is formatted for ease of reading. For proper parsing, it must be added as a single line in the **Log format** field, removing all line breaks and indentation whitespace first.

For example, in the JSON below we've set `service` to the ID of the Fastly service that sent the log but you could also use a human-readable name or you could group all logs under a common name such as `fastly`.

```
{
  "ddsource": "fastly",
```

```
    "service": "%{req.service_id}V",
    "date": "%{begin:%Y-%m-%dT%H:%M:%S%z}t",
    "time_start": "%{begin:%Y-%m-%dT%H:%M:%S%Z}t",
    "time_end": "%{end:%Y-%m-%dT%H:%M:%S%Z}t",
    "http": {
      "request_time_ms": %{time.elapsed.msec}V,
      "method": "%m",
      "url": "%{json.escape(req.url)}V",
      "useragent": "%{json.escape(req.http.User-Agent)}V",
      "referer": "%{json.escape(req.http.referer)}V",
      "protocol": "%H",
      "request_x_forwarded_for": "%{X-Forwarded-For}i",
      "status_code": "%s"
    },
    "network": {
      "client": {
        "ip": "%h",
        "name": "%{client.as.name}V",
        "number": "%{client.as.number}V",
        "connection_speed": "%{client.geo.conn_speed}V"
      },
      "destination": {
        "ip": "%A"
      },
    "geoip": {
    "geo_city": "%{client.geo.city.utf8}V",
    "geo_country_code": "%{client.geo.country_code}V",
    "geo_continent_code": "%{client.geo.continent_code}V",
    "geo_region": "%{client.geo.region}V"
    },
    "bytes_written": %B,
    "bytes_read": %{req.body_bytes_read}V
    },
    "host":"%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Orig
    "origin_host": "%v",
    "is_ipv6": %{if(req.is_ipv6, "true", "false")}V,
    "is_tls": %{if(req.is_ssl, "true", "false")}V,
    "tls_client_protocol": "%{json.escape(tls.client.protocol)}V
    "tls_client_servername": "%{json.escape(tls.client.servernam
    "tls_client_cipher": "%{json.escape(tls.client.cipher)}V",
```

```
    "tls_client_cipher_sha": "%{json.escape(tls.client.ciphers_s
    "tls_client_tlsexts_sha": "%{json.escape(tls.client.tlsexts_
    "is_h2": %{if(fastly_info.is_h2, "true", "false")}V,
    "is_h2_push": %{if(fastly_info.h2.is_push, "true", "false")}
    "h2_stream_id": "%{fastly_info.h2.stream_id}V",
    "request_accept_content": "%{Accept}i",
    "request_accept_language": "%{Accept-Language}i",
    "request_accept_encoding": "%{Accept-Encoding}i",
    "request_accept_charset": "%{Accept-Charset}i",
    "request_connection": "%{Connection}i",
    "request_dnt": "%{DNT}i",
    "request_forwarded": "%{Forwarded}i",
    "request_via": "%{Via}i",
    "request_cache_control": "%{Cache-Control}i",
    "request_x_requested_with": "%{X-Requested-With}i",
    "request_x_att_device_id": "%{X-ATT-Device-Id}i",
    "content_type": "%{Content-Type}o",
    "is_cacheable": %{if(fastly_info.state~"^(HIT|MISS)$", "true
    "response_age": "%{Age}o",
    "response_cache_control": "%{Cache-Control}o",
    "response_expires": "%{Expires}o",
    "response_last_modified": "%{Last-Modified}o",
    "response_tsv": "%{TSV}o",
    "server_datacenter": "%{server.datacenter}V",
    "req_header_size": %{req.header_bytes_read}V,
    "resp_header_size": %{resp.header_bytes_written}V,
    "socket_cwnd": %{client.socket.cwnd}V,
    "socket_nexthop": "%{client.socket.nexthop}V",
    "socket_tcpi_rcv_mss": %{client.socket.tcpi_rcv_mss}V,
    "socket_tcpi_snd_mss": %{client.socket.tcpi_snd_mss}V,
    "socket_tcpi_rtt": %{client.socket.tcpi_rtt}V,
    "socket_tcpi_rttvar": %{client.socket.tcpi_rttvar}V,
    "socket_tcpi_rcv_rtt": %{client.socket.tcpi_rcv_rtt}V,
    "socket_tcpi_rcv_space": %{client.socket.tcpi_rcv_space}V,
    "socket_tcpi_last_data_sent": %{client.socket.tcpi_last_data
    "socket_tcpi_total_retrans": %{client.socket.tcpi_total_retr
    "socket_tcpi_delta_retrans": %{client.socket.tcpi_delta_retr
    "socket_ploss": %{client.socket.ploss}V
  }

```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.
2. In the Datadog area, click **Create endpoint**.
3. Fill out the **Create a Datadog endpoint** fields as follows:
   - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
   - From the **Region** menu, select the region to stream logs to.
   - In the **API key** field, enter the API key of your Datadog account.
4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

Recommended log format

Data sent to Datadog must be serialized in a way conforming to Datadog's expectations.

If your logs are not formatted properly, attempts at processing your logs by your Datadog endpoint may fail. Here's an example format string for sending data to Datadog:

```
{
  "ddsource": "fastly",
  "ddtags": "env:production,version:1.0",
  "hostname": "hostname",
  "message": "2019-11-19T14:37:58,995 INFO Hello World",
  "service": "service_id"
}
```

You can follow the general JSON structure above regardless of the chosen language for your Compute service and include the specific details inside designated fields, such as `message`. The `ddsource` field is required. Nested JSON objects are supported. Refer to the Datadog documentation for other available options for Datadog log messages. The emitted logs must be formatted as valid JSON.

Logs should begin appearing in your Datadog account a few seconds after you've created the endpoint and deployed your service changes. These logs can then be accessed via the Datadog Log Explorer on your Datadog account.

---

* * *

	Log streaming: DigitalOcean Spaces
	/en/guides/log-streaming-digitalocean-spaces

Fastly's Real-Time Log Streaming feature can send log files to DigitalOcean Spaces. DigitalOcean Spaces is an Amazon S3-compatible static file storage service used by developers and IT teams.

> NOTE
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

Before adding DigitalOcean Spaces as a logging endpoint for Fastly services, you'll need to create a DigitalOcean account if you don't already have one. Then you'll need to create a space with private access permissions on DigitalOcean's website, generate a secret key and an access key, and make a note of the endpoint.

Adding DigitalOcean Spaces as a logging endpoint

After you've created a DigitalOcean Space, follow these instructions to add DigitalOcean Spaces as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the Spaces by DigitalOcean area, click **Create endpoint**.
3. Fill out the **Create a DigitalOcean endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.

- In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
- In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
- *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.
- In the **Space name** field, enter the name of the DigitalOcean Space in which to store the logs.
- In the **Access key** field, enter the access key associated with the DigitalOcean Space. Refer to the DigitalOcean Spaces Authentication Guide for more information.
- In the **Secret key** field, enter the secret key associated with the DigitalOcean Space.
- *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds.

4. Click **Advanced options** and fill out the fields as follows:
   - *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be saved in the bucket's root path. Our guide on changing where log files are written provides more information.
   - In the **Domain** field, enter the region-specific endpoint for your domain. In most cases, this should be `nyc3.digitaloceanspaces.com`. If the DigitalOcean Space was not created in the `nyc3` region, refer to DigitalOcean's documentation to find the correct domain.
   - *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.

- In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
- *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.

5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

Example format

The following is an example format string for sending data to DigitalOcean. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.start)
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Orig-H
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V",
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(resp.r
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0, "tru
}
```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.

2. In the Spaces by DigitalOcean area, click **Create endpoint**.

3. Fill out the **Create a DigitalOcean endpoint** fields as follows:
    - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
    - *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.
    - In the **Space name** field, enter the name of the DigitalOcean Space in which to store the logs.
    - In the **Access key** field, enter the access key associated with the DigitalOcean Space. Check out the DigitalOcean Spaces Authentication Guide for more information.
    - In the **Secret key** field, enter the secret key associated with the DigitalOcean Space.
    - *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds.

4. Click **Advanced options** and fill out the fields as follows:
    - *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be saved in the bucket's root path. Our guide on changing where log files are written provides more information.
    - In the **Domain** field, enter the region-specific endpoint for your domain. In most cases, this should be `nyc3.digitaloceanspaces.com`. If the DigitalOcean Space was not created in the `nyc3` region, refer to DigitalOcean's documentation to find the correct domain.
    - *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.

- In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
- *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.

5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

---

* * *

Log streaming: Dynatrace

/en/guides/log-streaming-dynatrace

Fastly's Real-Time Log Streaming feature can send log files to Dynatrace. Dynatrace delivers end-to-end observability with artificial intelligence for IT operations (AIOps) and application security in one unified platform.

> **NOTE**
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

Before adding Dynatrace as a logging endpoint for Fastly services, you will need to have both a Dynatrace account and API access token.

Dynatrace Account. If you don't have an account, you can sign up for one on the Dynatrace website.

Dynatrace API access token. Follow these instructions to create one:

1. In the Dynatrace interface, go to **Access Tokens**.
2. Select **Generate new token**.

3. Enter a name for your token. Dynatrace doesn't enforce unique token names. You can create multiple tokens with the same name. Be sure to provide a meaningful name for each token you generate. Proper naming helps you to efficiently manage your tokens and delete them when they're no longer needed.
4. Select the scope of `logs.ingest`.
5. Choose **Generate access token**.
6. Copy the generated token to the clipboard and store the token in a password manager for future use.

Adding Dynatrace as a logging endpoint

> **NOTE**
>
> This logging endpoint is only available for Fastly's Deliver (VCL-based) services, not Compute services.

Follow these instructions to add Dynatrace as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the HTTPS area, click **Create endpoint** button.
3. Fill out the **Create an HTTPS endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, replace the placeholder log format and make the appropriate changes as shown in our log format and recommendations section below.
    - In the **URL** field, enter `https://<dynatrace-instance-id>.live.dynatrace.com/api/v2/logs/ingest`, replacing `<dynatrace-instance-id>` with the name of your Dynatrace instance. Refer to the Dynatrace documentation for additional information.
    - In the **Maximum logs** field, leave as `0` (the default).
    - In the **Maximum bytes** field, enter `0`.

4. Click the **Advanced options** link of the **Create an HTTPS endpoint** page. The Advanced options appear.

5. Fill out the **Advanced options** of the **Create an HTTPS endpoint** page as follows:
    - In the **Content type** field, enter `application/json`.
    - In the **Custom header name** field, enter `Authorization`.
    - In the **Custom header value** field, enter `Api-Token <Dynatrace API Access token>`, substituting the values for your Dynatrace token. Refer to the Dynatrace documentation for additional information.
    - From the **Method** controls, select **POST**.
    - From the **JSON log entry format** controls, select **Array of JSON** as the appropriate log entry format to use.
    - In the **Select a log line format** area, select **Blank** as the log line format for your log messages. Our guide on changing log line formats provides more information.
    - Leave the **Placement** controls set to the default.
    - In the **TLS hostname** field, optionally enter a hostname to verify the logging destination server's certificate. This should be one of the Subject Alternative Name (SAN) fields for the certificate. Common Names (CN) are not supported.
    - Leave **TLS CA certificate**, **TLS client certificate**, and **TLS client key** fields empty.

6. Click **Create** to create the new logging endpoint.

7. Click **Activate** to deploy your configuration changes.

Log format recommendations

Data sent to Dynatrace must be formatted as valid JSON that conforms to Dynatrace's expectations. Here's an example format string for sending data to Dynatrace. The fields used here are in accordance with the Dynatrace Semantic Dictionary.

The Fastly docs for format strings provide more information.

```
{
  "log.source":"fastly",
```

```
    "loglevel":"INFO",
    "status":"INFO",
    "event.type":"LOG",
    "dt.ingest.format":"dtapi/json",
    "timestamp":"%{begin:%s000}t",
    "fastly.service.id":"%{req.service_id}V",
    "fastly.service.version":"%{req.vcl.version}V",
    "fastly.service.products":"%{if(req.http.x-sigsci-agentrespo
    "fastly.server":"%{server.identity}V",
    "fastly.datacenter":"%{server.datacenter}V",
    "fastly.region":"%{server.region}V",
    "fastly.billing_region":"%{server.billing_region}V",
    "fastly.cache_status":"%{regsub(fastly_info.state, "^(HIT-(S
    "fastly.is_edge":%{if(fastly.ff.visits_this_service == 0, "t
    "fastly.waf.tags":%{if(req.http.x-sigsci-tags, "%22"+json.es
    "fastly.waf.agentresponse":%{if(req.http.x-sigsci-agentrespo
    "fastly.waf.decision_ms":%{if(req.http.x-sigsci-decision-ms,
    "browser.user_agent":"%{req.http.User-Agent}V",
    "browser.name":"%{client.browser.name}V",
    "browser.version":"%{client.browser.version}V",
    "client.ip":"%{req.http.Fastly-Client-IP}V",
    "client.port":%{client.port}V,
    "client.isp":"%{client.as.name}V",
    "cloud.availability_zone":"%{server.datacenter}V",
    "cloud.region":"%{server.region}V",
    "cloud.resource_id":"%{req.service_id}V",
    "cloud.provider":"fastly",
    "cloud.platform":"fastly_vcl",
    "host.name":"%{req.http.Fastly-Orig-Host}V",
    "host.ip":"%{server.ip}V",
    "http.request.method":"%{req.method}V",
    "http.request.body.size":%{req.body_bytes_read}V,
    "http.request.header.referer":"%{json.escape(req.http.Refere
    "http.request.header.accept_content":"%{json.escape(req.http
    "http.request.header.accept_language":"%{json.escape(req.htt
    "http.request.header.accept_charset":"%{json.escape(req.http
    "http.response.state":"%{json.escape(fastly_info.state)}V",
    "http.response.status_code":%{resp.status}V,
    "http.response.reason_phrase":%{if(resp.response, "%22"+jso
    "http.response.body.size":%{resp.body_bytes_written}V,
```

```
    "http.response.header.content_type":"%{resp.http.Content-Typ
    "network.type":"%{if(req.is_ipv6, "ipv6", "ipv4")}V",
    "network.protocol.name":"%{if(fastly_info.edge.is_tls, "http
    "network.protocol.version":"%{regsub(req.proto, "^HTTP\/", "
    "url.scheme":"%{if(fastly_info.edge.is_tls, "https", "http"
    "url.full":"%{json.escape(if(fastly_info.edge.is_tls, "https
    "url.path":"%{json.escape(req.url.path)}V",
    "url.query":"%{json.escape(req.url.qs)}V",
    "url.domain":"%{req.http.Fastly-Orig-Host}V",
    "url.port":%{client.port}V,
    "geo.country_name":"%{client.geo.country_name}V",
    "geo.city_name":"%{client.geo.city}V",
    "geo.continent.name":"%{client.geo.continent_code}V",
    "geo.region.name":"%{client.geo.region}V"
  }
```

Logs should begin appearing in your Dynatrace account a few seconds after you've created the endpoint and deployed your service changes. These logs can then be accessed using the Logs App or the Dynatrace Logs and events viewer.

---

* * *

Log streaming: Elasticsearch

/en/guides/log-streaming-elasticsearch

Fastly's Real-Time Log Streaming feature can send log files to Elasticsearch. Elasticsearch is a distributed, RESTful search and analytics engine.

> **NOTE**
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

Before adding Elasticsearch as a logging endpoint for Fastly services, ensure Elasticsearch is running on a remote server. You'll need to know the endpoint URL that includes a port to which logs should be sent (make sure it can receive traffic from Fastly) and also the name of the index to send logs to. For more information on setting up Elasticsearch, check out the Elasticsearch setup documentation.

This logging endpoint works with all actively supported versions of Elasticsearch as well as some versions that have already reached their end-of-life. We also work with OpenSearch server integration. Other distributions that are API-compatible with Elasticsearch may also work but have not been explicitly tested and are not guaranteed.

Required privileges

We send data using the Bulk API via the `index` action. When using basic authentication, ensure that the required index privileges to use the `index` action are granted to the user role.

We also require access to the root path API of the Elasticsearch server. This API returns metadata about the server, such as the version number, that allows our integration to make the best choice about which bulk data API to use for each customer's server. Access to this API allows us to properly work with the wide range of Elasticsearch versions used by our customers as well as other Elasticsearch-compatible distributions.

Adding Elasticsearch as a logging endpoint

Follow these instructions to add Elasticsearch as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the Elasticsearch area, click **Create endpoint**.
3. Fill out the **Create an Elasticsearch endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, enter the data to send to Elasticsearch. See the example format section for details.
    - In the **URL** field, enter the Elasticsearch endpoint URL that includes a port to which logs should be sent. The URL must be sent using HTTPS on a port that

can receive incoming TCP traffic from Fastly.

- In the **Index** field, enter the name of the Elasticsearch index to send logs to. The index must follow the Elasticsearch index format rules. We support strftime interpolated variables inside braces prefixed with a pound symbol. For example, `#{%F}` will interpolate as YYYY-MM-DD with today's date.
- *(Optional)* In the **Pipeline** field, enter the ID of the Elasticsearch ingest pipeline to apply pre-process transformations to before indexing (for example, `my_pipeline_id`).
- *(Optional)* In the **Maximum logs** field, enter the maximum number of logs to append to a batch, if non-zero.
- *(Optional)* In the **Maximum bytes** field, enter the maximum size of the log batch.
- *(Optional)* In the **BasicAuth user** field, enter your basic authentication username.
- *(Optional)* In the **BasicAuth password** field, enter your basic authentication password.
- In the **TLS hostname** field, optionally enter a hostname to verify the logging destination server's certificate. This should be one of the Subject Alternative Name (SAN) fields for the certificate. Common Names (CN) are not supported.
- *(Optional)* In the **TLS CA certificate** field, copy and paste the certification authority (CA) certificate used to verify that the origin server's certificate is valid. The certificate you upload must be in PEM format. Consider uploading the certificate if it's not signed by a well-known certification authority. This value is not required if your TLS certificate is signed by a well-known authority.
- *(Optional)* In the **TLS client certificate** field, copy and paste the TLS client certificate used to authenticate to the origin server. The TLS client certificate you upload must be in PEM format and must be accompanied by a client certificate. A TLS client certificate allows your server to authenticate that Fastly is performing the connection.
- *(Optional)* In the **TLS client key** field, copy and paste the TLS client key used to authenticate to the backend server. The TLS client key you upload must be in PEM format and must be accompanied by a TLS client certificate. A TLS client key allows your server to authenticate that Fastly is performing the connection.

4. Click **Create** to create the new logging endpoint.

5. Click **Activate** to deploy your configuration changes.

Example format

Data sent to Elasticsearch must be serialized as a JSON object. Here's an example format string for sending data to Elasticsearch:

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.start)
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Orig-H
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V",
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(resp.r
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0, "tru
}

```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.

2. In the Elasticsearch area, click **Create endpoint**.

3. Fill out the **Create an Elasticsearch endpoint** fields as follows:
   - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.

- In the **URL** field, enter the Elasticsearch endpoint URL that includes a port to which logs should be sent. The URL must be sent using HTTPS on a port that can receive incoming TCP traffic from Fastly.
- In the **Index** field, enter the name of the Elasticsearch index to send logs to. The index must follow the Elasticsearch index format rules. We support strftime interpolated variables inside braces prefixed with a pound symbol. For example, `#{%F}` will interpolate as YYYY-MM-DD with today's date.
- *(Optional)* In the **Pipeline** field, enter the ID of the Elasticsearch ingest pipeline to apply pre-process transformations to before indexing (for example, `my_pipeline_id`).
- *(Optional)* In the **Maximum logs** field, enter the maximum number of logs to append to a batch.
- *(Optional)* In the **Maximum bytes** field, enter the maximum size of the log batch.
- *(Optional)* In the **BasicAuth user** field, enter your basic authentication username.
- *(Optional)* In the **BasicAuth password** field, enter your basic authentication password.
- In the **TLS hostname** field, optionally enter a hostname to verify the logging destination server's certificate. This should be one of the Subject Alternative Name (SAN) fields for the certificate. Common Names (CN) are not supported.
- *(Optional)* In the **TLS CA certificate** field, copy and paste the certification authority (CA) certificate used to verify that the origin server's certificate is valid. The certificate you upload must be in PEM format. Consider uploading the certificate if it's not signed by a well-known certification authority. This value is not required if your TLS certificate is signed by a well-known authority.
- *(Optional)* In the **TLS client certificate** field, copy and paste the TLS client certificate used to authenticate to the origin server. The TLS client certificate you upload must be in PEM format and must be accompanied by a client certificate. A TLS client certificate allows your server to authenticate that Fastly is performing the connection.
- *(Optional)* In the **TLS client key** field, copy and paste the TLS client key used to authenticate to the backend server. The TLS client key you upload must be in PEM format and must be accompanied by a TLS client certificate. A TLS client

key allows your server to authenticate that Fastly is performing the connection.

4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

---

* * *

📄	**Log streaming: Fastly Object Storage**
🔗	/en/guides/log-streaming-fastly-object-storage

Fastly's Real-Time Log Streaming feature can send log files to Fastly Object Storage using Fastly's S3-compatible API connectivity option.

Prerequisites

Before adding Fastly Object Storage as a logging endpoint for Fastly services, you must create an Object Storage access key. You also need a bucket created in Object Storage to store logs to.

Adding Fastly Object Storage as a logging endpoint

After you've created an Access Key and a Bucket follow these instructions to add Fastly Object Storage as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the Amazon Web Services S3 area, click **Create endpoint**.
3. Fill out the **Create an Amazon S3 endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for

details.

- *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.
- In the **Bucket name** field, enter the name of the Object Storage bucket you want to store logs to.
- In the **Access method** area, select **User Credentials**.
- In the **Access key** field, enter the access key associated with the Fastly Object Storage account.
- In the **Secret key** field, enter the secret key associated with the Fastly Object Storage account.
- *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds.

4. Click **Advanced options** and fill out the following fields:
   - *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be saved in the bucket's root path. Our guide on changing where log files are written provides more information.
   - In the **Domain** field, enter a regional Object Storage endpoint, formatted as `<region>.object.fastlystorage.app` e.g., (`us-east.object.fastlystorage.app`).
   - *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.
   - In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
   - *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.

5. Click **Create** to create the new logging endpoint.

6. Click **Activate** to deploy your configuration changes.

> NOTE
>
> Although Fastly continuously streams logs into Object Storage, you must wait for file uploads to be completed before accessing logs via the S3-compatible API.

Example format

The following is an example format string for sending data to Fastly Object Storage. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.start)
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Orig-H
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V",
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(resp.r
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0, "tru
}

```

1. Review the information in our guide to setting up remote log streaming.

2. In the Amazon Web Services S3 area, click **Create endpoint**.

3. Fill out the **Create an Amazon S3 endpoint** fields as follows:
   - In the **Name** field, enter a human-readable name for the endpoint.

- In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
- In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
- *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.
- In the **Bucket name** field, enter the name of the Object Storage bucket you want to store logs to.
- In the **Access method** area, select **User Credentials**.
- In the **Access key** field, enter the access key associated with the Fastly Object Storage account.
- In the **Secret key** field, enter the secret key associated with the Fastly Object Storage account.
- *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds.

4. Click **Advanced options** and fill out the following fields:
   - *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be saved in the bucket's root path. Our guide on changing where log files are written provides more information.
   - In the **Domain** field, enter a regional Object Storage endpoint, formatted as `<region>.object.fastlystorage.app` e.g., (`us-east.object.fastlystorage.app`).
   - *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.

- In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
- *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.

5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

> **NOTE**
>
> Although Fastly continuously streams logs into its Object Storage, the API will not make files available for access until after their upload is complete.

Example format

The following is an example format string for sending data to Fastly Object Storage. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.start)
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Orig-H
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V",
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(resp.r
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0, "tru
}
```

* * *

Log streaming: FTP

/en/guides/log-streaming-ftp

Fastly's Real-Time Log Streaming feature can send log files to password-protected and anonymous FTP servers.

> NOTE
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Adding FTP as a logging endpoint

Follow these instructions to add FTP as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the FTP area, click **Create endpoint**.
3. Fill out the **Create a File Transfer Protocol (FTP) endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
    - *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.
    - In the **Address** field, enter the hostname or IP address of the FTP server. In the port field, enter the port number you're using for FTP (the default is `21`).

- *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be saved in the bucket's root path. Our guide on changing where log files are written provides more information.
- In the **User** field, enter the username used to authenticate to the FTP server. For anonymous access, use the username `anonymous`.
- In the **Password** field, enter the password used to authenticate to the FTP server. For anonymous access, use an email address as the password.
- *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.
- *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds.

4. Click **Advanced options** and fill out the fields as follows:
   - In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
   - *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.
5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

Example format

The following is an example format string for sending data to an FTP logging endpoint. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.sta
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
```

```
    "geo_city": "%{client.geo.city}V",
    "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Or
    "url": "%{json.escape(req.url)}V",
    "request_method": "%{json.escape(req.method)}V",
    "request_protocol": "%{json.escape(req.proto)}V",
    "request_referer": "%{json.escape(req.http.referer)}V",
    "request_user_agent": "%{json.escape(req.http.User-Agent)}V
    "response_state": "%{json.escape(fastly_info.state)}V",
    "response_status": %{resp.status}V,
    "response_reason": %{if(resp.response, "%22"+json.escape(res
    "response_body_size": %{resp.body_bytes_written}V,
    "fastly_server": "%{json.escape(server.identity)}V",
    "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0,
}

```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.

2. In the FTP area, click **Create endpoint**.

3. Fill out the **Create a File Transfer Protocol (FTP) endpoint** fields as follows:
    - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
    - *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.
    - In the **Address** field, enter the hostname or IP address of the FTP server. In the port field, enter the port number you're using for FTP (the default is `21`).
    - *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be saved in the bucket's root path. Our guide on changing where log files are written provides more information.
    - In the **User** field, enter the username used to authenticate to the FTP server. For anonymous access, use the username `anonymous`.

- In the **Password** field, enter the password used to authenticate to the FTP server. For anonymous access, use an email address as the password.
- *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.
- *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds.

4. Click **Advanced options** and fill out the fields as follows:
   - In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
   - *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.
5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

---

* * *

Log streaming: Google BigQuery

/en/guides/log-streaming-google-bigquery

Fastly's Real-Time Log Streaming feature can send log files to BigQuery, Google's managed enterprise data warehouse.

> **NOTE**
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites


Before adding BigQuery as a logging endpoint for Fastly services you will need to:

- Register for a Google Cloud Platform (GCP) account.
- Create a service account on Google's website.
- Use Google IAM service account impersonation or key-based access to configure the access method that Fastly uses to send logs.
- Enable the BigQuery API.
- Create a BigQuery dataset.
- Add a BigQuery table.

Creating a service account

Google Cloud Platform (GCP) uses service accounts for third-party application authentication and role-based access to Google Cloud resources. To create a new service account, follow the instructions in the Google Cloud documentation.

> **NOTE**
>
> When creating the service account for logging to BigQuery, the service account must be assigned the `Big Query Data Editor` role to write to the table you use for Fastly logging. You can assign the `Big Query Data Editor` role to the entire project using Google Console or apply the `roles/bigquery.dataEditor` to the project using Google Terraform - IAM Project.



Configure access for the service account

Fastly requires access to write logs to your BigQuery table. You can use either Google IAM service account impersonation or key-based access to allow Fastly to send logs to BigQuery.

Configuring Google IAM service account impersonation

If you elect to use Google IAM service account impersonation to avoid storing keys with Fastly, you'll need to specify a service account name and a project ID when adding GCS as

your logging endpoint. The service account ID comes before the `@` in the service account email and the project ID immediately after. For example, if your service account email is `my-name@projectid.iam.gserviceaccount.com`, the service account ID is `my-name` and the project ID is `projectid`. Our guide to creating an Google IAM role provides specific details on configuring this feature.

Configuring key-based access

If you elect to use key-based access, refer to Google's guide on generating a service account credential.

When configuring key-based access, you must select the JSON format. Upon saving the configuration, a JSON file will be downloaded to your computer, containing the credentials for the GCS service account you just created. Open the file with a text editor and make a note of the `private_key` and `client_email`.

Enabling the BigQuery API

To send your Fastly logs to your BigQuery table, you'll need to enable the BigQuery API in the Google Cloud Platform API Manager.

Creating the BigQuery dataset

After you've enabled the BigQuery API, follow these instructions to create a BigQuery dataset:

1. Open the BigQuery page in the Cloud Console.
2. In the **Explorer** panel, select the project where you want to create the dataset.
3. In the details panel, click **Create dataset**.
4. In the **Dataset ID** field, enter a name for the dataset (e.g., `fastly_bigquery`).
5. Click **Create dataset**.

Adding a BigQuery table

After you've created the BigQuery dataset, you'll need to add a BigQuery table. There are four ways of creating the schema for the table:


- Edit the schema using the BigQuery web interface.
- Edit the schema using the text field in the BigQuery web interface.

- Use an existing table.
- Set the table to automatically detect the schema.

> **NOTE**
>
> Setting the table to automatically detect the schema may give unpredictable results.

Follow these instructions to add a BigQuery table:

1. Open the BigQuery page in the Cloud Console.
2. In the Explorer panel, expand your project and select the BigQuery dataset you created previously.
3. In the **Source** section, select **Empty Table** from the **Create table from:** menu.



4. In the **Table name** field, enter a name for the table (e.g., `logs`).

5. In the **Schema** section of the BigQuery website, use the interface to add fields and complete the schema. Check out the example schema section for details.

6. Click **Create Table**.

Adding BigQuery as a logging endpoint

Follow these instructions to add BigQuery as a logging endpoint. As part of configuration, you can elect to configure Google IAM role-based service account impersonation to avoid storing secrets. Read our guide on creating a Google IAM role for more information on this feature.

1. Review the information in our guide to setting up remote log streaming.

2. In the Google BigQuery area, click **Create endpoint**.

3. Fill out the **Create a BigQuery endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, enter the data to send to BigQuery. Check out the example format section for details.
    - In the **Access Method** area, select how Fastly will access Google resources for purposes of log delivery. Select either **User Credentials** or **IAM Role**.
    - If you selected **User Credentials**, fill out the following fields:
        - In the **Email** field, enter the `client_email` address associated with the BigQuery service account.
        - In the **Secret key** field, enter the value of the `private_key` associated with your BigQuery service account.
        - In the **Project ID** field, enter the ID of your Google Cloud Platform project.
        - In the **Dataset** field, enter the name of your BigQuery dataset.
        - In the **Table** field, enter the name of your BigQuery table.
        - *(Optional)* In the **Template** field, enter an `strftime` compatible string to use as the template suffix for your table.

- If you selected **IAM Role**, fill out the following fields:
  - In the **Service Account Name** field, enter the name of the service account email address you selected when configuring Google IAM service account impersonation.
  - In the **Project ID** field, enter the ID of your Google Cloud Platform project.
  - In the **Dataset** field, enter the name of your BigQuery dataset.
  - In the **Table** field, enter the name of your BigQuery table.
  - *(Optional)* In the **Template** field, enter an `strftime` compatible string to use as the template suffix for your table.

4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

Example format

Data sent to BigQuery must be serialized as a JSON object, and every field in the JSON object must map to a string in your table's schema. The JSON can have nested data in it (e.g., the value of a key in your object can be another object). Here's an example format string for sending data to BigQuery:

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S"\}, time.start
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Or
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(res
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0,
```

```
}

```

Example schema

The BigQuery schema for the example format shown above would look something like this:

```
timestamp:TIMESTAMP,client_ip:STRING,geo_country:STRING,geo_city:
```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.
2. In the Google BigQuery area, click **Create endpoint**.
3. Fill out the **Create a BigQuery endpoint** fields as follows:
    - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
    - In the **Access Method** area, select how Fastly will access Google resources for purposes of log delivery. Select either **User Credentials** or **IAM Role**.
    - If you selected **User Credentials**, fill out the following fields:
        - In the **Email** field, enter the `client_email` address associated with the BigQuery service account.
        - In the **Secret key** field, enter the value of the `private_key` associated with your BigQuery service account.
        - In the **Project ID** field, enter the ID of your Google Cloud Platform project.
        - In the **Dataset** field, enter the name of your BigQuery dataset.
        - In the **Table** field, enter the name of your BigQuery table.
        - *(Optional)* In the **Template** field, enter an `strftime` compatible string to use as the template suffix for your table.

- If you selected **IAM Role**, fill out the following fields:
  - In the **Service Account Name** field, enter the name of the service account email address you selected when configuring Google IAM service account impersonation.
  - In the **Project ID** field, enter the ID of your Google Cloud Platform project.
  - In the **Dataset** field, enter the name of your BigQuery dataset.
  - In the **Table** field, enter the name of your BigQuery table.
  - *(Optional)* In the **Template** field, enter an `strftime` compatible string to use as the template suffix for your table.

4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

Recommended log format

Data sent to BigQuery must be serialized as a JSON object, and every field in the JSON object must map to a field in your table's schema. The JSON can have nested data in it (e.g., the value for a key in your object can be another object). Here's an example format string for sending data to BigQuery:

```
{
  "client_ip": "127.0.0.1",
  "timestamp": "2022-05-17 15:09:24.037547 UTC",
  "geo_country": "USA",
  "geo_city": "boston",
  "host": "curiously-selected-polecat.edgecompute.app",
  "url": "https://curiously-selected-polecat.edgecompute.app/
  "request_method": "GET",
  "request_protocol": "https",
  "request_referer": "",
  "request_user_agent": "Mozilla/5.0 (Macintosh; Intel Mac OS
  "response_status": "200",
  "response_reason": "OK",
  "response_body_size": "1234",
  "fastly_server": "IAD"

```

```
}
```

Example schema

The BigQuery schema for the example format shown above would look like this:

```
client_ip:STRING,timestamp:TIMESTAMP,geo_country:STRING,geo_city:
```

---

* * *

Log streaming: Google Cloud Pub/Sub

/en/guides/log-streaming-google-cloud-pubsub

Fastly's Real-Time Log Streaming feature can send log files to Cloud Pub/Sub, Google's global messaging and event data ingestion product.

> **NOTE**
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

Before adding Cloud Pub/Sub as a logging endpoint for Fastly services, you will need to register for a Google Cloud Platform (GCP) account and then:


- Create a service account on Google's website.
- Navigate to the Pub/Sub section of the Google Cloud console. Follow the prompts to enable the API.
- Create a Pub/Sub topic.

- Use Google IAM service account impersonation or key-based access to configure the access method that Fastly uses to send logs.

Creating a service account

Google Cloud Platform (GCP) uses service accounts for third-party application authentication and role-based access to Google Cloud resources. To create a new service account, follow the instructions in the Google Cloud documentation.

> **NOTE**
>
> When creating the service account for logging to Google Pub/Sub, the service account must be assigned the `Pub/Sub Publisher` role to publish to the topic you created for Fastly logging.



Configure access for the service account

Fastly requires access to write logs to your Pub/Sub topic. You can use either role-based, service account impersonation, or key-based access to allow Fastly to send logs to Google Pub/Sub.

Configuring Google IAM service account impersonation

If you elect to use Google IAM service account impersonation to avoid storing keys with Fastly, you'll need to specify a service account name and a project ID when adding GCS as your logging endpoint. The service account ID comes before the `@` in the service account

email and the project ID immediately after. For example, if your service account email is `my-name@projectid.iam.gserviceaccount.com`, the service account ID is `my-name` and the project ID is `projectid`. Our guide to creating an Google IAM role provides specific details on configuring this feature.

Configuring key-based access

If you elect to use key-based access, refer to Google's guide on generating a service account credential.

When configuring key-based access, you must select the JSON format. Upon saving the configuration, a JSON file will be downloaded to your computer, containing the credentials for the GCS service account you just created. Open the file with a text editor and make a note of the `private_key` and `client_email`.

> **NOTE**
>
> Read more about Cloud Pub/Sub in Google's documentation.

Adding Cloud Pub/Sub as a logging endpoint

Follow these instructions to add Cloud Pub/Sub as a logging endpoint. As part of configuration, you can elect to configure Google IAM role-based service account impersonation to avoid storing secrets. Read our guide on creating a Google IAM role for more information on this feature.

1. Review the information in our guide to setting up remote log streaming.
2. In the Google Cloud Pub/Sub area, click **Create endpoint**.
3. Fill out the **Create a Google Cloud Pub/Sub endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, enter the data to send to Google Cloud Pub/Sub. See the example format section for details.
    - In the **Project ID** field, enter the ID of your Google Cloud Platform project.

- In the **Email** field, enter the email address of the service account configured for your Pub/Sub topic.
- In the **Topic** field, enter the Pub/Sub topic to which logs should be sent.
- In the **Access Method** area, select how Fastly will access Google resources for purposes of log delivery. Valid values are **User Credentials** and **IAM Role**.
- If you selected **User Credentials**, fill out the following fields:
  - In the **Email** field, enter the email address of the service account configured for your Pub/Sub topic.
  - In the **Secret Key** field, enter the exact value of the `private_key` associated with the service account configured for your Pub/Sub topic.
- If you selected **IAM Role**, enter fill out following field:
  - In the **Service Account Name** field, enter the name of the service account email address you selected when configuring Google IAM service account impersonation.

4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

Example format

Data sent to Cloud Pub/Sub must be serialized as a JSON object, and every field in the JSON object must map to a string in your table's schema. The JSON can have nested data in it (e.g., the value of a key in your object can be another object). Here's an example format string for sending data:

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.sta
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Ori
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V
  "response_state": "%{json.escape(fastly_info.state)}V",
```

```
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(res
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0,
}
```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.
2. In the Google Cloud Pub/Sub area, click **Create endpoint**.
3. Fill out the **Create a Google Cloud Pub/Sub endpoint** fields as follows:
    - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
    - In the **Project ID** field, enter the ID of your Google Cloud Platform project.
    - In the **Topic** field, enter the Pub/Sub topic to which logs should be sent.
    - In the **Access Method** area, select how Fastly will access Google resources for purposes of log delivery. Valid values are **User Credentials** and **IAM Role**.
    - If you selected **User Credentials**, fill out the following fields:
        - In the **Email** field, enter the email address of the service account configured for your Pub/Sub topic.
        - In the **Secret Key** field, enter the exact value of the private key associated with the service account configured for your Pub/Sub topic.
    - If you selected **IAM Role**, fill out the following field:
        - In the **Service Account Name** field, enter the name of the service account email address you selected when configuring Google IAM service account impersonation.
4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

* * *

Log streaming: Google Cloud Storage

/en/guides/log-streaming-google-cloud-storage

Fastly's Real-Time Log Streaming feature can send log files to Google Cloud Storage (GCS). GCS is an online file storage service used for storing and accessing data on Google's infrastructure. One advantage of using GCS is that you can use Google BigQuery to analyze the log files.

NOTE

Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

Before adding GCS as a logging endpoint for Fastly services, you will need to:

- Register for a GCS account.
- Create a bucket and service account on Google's website.
- Use Google IAM service account impersonation or key-based access to configure the access method that Fastly uses to send logs.
- Enable the Google Cloud Storage JSON API.

Creating a GCS bucket


You can create a new GCS bucket to hold the logs, or you can use an existing bucket. Be sure to note the name of the bucket as you will need it later. To learn how to create a GCS bucket, refer to Google's guide on creating a bucket.

Creating a service account

Google Cloud Platform (GCP) uses service accounts for third-party application authentication and role-based access to Google Cloud resources. To create a new service

account, follow the instructions in the Google Cloud documentation.

> **NOTE**
>
> When creating the service account for logging to GCS, the service account must be assigned the `Storage Object Creator` role for the bucket you created above. Refer to the Storage Object Roles for details.



Configure access for the service account

Fastly requires access to write logs to your GCS bucket. You can use either Google IAM service account impersonation or key-based access to allow Fastly to send logs to your GCS bucket

Configuring Google IAM service account impersonation

If you elect to use Google IAM service account impersonation to avoid storing keys with Fastly, you'll need to specify a service account name and a project ID when adding GCS as your logging endpoint. The service account ID comes before the `@` in the service account email and the project ID immediately after. For example, if your service account email is `my-name@projectid.iam.gserviceaccount.com`, the service account ID is `my-name` and the project ID is `projectid`. Our guide to creating an Google IAM role provides specific details on configuring this feature.

Configuring key-based access

If you elect to use key-based access, refer to Google's guide on generating a service account credential.

When configuring key-based access, you must select the JSON format. Upon saving the configuration, a JSON file will be downloaded to your computer, containing the credentials for the GCS service account you just created. Open the file with a text editor and make a note of the `private_key` and `client_email`.

Enabling the Google Cloud Storage JSON API

To ensure the Fastly logs are sent to your GCS bucket, you need to enable the Google Cloud Storage JSON API. For more information, refer to Google's instructions for activating the API.

Adding GCS as a logging endpoint

Follow these instructions to add GCS as a logging endpoint. As part of configuration, you can elect to configure Google IAM role-based service account impersonation to avoid storing secrets. Read our guide on creating a Google IAM role for more information on this feature.

1. Review the information in our guide to setting up remote log streaming.
2. In the Google Cloud Services area, click **Create endpoint**.
3. Fill out the **Create a Google Cloud Storage (GCS) endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.

- In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
- In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
- *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.
- In the **Email** field, enter the `client_email` address listed in the JSON file associated with the service account you created on Google's website.
- In the **Bucket name** field, enter the name of the GCS bucket in which to store the logs.
- In the **Access Method** area, select how Fastly will access Google resources for purposes of log delivery. Valid values are **User Credentials** and **IAM Role**.
- If you selected **User Credentials**, fill out the following fields:
  - In the **Email** field, enter the `client_email` address listed in the JSON file associated with the service account you created on Google's website.
  - In the **Secret key** field, enter the `private_key` value listed in the JSON file associated with the service account you created on Google's website. We strip out the JSON newline escape characters for you so don't worry about removing them.
- If you selected **IAM Role**, fill out the following field:
  - In the **Service Account Name** field, enter the service account ID which was created for you from the service account name you entered when configuring Google IAM service account impersonation. The service account ID comes before the `@` in the service account email. For example, if your service account email is `my-name@projectid.iam.gserviceaccount.com`, the service account ID is `my-name`.
  - In the **Project ID** field, enter the ID of your Google Cloud Platform project.
- *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key

should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.

- *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds.

4. Click **Advanced options** and fill out the fields as follows:
   - *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be saved in the bucket's root path. Our guide on changing where log files are written provides more information.
   - In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
   - *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.
5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

Example format

The following is an example format string for sending data to GCS. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.sta
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Or
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V
  "response_state": "%{json.escape(fastly_info.state)}V",
```

```
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(res
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0,
}
```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.

2. In the Google Cloud Services area, click **Create endpoint**.

3. Fill out the **Create a Google Cloud Storage (GCS) endpoint** fields as follows:
    - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
    - *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.
    - In the **Bucket name** field, enter the name of the GCS bucket in which to store the logs.
    - In the **Access Method** area, select how Fastly will access Google resources for purposes of log delivery. Valid values are **User Credentials** and **IAM Role**.
    - If you selected **User Credentials**, fill out the following fields:
        - In the **Email** field, enter the `client_email` address listed in the JSON file associated with the service account you created on Google's website.
        - In the **Secret key** field, enter the `private_key` value listed in the JSON file associated with the service account you created on Google's website. We strip out the JSON newline escape characters for you so don't worry about removing them.
    - If you selected **IAM Role**, fill out the following field:
        - In the **Service Account Name** field, enter the service account ID which was created for you from the service account name you entered when configuring Google IAM service account impersonation. The service

account ID comes before the `@` in the service account email. For example, if your service account email is `my-name@projectid.iam.gserviceaccount.com`, the service account ID is `my-name`.

- In the **Project ID** field, enter the ID of your Google Cloud Platform project.

- *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.

- *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds.

4. Click **Advanced options** and fill out the fields as follows:
   - *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be saved in the bucket's root path. Our guide on changing where log files are written provides more information.
   - In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
   - *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.
5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

Recommended log format

Log messages can take on any format you choose as long as they can be processed from GCS.

---

* * *

Log streaming: Grafana Cloud Logs

/en/guides/log-streaming-grafana-cloud-logs

Fastly's Real-Time Log Streaming feature can send log files to Grafana Cloud Logs, a scalable, multi-tenant log aggregation system by Grafana Labs.

> **NOTE**
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

Before adding Grafana Cloud Logs as a logging endpoint for Fastly services, you will need to:

- Register for a Grafana Cloud Account.
- Create a Grafana Cloud Loki instance in your Grafana stack. Check out the Grafana Cloud Logs documentation for more details.
- Create a Grafana Access Policy with `logs:write` access scoped to your Loki instance.

Grafana Streams

Grafana Cloud Logs to sends data to Grafana Cloud via a stream. Grafana uses labels, formatted as a JSON string (e.g., `{ "app": "my app", "env": "staging" }`), to define a particular log stream.

> **IMPORTANT**
>
> Dynamic labels are not supported with this logging endpoint. Be sure to follow Grafana's current best practices for using labels.

Adding Grafana Cloud Logs as a logging endpoint

Follow these instructions to add Grafana Cloud Logs as a logging endpoint.

1. Review the information in our guide to setting up remote log streaming.
2. In the Grafana Cloud Logs area, click **Create endpoint**.
3. Fill out the **Create a Grafana Cloud Logs endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, enter the data to send to Grafana Cloud. Check out the example format section for details.
    - In the **User ID** area, enter your Grafana User ID.
    - In the **URL** area, enter the URL of your Grafana stack (e.g., `https://myhost.grafana.net`).
    - In the **Access Policy Token** area, enter the Grafana Access Policy token with `logs:write` scope you created.
    - In the **Stream Labels** area, enter the JSON string used to identify this stream in Grafana (e.g., `{ "app": "my app", "env": "staging" }`).
4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

Example format

Data sent to Grafana Cloud Logs can be sent as JSON or plain text. Here's an example of JSON message data sent to Grafana Cloud Logs:

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S"\}, time.start
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Or
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
```

```
    "request_user_agent": "%{json.escape(req.http.User-Agent)}V"
    "response_state": "%{json.escape(fastly_info.state)}V",
    "response_status": %{resp.status}V,
    "response_reason": %{if(resp.response, "%22"+json.escape(res
    "response_body_size": %{resp.body_bytes_written}V,
    "fastly_server": "%{json.escape(server.identity)}V",
    "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0, "
}
```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.
2. In the Grafana Cloud Logs area, click **Create endpoint**.
3. Fill out the **Create a Grafana Cloud Logs endpoint** fields as follows:
   - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
   - In the **User ID** area, enter your Grafana User ID.
   - In the **URL** area, enter the URL of your Grafana stack (e.g., `https://myhost.grafana.net`).
   - In the **Access Policy Token** area, enter the Grafana Access Policy token with `logs:write` scope you created.
   - In the **Stream Labels** area, enter the JSON string used to identify this stream in Grafana (e.g., `{ "app": "my app", "env": "staging" }`).
4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

---

* * *

Log streaming: Honeycomb

/en/guides/log-streaming-honeycomb

Fastly's Real-Time Log Streaming feature can send logs in JSON format to Honeycomb. Honeycomb is a tool that allows developers to explore the operations of complex systems, microservices, and databases.

> **NOTE**
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

Before adding Honeycomb as a logging endpoint for Fastly services, you'll need to perform the following steps:

- Sign up for a Honeycomb account if you don't already have one.
- Obtain the Write Key for your team on the Honeycomb Account page.
- Choose a Dataset name. If you plan to collect data from multiple environments (like production, development, staging), Honeycomb recommends creating a Dataset for each environment and naming your Datasets accordingly (e.g., `prod.queries`, `dev.queries`, and `staging.queries`). If a Dataset doesn't exist, Honeycomb will create one automatically.

Adding Honeycomb as a logging endpoint

1. Review the information in our guide to setting up remote log streaming.
2. In the Honeycomb area, click **Create endpoint**.
3. Fill out the **Create a Honeycomb endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, enter the data to send to Honeycomb. See the example format section for details.
    - In the **Write Key** field, enter the write key for your Honeycomb team. This is available on the Honeycomb Account page.

- In the **Dataset** field, enter the name of the Honeycomb Dataset (e.g., `myDataset`).

4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

Example format

Data sent to Honeycomb must be serialized as a JSON object. Here's an example format string for sending data to Honeycomb:

```
{
  "time":"%{begin:%Y-%m-%dT%H:%M:%SZ}t",
  "data":  {
    "service_id":"%{req.service_id}V",
    "time_elapsed":%D,
    "request":"%m",
    "host":"%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Or
    "url":"%{cstr_escape(req.url)}V",
    "protocol":"%H",
    "is_ipv6":%{if(req.is_ipv6, "true", "false")}V,
    "is_tls":%{if(req.is_ssl, "true", "false")}V,
    "is_h2":%{if(fastly_info.is_h2, "true", "false")}V,
    "client_ip":"%h",
    "geo_city":"%{client.geo.city.utf8}V",
    "geo_country_code":"%{client.geo.country_code}V",
    "server_datacenter":"%{server.datacenter}V",
    "request_referer":"%{Referer}i",
    "request_user_agent":"%{User-Agent}i",
    "request_accept_content":"%{Accept}i",
    "request_accept_language":"%{Accept-Language}i",
    "request_accept_charset":"%{Accept-Charset}i",
    "cache_status":"%{regsub(fastly_info.state, "^(HIT-(SYNTH)
    "status":"%s",
    "content_type":"%{Content-Type}o",
    "req_header_size":%{req.header_bytes_read}V,
    "req_body_size":%{req.body_bytes_read}V,
    "resp_header_size":%{resp.header_bytes_written}V,
    "resp_body_size":%{resp.body_bytes_written}V
  }
```

```
}

```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.
2. In the Honeycomb area, click **Create endpoint**.
3. Fill out the **Create a Honeycomb endpoint** fields as follows:
    - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
    - In the **Write Key** field, enter the write key for your Honeycomb team. This is available on the Honeycomb Account page.
    - In the **Dataset** field, enter the name of the Honeycomb Dataset (e.g., `myDataset`).
4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

Recommended log format

Data sent to Honeycomb must be serialized in a way conforming to Honeycomb's expectations. If your logs are not formatted properly, attempts at processing your logs by your Honeycomb endpoint may fail. Here's an example format string for sending data to Honeycomb:

```
{
    "time": "2022-05-11T23:35:30.384Z",
    "data": {
        "message": "Something happened",
        "severity": "INFO"
    }
}

```

You can follow the general JSON structure above regardless of the chosen language for your Compute service and include the specific details inside the nested `data` structure. Consult the Honeycomb documentation for other available options for Honeycomb log messages. The emitted logs must be formatted as valid JSON.

---

* * *

Log streaming: HTTPS

/en/guides/log-streaming-https

Fastly's Real-Time Log Streaming feature can send log files to an HTTPS endpoint.

> NOTE
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

When sending logs to a HTTPS endpoint, Fastly requires proof that you control the domain name specified in the **URL** field by using a HTTP challenge on a well-known path. If, for example, your **URL** field is `foo.example.com/some/log/path`, then the following challenge path must send a 200 response:

```
foo.example.com/.well-known/fastly/logging/challenge
```

Responses must include the hex representation of the SHA-256 of your Fastly service ID and it must appear on its own line in the response. For example:

```
$ sha256sum <SERVICEID>

ef537f25c895bfa782526529a9b63d97aa631564d5d789c2b765448c8635fb6c
```

If multiple service IDs are used, multiple hex(sha256) lines can be added to that challenge body. In addition, an asterisk (`*`) can be used on a line to allow any service to post to the

HTTP endpoint. For example:

```
ef537f25c895bfa782526529a9b63d97aa631564d5d789c2b765448c8635fb6c
06ae6402e02a9dad74edc71aa69c77c5747e553b0840bfc56feb7e65b23f0f61
*
```

Adding HTTPS as a logging endpoint

Follow these instructions to add HTTPS as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the HTTPS area, click **Create endpoint**.
3. Fill out the **Create an HTTPS endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
    - In the **URL** field, enter the URL to which log data will be sent (e.g., `https://logs.example.com/`).
    - *(Optional)* In the **Maximum logs** field, enter the maximum number of logs to send as a batch.
    - *(Optional)* In the **Maximum bytes** field, enter the maximum size of a log batch.
4. Click **Advanced options** and fill out the fields as follows:
    - *(Optional)* In the **Content type** field, enter the content type to use when sending logs (e.g., `application/json`).
    - *(Optional)* In the **Custom header name** field, enter a custom header to use when sending logs (e.g., `Authorization`).
    - *(Optional)* In the **Custom header value** field, enter a custom header value to use when sending logs (e.g., `Bearer <token>`).

- *(Optional)* In the **Method** area, select the appropriate HTTP method to use.
- In the **JSON log entry format** area, select the appropriate log entry format to use. The JSON log entry format enforces valid JSON formatting. Selecting **Array of JSON** wraps JSON log batches in an array. Selecting **Newline delimited** places each JSON log entry onto a new line in a batch.
- In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.

5. Fill out the **Using your own certificate authority (CA)** section of the **Advanced options** area as follows:
   - *(Optional)* In the **TLS Hostname** field, enter the hostname used to verify the logging endpoint server's certificate. This can be either the Common Name (CN) or Subject Alternative Name (SAN). This field only appears when you select Yes from the Use TLS menu.
   - *(Optional)* In the **TLS CA certificate** field, copy and paste the certification authority (CA) certificate used to verify the logging endpoint server's certificate is valid. The certificate you upload must be in PEM format. Consider uploading the certificate if it's not signed by a well-known certification authority. This value is not required if your TLS certificate is signed by a well-known authority. This field only appears when you select Yes from the Use TLS menu.
   - *(Optional)* In the **TLS client certificate** field, copy and paste the TLS client certificate used to authenticate Fastly to the logging endpoint server. The TLS client certificate you upload must be in PEM format and must be accompanied by a client key. A TLS client certificate allows your logging endpoint server to authenticate that Fastly is performing the connection. This field only appears when you select Yes from the Use TLS menu.
   - *(Optional)* In the **TLS client key** field, copy and paste the TLS client key used to authenticate to the logging endpoint server. The TLS client key you upload must be in PEM format and must be accompanied by a TLS client certificate. A TLS client key allows your logging endpoint server to authenticate that Fastly is performing the connection. This field only appears when you select Yes from the Use TLS menu.
6. Click **Create** to create the new logging endpoint.
7. Click **Activate** to deploy your configuration changes.

Example format

The following is an example format string for sending data to an HTTPS logging endpoint. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.start
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Orig-H
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V",
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(resp.r
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0, "tru
}
```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.
2. In the HTTPS area, click **Create endpoint**.
3. Fill out the **Create an HTTPS endpoint** fields as follows:
   - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
   - In the **URL** field, enter the URL to which log data will be sent (e.g., `https://logs.example.com/`).

- *(Optional)* In the **Maximum logs** field, enter the maximum number of logs to send as a batch.
- *(Optional)* In the **Maximum bytes** field, enter the maximum size of a log batch.

4. Click **Advanced options** and fill out the fields as follows:
   - *(Optional)* In the **Content type** field, enter the content type to use when sending logs (e.g., `application/json`).
   - *(Optional)* In the **Custom header name** field, enter a custom header to use when sending logs (e.g., `Authorization`).
   - *(Optional)* In the **Custom header value** field, enter a custom header value to use when sending logs (e.g., `Bearer <token>`).
   - *(Optional)* In the **Method** area, select the appropriate HTTP method to use.
   - In the **JSON log entry format** area, select the appropriate log entry format to use. The JSON log entry format enforces valid JSON formatting. Selecting **Array of JSON** wraps JSON log batches in an array. Selecting **Newline delimited** places each JSON log entry onto a new line in a batch.
   - In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
5. Fill out the **Using your own certificate authority (CA)** section of the **Advanced options** area as follows:
   - *(Optional)* In the **TLS Hostname** field, enter the hostname used to verify the logging endpoint server's certificate. This can be either the Common Name (CN) or Subject Alternative Name (SAN). This field only appears when you select Yes from the Use TLS menu.
   - *(Optional)* In the **TLS CA certificate** field, copy and paste the certification authority (CA) certificate used to verify the logging endpoint server's certificate is valid. The certificate you upload must be in PEM format. Consider uploading the certificate if it's not signed by a well-known certification authority. This value is not required if your TLS certificate is signed by a well-known authority. This field only appears when you select Yes from the Use TLS menu.
   - *(Optional)* In the **TLS client certificate** field, copy and paste the TLS client certificate used to authenticate Fastly to the logging endpoint server. The TLS client certificate you upload must be in PEM format and must be accompanied by a client key. A TLS client certificate allows your logging endpoint server to

authenticate that Fastly is performing the connection. This field only appears when you select Yes from the Use TLS menu.

- *(Optional)* In the **TLS client key** field, copy and paste the TLS client key used to authenticate to the logging endpoint server. The TLS client key you upload must be in PEM format and must be accompanied by a TLS client certificate. A TLS client key allows your logging endpoint server to authenticate that Fastly is performing the connection. This field only appears when you select Yes from the Use TLS menu.

6. Click **Create** to create the new logging endpoint.
7. Click **Activate** to deploy your configuration changes.

Firewall considerations

Your HTTPS endpoint may have limited security features. For this reason, it's best to create a firewall for your HTTP endpoint server and only accept TCP traffic on your configured port from our address blocks. Our list of IP address blocks is dynamic, so we recommend programmatically obtaining the list whenever possible.

---

* * *

	Log streaming: Hydrolix
🔗	/en/guides/log-streaming-hydrolix

Fastly's Real-Time Log Streaming feature can send log files to Hydrolix, a cloud-based time-series data platform. Hydrolix provides a native integration for Fastly log storage and analysis through Fastly's HTTPS logging endpoint. Hydrolix lets you ingest and query those logs in real-time.

> **NOTE**
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

If you don't already have a Hydrolix account, you'll need to sign up on the Hydrolix website. You'll also need to know the following about the target Hydrolix environment:

- Instance name
- Project name
- Table name

> **TIP**
>
> Consider reading Hydrolix's documentation on integrating with Fastly.

Adding Hydrolix as a logging endpoint

> **NOTE**
>
> This logging endpoint is only available for Fastly's Deliver (VCL-based) services, not for Compute services.

Follow these instructions to add Hydrolix as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the HTTPS area, click **Create endpoint** button.
3. Fill out the **Create an HTTPS endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, replace the placeholder log format and make the appropriate changes as shown in our log format and recommendations section below.
    - In the **URL** field, enter `https://<hydrolix-instance>.hydrolix.live/ingest/event`, replacing `<hydrolix-instance>` with the name of your Hydrolix instance.
    - In the **Maximum logs** field, leave as `0` (the default).
    - In the **Maximum bytes** field, enter `0`.

4. Click the **Advanced options** link of the **Create an HTTPS endpoint** page. The Advanced options appear.

5. Fill out the **Advanced options** of the **Create an HTTPS endpoint** page as follows:
    - In the **Content type** field, enter `application/json`.
    - In the **Custom header name** field, enter `x-hdx-table`.
    - In the **Custom header value** field, enter `<hydrolix-project-name>.<hydrolix-table-name>`, substituting the values for your Hydrolix project and table names.
    - From the **Method** controls, select **POST**.
    - From the **JSON log entry format** controls, select **Newline delimited**.
    - Leave the **Select a log line format** and **Placement** controls set to the defaults.
    - In the **TLS hostname** field, optionally enter a hostname to verify the logging destination server's certificate. This should be one of the Subject Alternative Name (SAN) fields for the certificate. Common Names (CN) are not supported.
    - Leave **TLS CA certificate** field, **TLS client certificate** field and **TLS client key** field all empty.

6. Click **Create** to create the new logging endpoint.

7. Click **Activate** to deploy your configuration changes.

Log format recommendations

For this example we use the log format shown below. You can customize this format with any values you want as long as you also modify your **Transform** and **View** configurations.

```
{
  "timestamp":"%{begin:%Y-%m-%dT%H:%M:%S}t",
  "time_elapsed":%{time.elapsed.usec}V,
  "is_tls":%{if(req.is_ssl, "true", "false")}V,
  "client_ip":"%{req.http.Fastly-Client-IP}V",
  "geo_city":"%{client.geo.city}V",
  "geo_country_code":"%{client.geo.country_code}V",
  "request":"%{req.request}V",
  "host":"%{req.http.Fastly-Orig-Host}V",
  "url":"%{json.escape(req.url)}V",
```

```
    "request_referer":"%{json.escape(req.http.Referer)}V",
    "request_user_agent":"%{json.escape(req.http.User-Agent)}V",
    "request_accept_language":"%{json.escape(req.http.Accept-Lan
    "request_accept_charset":"%{json.escape(req.http.Accept-Cha
    "cache_status":"%{regsub(fastly_info.state, "^(HIT-(SYNTH)|(
  }

```

Configuring Hydrolix Streaming Intake

Once you have your `project` and `table` setup and Fastly is configured to send logs to your Hydrolix instance, you can focus on setting up the Fastly Log streaming ingest pipeline by defining an ingest transform schema.

Creating a transform schema

Below is the suggested transform schema to use with the recommended log format described above. Be sure to replace `<table uuid>` with the UUID of your target Hydrolix table. You need to have this transform setup as the default, so `"is_default"` is set to `true`.

```
{
    "name": "fastly_transform",
    "type": "json",
    "table": "<table uuid>",
    "description": "fastly https logs",
    "settings": {
        "is_default": true,
        "output_columns": [
                            {
                                "name": "timestamp",
                                "datatype": {
                                    "type": "datetime",
                                    "primary": true,
                                    "format": "2006-01-02T15:04:
                                }
                            },
                            {
                                "name": "time_elapsed",
```

```
            "datatype": {
                "type": "uint64"
            }
        },
        {
            "name": "is_tls",
            "datatype": {
                "type": "bool"
            }
        },
        {
            "name": "client_ip",
            "datatype": {
                "type": "string"
            }
        },
        {
            "name": "geo_city",
            "datatype": {
                "type": "string"
            }
        },
        {
            "name": "geo_country_code",
            "datatype": {
                "type": "string"
            }
        },
        {
            "name": "request",
            "datatype": {
                "type": "string"
            }
        },
        {
            "name": "host",
            "datatype": {
                "type": "string"
            }
        },
```

```
                {
                    "name": "url",
                    "datatype": {
                        "type": "string"
                    }
                },
                {
                    "name": "request_referer",
                    "datatype": {
                        "type": "string"
                    }
                },
                {
                    "name": "request_user_agent",
                    "datatype": {
                        "type": "string"
                    }
                },
                {
                    "name": "request_accept_language
                    "datatype": {
                        "type": "string"
                    }
                },
                {
                    "name": "request_accept_charset"
                    "datatype": {
                        "type": "string"
                    }
                },
                {
                    "name": "cache_status",
                    "datatype": {
                        "type": "string"
                    }
                }
            ]
        }
    }

```

Once you define the transform schema, Hydrolix is configured to accept the incoming Fastly log data.

Leveraging views

Hydrolix supports having many different query formats for a single dataset. The query data structure, or view, for a given dataset allows you to customized the queried data and restrict a user's access to a specific set of columns.

Hydrolix automatically generates a default view upon transform creation that can be used to immediately query the dataset - no additional configuration is required. However, you are encouraged to familiarize yourself with the view concept and the benefits that the feature can provide. More detailed information can be found on the Hydrolix site.

Further reading

Hydrolix provides a tutorial for querying and analyzing Fastly data from within their system.

* * *

Log streaming: Kafka

/en/guides/log-streaming-kafka

Fastly's Real-Time Log Streaming feature can send logs to Apache Kafka. Kafka is an open-source, high-throughput, low-latency platform for handling real-time data feeds.

NOTE

Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Before you begin

Before adding Apache Kafka as a logging endpoint for Fastly services, ensure Kafka is running on a remote server. You'll need to know the hostname or IP address of one or more

servers (brokers) and the category or feed name to which messages will be stored (topic). For more information on setting up Kafka check out the Apache Kafka Quickstart guide.

Each emitted Fastly log constitutes an individual Kafka record, and Fastly follows standard Kafka client protocols of producing multiple records for multiple Kafka partitions in batches. To ensure adequate log message throughput, be sure to adjust the **Maximum bytes** and **Compression codec** settings to match the capabilities of your log processing infrastructure.

Kafka is a shared resource by default, and other users of Kafka within your environment may affect throughput for Fastly logs. If you are operating your own Kafka infrastructure, Fastly recommends designating exclusive disk storage volumes to the partitions of the Kafka topic where you will send logs. You should also monitor IOPS and consumed bandwidth against the storage maximums to anticipate the need to expand capacity.

IMPORTANT

If your Kafka cluster's brokers use unique TLS certificates (i.e., each with a SAN section, uniquely identifying that broker), you must list every broker individually in the **Brokers** field. Otherwise, if your Kafka cluster configuration relies on auto-discovery of all brokers via one or a few Kafka bootstrap brokers, then all the brokers in the cluster must have TLS certificates, referencing a single shared hostname in the **TLS hostname** field.

Adding Kafka as a logging endpoint

Follow these instructions to add Kafka as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the Apache Kafka area, click **Create endpoint**.
3. Fill out the **Create an Apache Kafka endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.

- In the **Brokers** field, enter the hostname or IP address of one or more servers (Kafka brokers). By default, it will use port 9092. Be sure to append the port using the format `:[port]` (e.g., `:9093`) to the hostname if it is different from the default port. You can specify multiple servers using a comma-separated string.
- In the **Topic** field, enter the name of the topic to send logs to.
- *(Optional)* In the **Maximum bytes** field, enter the maximum size of a Kafka produce request message in bytes.
- *(Optional)* From the **Parse key-values** controls, select whether or not to parse any key-value pairs within the log format into Kafka record headers. Key-value pairs must lead a formatted log line as `key=val` and must be comma-separated. Neither keys nor values can begin with a double-quote. Keys can be preceded by an arbitrary number of spaces, cannot contain spaces, and must have at least one character. Values can be empty as in `key=`. Specify a record key for partitioning by including a `__record_key` key-value pair in your log line. Logs will be partitioned according to Kafka's uniform sticky partitioner strategy. In the absence of a designated record key, Fastly's Kafka client will distribute log messages evenly across the available partitions of a topic.
- *(Optional)* In the **Write acknowledgement** area, select the appropriate write acknowledgement a leader Kafka broker must receive for a produce request to be successful. Fastly's Kafka client will attempt limited redelivery of failed produce requests with exponential backoff and jitter to reduce thundering herd scenarios.
- *(Optional)* In the **Compression codec** area, select the appropriate codec to use for compression of your logs.
- *(Optional)* From the **Use SASL** controls, select whether or not to enable SASL authentication. SASL authentication can be enabled concurrently with TLS encryption. When you select Yes, additional SASL authentication fields appear.
- From the **SASL authentication mechanism** menu, select the appropriate challenge-response mechanism to use for authenticating the SASL client authentication username and password.
- In the **User** field, enter the SASL client authentication username.
- In the **Password** field, enter the SASL client authentication password.

- *(Optional)* From the **Use TLS** controls, select whether or not to enable TLS encryption for the Kafka endpoint. TLS encryption can be enabled concurrently with SASL authentication. When you select Yes, additional TLS fields appear.
- In the **TLS hostname** field, optionally enter a hostname to verify the logging destination server's certificate. This should be one of the Subject Alternative Name (SAN) fields for the certificate. Common Names (CN) are not supported. This field only appears when you select Yes from the **Use TLS** menu.
- *(Optional)* In the **TLS CA certificate** field, copy and paste the certification authority (CA) certificate used to verify that the Kafka broker's certificate is valid. The certificate you upload must be in PEM format. Consider uploading the certificate if it's not signed by a well-known certification authority. This value is not required if your TLS certificate is signed by a well-known authority. This field only appears when you select Yes from the Use TLS menu.
- *(Optional)* In the **TLS client certificate** field, copy and paste the TLS client certificate used to authenticate to the Kafka broker. The TLS client certificate you upload must be in PEM format and must be accompanied by a client key. A TLS client certificate allows your Kafka broker to authenticate that Fastly is performing the connection. This field only appears when you select Yes from the Use TLS menu.
- *(Optional)* In the **TLS client key** field, copy and paste the TLS client key used to authenticate to the Kafka broker. The TLS client key you upload must be in PEM format and must be accompanied by a TLS client certificate. A TLS client key allows your Kafka broker to authenticate that Fastly is performing the connection. This field only appears when you select Yes from the Use TLS menu.

4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

Example format

The following is an example format string for sending data to Apache Kafka. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.sta
```

```
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Or
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(res
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0,
}
```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.

2. In the Apache Kafka area, click **Create endpoint**.

3. Fill out the **Create an Apache Kafka endpoint** fields as follows:
    - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
    - In the **Brokers** field, enter the hostname or IP address of one or more servers (Kafka brokers). By default, it will use port 9092. Be sure to append the port using the format `:[port]` (e.g., `:9093`) to the hostname if it is different from the default port. You can specify multiple servers using a comma-separated string.
    - In the **Topic** field, enter the name of the topic to send logs to.
    - *(Optional)* In the **Maximum bytes** field, enter the maximum size of a Kafka produce request message in bytes.

- *(Optional)* From the **Parse key-values** controls, select whether or not to parse any key-value pairs within the log format into Kafka record headers. Key-value pairs must lead a formatted log line as `key=val` and must be comma-separated. Neither keys nor values can begin with a double-quote. Keys can be preceded by an arbitrary number of spaces, cannot contain spaces, and must have at least one character. Values can be empty as in `key=`. Specify a record key for partitioning by including a `__record_key` key-value pair in your log line. Logs will be partitioned according to Kafka's uniform sticky partitioner strategy. In the absence of a designated record key, Fastly's Kafka client will distribute log messages evenly across the available partitions of a topic.

- *(Optional)* In the **Write acknowledgement** area, select the appropriate write acknowledgement a leader Kafka broker must receive for a produce request to be successful. Fastly's Kafka client will attempt limited redelivery of failed produce requests with exponential backoff and jitter to reduce thundering herd scenarios.

- *(Optional)* In the **Compression codec** area, select the appropriate codec to use for compression of your logs.

- *(Optional)* From the **Use SASL** controls, select whether or not to enable SASL authentication. SASL authentication can be enabled concurrently with TLS encryption. When you select Yes, additional SASL authentication fields appear.

- From the **SASL authentication mechanism** menu, select the appropriate challenge-response mechanism to use for authenticating the SASL client authentication username and password.

- In the **User** field, enter the SASL client authentication username.

- In the **Password** field, enter the SASL client authentication password.

- *(Optional)* From the **Use TLS** controls, select whether or not to enable TLS encryption for the Kafka endpoint. TLS encryption can be enabled concurrently with SASL authentication. When you select Yes, additional TLS fields appear.

- In the **TLS hostname** field, optionally enter a hostname to verify the logging destination server's certificate. This should be one of the Subject Alternative Name (SAN) fields for the certificate. Common Names (CN) are not supported. If the hostname is not specified, the hostname of the first broker in the Brokers

field will be used. This field only appears when you select Yes from the Use TLS menu.

- *(Optional)* In the **TLS CA certificate** field, copy and paste the certification authority (CA) certificate used to verify that the Kafka broker's certificate is valid. The certificate you upload must be in PEM format. Consider uploading the certificate if it's not signed by a well-known certification authority. This value is not required if your TLS certificate is signed by a well-known authority. This field only appears when you select Yes from the Use TLS menu.
- *(Optional)* In the **TLS client certificate** field, copy and paste the TLS client certificate used to authenticate to the Kafka broker. The TLS client certificate you upload must be in PEM format and must be accompanied by a client key. A TLS client certificate allows your Kafka broker to authenticate that Fastly is performing the connection. This field only appears when you select Yes from the Use TLS menu.
- *(Optional)* In the **TLS client key** field, copy and paste the TLS client key used to authenticate to the Kafka broker. The TLS client key you upload must be in PEM format and must be accompanied by a TLS client certificate. A TLS client key allows your Kafka broker to authenticate that Fastly is performing the connection. This field only appears when you select Yes from the Use TLS menu.

4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

---

* * *

Log streaming: Log Shuttle

/en/guides/log-streaming-log-shuttle

Fastly's Real-Time Log Streaming feature can send log files to Log Shuttle. Log Shuttle is an open source application designed to provide simpler encrypted and authenticated log delivery.

NOTE

Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Adding Log Shuttle as a logging endpoint

Follow these instructions to add Log Shuttle as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the Log Shuttle area, click **Create endpoint**.
3. Fill out the **Create a Log Shuttle endpoint** fields as follows:
   - In the **Name** field, enter a human-readable name for the endpoint.
   - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
   - In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
   - In the **Token** field, enter the data authentication token. This is required for some endpoints like Heroku's Log Integration.
   - In the **URL** field, enter the URL to which log data will be sent (e.g., `https://logs.example.com/`).
4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

Example format

The following is an example format string for sending data to Log Shuttle. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.sta
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Ori
```

```
    "url": "%{json.escape(req.url)}V",
    "request_method": "%{json.escape(req.method)}V",
    "request_protocol": "%{json.escape(req.proto)}V",
    "request_referer": "%{json.escape(req.http.referer)}V",
    "request_user_agent": "%{json.escape(req.http.User-Agent)}V"
    "response_state": "%{json.escape(fastly_info.state)}V",
    "response_status": %{resp.status}V,
    "response_reason": %{if(resp.response, "%22"+json.escape(res
    "response_body_size": %{resp.body_bytes_written}V,
    "fastly_server": "%{json.escape(server.identity)}V",
    "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0, "
}
```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.
2. In the Log Shuttle area, click **Create endpoint**.
3. Fill out the **Create a Log Shuttle endpoint** fields as follows:
    - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
    - In the **Token** field, enter the data authentication token. This is required for some endpoints like Heroku's Log Integration.
    - In the **URL** field, enter the URL to which log data will be sent (e.g., `https://logs.example.com/`).
4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

---

* * *

Log streaming: LogDNA

/en/guides/log-streaming-logdna

Fastly's Real-Time Log Streaming feature can be configured to send logs in a format that is readable by LogDNA. LogDNA is a cloud-based log management system that aggregates system and application logs into a single location.

> **NOTE**
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

Before adding LogDNA as a logging endpoint for Fastly services, you'll need to perform the following steps:

- Sign up for a LogDNA account if you don't already have one. You can sign up for a free (but restricted plan) or upgrade a LogDNA plan to include more features.
- Set up a new LogDNA syslog source via the LogDNA web application by following their account-tailored log source instructions. Be sure to make note of the port number displayed at the end of the syslog URL when you complete set up. This is the port number you'll enter when setting up LogDNA as a logging endpoint for Fastly.

Adding LogDNA as a logging endpoint

1. Review the information in our guide to setting up remote log streaming.
2. In the LogDNA (via Syslog) area, click **Create endpoint**.
3. Fill out the **Create a Syslog endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
    - In the **Syslog address** field, enter `syslog-a.logdna.com`. In the port field after the colon, enter the LogDNA port number you noted during your LogDNA

account setup.

- From the **TLS** menu, select **Yes** to enable encryption for the syslog endpoint. The TLS Hostname and TLS CA Certificate fields will both appear.
- In the **TLS Hostname** field, enter `syslog-a.logdna.com`. This is the hostname Fastly will use to verify the syslog server's certificate.

4. Click the **Advanced options** link of the **Create a Syslog endpoint** page and decide which of the optional fields to change, if any.
5. Fill out the **Advanced options** of the **Create a Syslog endpoint** page as follows:
   - In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
6. Click **Create** to create the new logging endpoint.
7. Click **Activate** to deploy your configuration changes.

Logs should begin appearing in your LogDNA account a few seconds after you've created the endpoint and deployed your service.

Example format

The following is an example format string for sending data to LogDNA. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.sta
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Ori
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(res
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
```

```
16    "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0,
17  }
18
```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.
2. In the LogDNA (via Syslog) area, click **Create endpoint**.
3. Fill out the **Create a Syslog endpoint** fields as follows:
    - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
    - In the **Syslog address** field, enter `syslog-a.logdna.com`. In the port field after the colon, enter the LogDNA port number you noted during your LogDNA account setup.
    - From the **TLS** menu, select **Yes** to enable encryption for the Syslog endpoint. The TLS Hostname and TLS CA Certificate fields will both appear.
    - In the **TLS Hostname** field, enter `syslog-a.logdna.com`. This is the hostname Fastly will use to verify the Syslog server's certificate.
4. *(Optional)* To change the log line format, click **Advanced options**. In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information. This must be compatible with your LogDNA configuration.
5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

Logs should begin appearing in your LogDNA account a few seconds after you've created the endpoint and deployed your service.

Recommended log format

Log messages can take on any format you choose because the log line format selected above will affect the overall line sent to and parsed by LogDNA.

* * *

Log streaming: Loggly

/en/guides/log-streaming-loggly

Fastly's Real-Time Log Streaming feature can send log files to Loggly. Loggly is an agent-less log collection and management tool.


> **NOTE**
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

If you don't already have a Loggly account, you'll need to register for one. Follow the signup instructions on the Loggly website.

Follow the steps below to find your Loggly customer token:

1. Navigate to the **Customer Tokens** area in the **Source Setup** on your Loggly dashboard.



2. Make note of your Loggly customer token. Loggly uses this to associate data you send them with your account.

Adding Loggly as a logging endpoint

After you've created a Loggly account and obtained your customer token, follow these instructions to add Loggly as a logging endpoint for Fastly services:

1. Review the information in our guide to setting up remote log streaming.
2. In the Loggly area, click **Create endpoint**.
3. Fill out the **Create a Loggly endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
    - In the **Token** field, enter your Loggly customer token.
4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

Example format

The following is an example format string for sending data to Loggly. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.sta
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Ori
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(res
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0,
```

```
17  }
18
```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.
2. In the Loggly area, click **Create endpoint** button.
3. Fill out the **Create a Loggly endpoint** fields as follows:
   - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
   - In the **Token** field, enter your Loggly customer token.
4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

---

* * *

Log streaming: Heroku's Logplex

/en/guides/log-streaming-logplex

As part of our Real-Time Log Streaming feature, you can send log files to Heroku's Logplex system. Logplex is Heroku's distributed syslog router that collates and distributes log entries from a variety of sources into a single channel.

> **NOTE**
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

Before continuing, you will need the token from your Heroku Logplex account. If you don't have a Heroku Logplex account, now is the time to set one up by signing up for Heroku.

Once enabled, your Fastly logs will be available in exactly the same way as your regular app and hosted service logs. You can view them using the Heroku command line log viewer or send them to a logging add-on.

Adding Heroku Logplex as a logging endpoint

Follow these instructions to add Heroku Logplex as a logging endpoint for Fastly services:

1. Review the information in our guide to setting up remote log streaming.
2. In the Heroku Logplex area, click **Create endpoint**.
3. Fill out the **Create a Heroku Logplex endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
    - In the **Token** field, enter your Heroku Logplex token.
    - In the **URL** field, enter `https://1.us.logplex.io/logs` unless otherwise instructed by our support staff.
4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

Example format

The following is an example format string for sending data to Logplex. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.sta
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
```

```
    "geo_city": "%{client.geo.city}V",
    "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Or
    "url": "%{json.escape(req.url)}V",
    "request_method": "%{json.escape(req.method)}V",
    "request_protocol": "%{json.escape(req.proto)}V",
    "request_referer": "%{json.escape(req.http.referer)}V",
    "request_user_agent": "%{json.escape(req.http.User-Agent)}V
    "response_state": "%{json.escape(fastly_info.state)}V",
    "response_status": %{resp.status}V,
    "response_reason": %{if(resp.response, "%22"+json.escape(res
    "response_body_size": %{resp.body_bytes_written}V,
    "fastly_server": "%{json.escape(server.identity)}V",
    "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0,
}
```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.
2. In the Heroku Logplex area, click **Create endpoint**.
3. Fill out the **Create a Heroku Logplex endpoint** fields as follows:
   - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
   - In the **Token** field, enter your Heroku Logplex token.
   - In the **URL** field, enter `https://1.us.logplex.io/logs` unless otherwise instructed by our support staff.
4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

---

* * *

Log streaming: New Relic Logs

/en/guides/log-streaming-newrelic-logs

Fastly's Real-Time Log Streaming feature can send log files to New Relic Logs.

> **NOTE**
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

Before adding New Relic Logs as a logging endpoint for Fastly services, you will need to:

- Register for a New Relic account.
- Obtain your license key.

Adding New Relic Logs as a logging endpoint

Follow these instructions to add New Relic Logs as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the New Relic Logs area, click **Create endpoint**.
3. Fill out the **Create a New Relic Logs endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
    - In the **License key / Insert key** field, enter your New Relic license key or Insert API key.
    - From the **Region** controls, select the region to stream logs to.

4. Click **Create** to create the new logging endpoint.

5. Click **Activate** to deploy your configuration changes.

Example format

Data sent to New Relic Logs must be serialized as a JSON object. Here's the recommended example format string for sending data to New Relic Logs:

```
{
  "timestamp": %{time.start.msec}V,
  "cache_status":"%{regsub(fastly_info.state, "^(HIT-(SYNTH)|(
  "client_ip":"%h",
  "client_device_type":"%{client.platform.hwtype}V",
  "client_os_name":"%{client.os.name}V",
  "client_os_version":"%{client.os.version}V",
  "client_browser_name":"%{client.browser.name}V",
  "client_browser_version":"%{client.browser.version}V",
  "client_as_name":"%{client.as.name}V",
  "client_as_number":"%{client.as.number}V",
  "client_connection_speed": "%{client.geo.conn_speed}V",
  "client_port": %{client.port}V,
  "client_rate_bps":%{client.socket.tcpi_delivery_rate}V,
  "client_recv_bytes":%{client.socket.tcpi_bytes_received}V,
  "client_requests_count":%{client.requests}V,
  "client_resp_body_size_write": %{resp.body_bytes_written}V,
  "client_resp_header_size_write": %{resp.header_bytes_writte
  "client_resp_ttfb": %{time.to_first_byte}V,
  "client_rtt_us":%{client.socket.tcpi_rtt}V,
  "content_type":"%{Content-Type}o",
  "domain": "%{Fastly-Orig-Host}i",
  "fastly_datacenter": "%{server.datacenter}V",
  "fastly_host": "%{server.hostname}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0, "
  "fastly_region": "%{server.region}V",
  "fastly_server": "%{json.escape(server.identity)}V",
  "host": "%v",
  "origin_host":"%v",
  "origin_name":"%{req.backend.name}V",
  "request":"%{req.request}V",
  "request_method":"%m",
```

```
    "request_accept_charset":"%{json.escape(req.http.Accept-Char
    "request_accept_language":"%{json.escape(req.http.Accept-Lan
    "request_referer":"%{json.escape(req.http.Referer)}V",
    "request_user_agent":"%{json.escape(req.http.User-Agent)}V",
    "resp_status":"%s",
    "response": "%{resp.response}V",
    "service_id":"%{req.service_id}V",
    "service_version": "%{req.vcl.version}V",
    "status":"%s",
    "time_start":"%{begin:%Y-%m-%dT%H:%M:%SZ}t",
    "time_end":"%{end:%Y-%m-%dT%H:%M:%SZ}t",
    "time_elapsed":%D,
    "tls_cipher":"%{json.escape(tls.client.cipher)}V",
    "tls_version":"%{json.escape(tls.client.protocol)}V",
    "url":"%{json.escape(req.url)}V",
    "user_agent":"%{json.escape(req.http.User-Agent)}V",
    "user_city":"%{client.geo.city.utf8}V",
    "user_country_code":"%{client.geo.country_code}V",
    "user_continent_code":"%{client.geo.continent_code}V",
    "user_region":"%{client.geo.region}V"
}
```

Logging a timestamp

If a timestamp field is present in the Fastly log, it must be specified as milliseconds since Epoch to override the New Relic timestamp. If not included, Fastly will generate a timestamp.

Using New Relic Instant Observability's prebuilt Fastly dashboard

New Relic I/O is an open source ecosystem of community-contributed quickstarts for hundreds of tools and technologies. We've worked with New Relic to develop a prebuilt dashboard that highlights certain key metrics we think are important and useful. Setting up the dashboard is easy and the code is open source in case you want to customize it.

Configure your service to use the recommended expanded logging format


Since the prebuilt dashboard expects certain fields to be present, we encourage using the recommended logging format. That said, there is nothing to stop you from adding

fields for your own purposes or to maintain backward compatibility with existing dashboards you've built. The dashboard won't break if you don't send some fields, but certain charts won't have data.


Install the Fastly dashboard

Follow these instructions to install the Fastly dashboard quickstart:


1. Select the Fastly dashboard quickstart from the New Relic marketplace.




2. Click **Install quickstart**.




3. Click **Begin installation**.




4. Click **Done** or **Skip this step**.



5. Click **See your data**.



The Fastly dashboard appears.



1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.

2. In the New Relic Logs area, click **Create endpoint**.


3. Fill out the **Create a New Relic Logs endpoint** fields as follows:
    - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
    - In the **License key / Insert key** field, enter your New Relic license key or Insert API key.

4. Click **Create** to create the new logging endpoint.

5. Click **Activate** to deploy your configuration changes.

Using New Relic Instant Observability's prebuilt Fastly dashboard

New Relic I/O is an open source ecosystem of a wide variety of community-contributed monitoring quickstarts. We worked with New Relic to develop a prebuilt dashboard that highlights key metrics. Because the code is open source, you can customize it.



Configure your log messages

Data sent to New Relic Logs must be serialized as a JSON object. The JSON object should include the following fields:

- `timestamp`: when the request occurred. The timestamp must be specified as milliseconds since Epoch to override the New Relic timestamp. If timestamp is not included, Fastly will generate a timestamp.
- `client_ip`: the IP address of the client making the HTTP request.
- `url`: the URL of the request.
- `resp_status`: the HTTP status code of the request.
- `client_resp_header_size_write`: the size of the response header.
- `client_resp_body_size_write`: the size of the response body.
- `fastly_datacenter`: the three-character identifying code of the FASTLY_POP in which the current instance is running.
- `time_elapsed`: the time since the request started.
- `service_id`: the identifier for the Fastly service that is processing the current request.

An example of the suggested more descriptive JSON log object is shown below.

```
{
  "timestamp": 1661976797605,
  "cache_status": "ERROR",
  "client_ip": "127.0.0.1",
  "client_device_type": "Chromebook",
  "client_os_name": "Ubuntu",
  "client_os_version": "17.10 (Artful Aardvark)",
  "client_browser_name": "Firefox",
  "client_browser_version": "113.0",
  "client_as_name": "zayo bandwidth",
  "client_as_number": "1234",
  "client_connection_speed": "broadband",
  "client_port": 63850,
  "client_rate_bps": 0,
  "client_recv_bytes": 74,
  "client_requests_count": 1,
  "client_resp_body_size_write": 56789,
  "client_resp_header_size_write": 1234,
  "client_resp_ttfb": 1.342,
  "client_rtt_us": 6818,
  "content_type": "text/html; charset=utf-8",
  "domain": "example.com",
  "fastly_datacenter": "HNL",
  "fastly_host": "cache-hnl00001",
  "fastly_is_edge": true,
  "fastly_region": "US-Pacific",
  "fastly_server": "cache-hnl00001-HNL",
  "host": "example.com",
  "origin_host": "example.com",
  "origin_name": "n/a",
  "request": "GET",
  "request_method": "GET",
  "request_accept_charset": "utf-8",
  "request_accept_language": "en-US",
  "request_referer": "",
  "request_user_agent": "curl/7.68.0",
  "resp_status": "503",
  "response": "Backend unavailable, connection timeout",
  "service_id": "000q0j0WE0f00z0KEVj5I0",
  "service_version": "29",
```

```
    "status": "503",
    "time_start": "2023-05-18T23:21:52Z",
    "time_end": "2023-05-18T23:21:53Z",
    "time_elapsed": 237,
    "tls_cipher": "TLS_ECDHE_ECDSA_WITH_AES_128_GCM_SHA256",
    "tls_version": "TLS 1.2",
    "url": "/",
    "user_agent": "curl/7.68.0",
    "user_city": "san francisco",
    "user_country_code": "US",
    "user_continent_code": "NA",
    "user_region": "CA"
  }
```

While the prebuilt dashboard won't break if the JSON object doesn't include all of the expected fields, certain charts won't have data.

In addition to the suggested fields, you can include fields of your choosing in the JSON object for your own purposes or to maintain backward compatibility with existing dashboards you've built.

Install the Fastly dashboard

Follow these instructions to install the Fastly dashboard quickstart:

1. Select the Fastly dashboard quickstart from the New Relic marketplace.
2. Click **Install quickstart**.
3. Click **Begin installation**.
4. Click **Done** or **Skip this step**.
5. Click **See your data**. The Fastly dashboard appears.

---

* * *

Log streaming: New Relic OTLP

/en/guides/log-streaming-newrelic-otlp

Fastly's Real-Time Log Streaming feature can send log files to New Relic OTLP.

> **NOTE**
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

Before adding New Relic OTLP as a logging endpoint for Fastly services, you will need to:

- Register for a New Relic account.
- Obtain your license key for reporting data.
- If you are using New Relic Infinite tracing, find your New Relic Trace Observer URL in the New Relic Infinite Tracing Settings. You'll need to copy the endpoint value under **For OTLP HTTP**.

Adding New Relic OTLP as a logging endpoint

Follow these instructions to add New Relic OTLP as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the **New Relic OTLP** area, click **Create endpoint**.
3. Fill out the **Create a New Relic OTLP endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **License key / Insert key** field, enter your New Relic license key or Insert API key.
    - From the **Region** controls, select the region to stream logs to.
4. *(Optional)* If you are using New Relic Infinite Tracing, click **Advanced options** and enter your **New Relic Trace Observer URL** in the **Trace Observer URL** field.
5. Click **Create** to create the new logging endpoint.

6. Click **Activate** to deploy your configuration changes.

7. Follow the instructions below to instrument your VCL service.

Instrumenting your VCL service

After setting up your endpoint, you will need to add custom VCL to gather the data and generate Open Telemetry traces at the edge.

1. Place the following functions at the top of your custom VCL file.

```
sub time_now_ns STRING {
  declare local var.time_now INTEGER;
  set var.time_now = std.atoi(time.start.usec);
  set var.time_now += std.atoi(time.elapsed.usec);
  set var.time_now *= 1000;
  return var.time_now;
}
sub random_8bit_identifier STRING {
  declare local var.id STRING;
  set var.id = randomstr(16, "0123456789abcdef");
  return var.id;
}
sub random_16bit_identifier STRING {
  declare local var.id STRING;
  set var.id = randomstr(32, "0123456789abcdef");
  return var.id;
}

sub otel_resource STRING {
   declare local var.str STRING;
   set var.str = {"{ "attributes": [ "}
   {"{ "key": "service.name",           "value": { "strin
   {"{ "key": "telemetry.sdk.language", "value": { "strin
   {"{ "key": "telemetry.sdk.name",     "value": { "strin
   {"{ "key": "telemetry.sdk.version",  "value": { "strin
   {"{ "key": "host.name",              "value": { "strin
   {"], "droppedAttributesCount": 0 }"};
   return var.str;
}

```

```
sub otel_attributes_general STRING {
   declare local var.data STRING;
   set var.data = ""
   {"{ "key": "http.method",    "value": { "stringValue":
   {"{ "key": "http.target",    "value": { "stringValue":
   {"{ "key": "http.host",      "value": { "stringValue":
   {"{ "key": "http.protocol",  "value": { "stringValue":
   {"{ "key": "http.client_ip", "value": { "stringValue":

   {"{ "key": "fastly.restarts",     "value": { "stringVa
   {"{ "key": "fastly.visits_this_service", "value": { "s
   {"{ "key": "fastly.server_role",  "value": { "stringVa
   {"{ "key": "fastly.server_ip",    "value": { "stringVa
   {"{ "key": "fastly.server_id",    "value": { "stringVa
   {"{ "key": "fastly.server_role",  "value": { "stringVa
   {"{ "key": "fastly.vcl_version",  "value": { "stringVa
   {"{ "key": "fastly.pop",          "value": { "stringVa
   {"{ "key": "fastly.workspace.overflowed",  "value": {
   {"{ "key": "fastly.workspace.bytes_total", "value": {
   {"{ "key": "fastly.workspace.bytes_free",  "value": {
   ;
   return var.data;
}

sub telem_start_backend_fetch {
  set bereq.http.traceparent = "00-" req.http.x-trace-id

  # Avoid leaking internal headers to backends
  unset bereq.http.x-trace-id;
  unset bereq.http.x-trace-parent-span-id;
  unset bereq.http.x-trace-server-role;

  # Leapfrog cloud service infra that creates 'ghost span
  set bereq.http.x-traceparent = bereq.http.traceparent;
}

```

2. Add the following VCL to the start of the `vcl_recv` subroutine to record a span for the whole of a request's lifetime within a Fastly POP.

```
if (req.restarts == 0) {
  set req.http.x-trace-vcl-span-id = random_8bit_identifier(
  if (req.http.traceparent ~ "^\d+-(\w+)-(\w+)-\d+$") {
    set req.http.x-trace-id = re.group.1;
    set req.http.x-trace-parent-span-id = re.group.2;
  } else {
    set req.http.x-trace-id = random_16bit_identifier();
  }
  set req.http.x-trace-server-role = if (fastly.ff.visits_th
}
```

3. Add the following VCL to the end of the `vcl_log` subroutine, replacing `otel_collector_http` with the name of your endpoint.

```
declare local var.otel_resource STRING;
declare local var.otel_attribs STRING;
declare local var.time_start_ns STRING;
declare local var.time_now_ns STRING;
set var.time_start_ns = time.start.usec "000";
set var.time_now_ns = time_now_ns();
set var.otel_resource = otel_resource();
set var.otel_attribs = otel_attributes_general();
log "syslog " req.service_id " otel_collector_http :: "
  {"{ "resourceSpans": [ { "}
    {""resource": "} var.otel_resource {", "}
    {""scopeSpans": [ { "spans": [ { "}
      {""traceId": ""} req.http.x-trace-id {"", "}
      {""spanId": ""} req.http.x-trace-vcl-span-id {"", "
      if(req.http.x-trace-parent-span-id,
        {""parentSpanId": ""} req.http.x-trace-parent-spa
      "")
      {""name": "Fastly request processing", "}
      {""kind": 1, "}
      {""startTimeUnixNano": "} var.time_start_ns {", "}
      {""endTimeUnixNano": "} var.time_now_ns {", "}
      {""attributes": [ "}
        var.otel_attribs
```

```
          {"{ "key": "http.user_agent", "value": { "stringV
          {"{ "key": "http.status_code", "value": { "string
        {"], "}
        {""status": { "code":"} if (fastly_info.state ~ "ER
        {""links": [], "}
        {""droppedLinksCount": 0"}
      {"} ] } ]"}
    {"} ] }"}
  ;
```

4. Add a call to `telem_start_backend_fetch` and place it in the `vcl_miss` and `vcl_pass` subroutines to see spans that happen in backend systems as children of the Fastly spans.

5. Activate the service.

1. Review the information in our guide to setting up remote log streaming.

2. In the **New Relic OTLP** area, click **Create endpoint**.

3. Fill out the **Create a New Relic OTLP endpoint** fields as follows:
   - In the **Name** field, enter a human-readable name for the endpoint.
   - In the **License key / Insert key** field, enter your New Relic license key or Insert API key.
   - From the **Region** controls, select the region to stream logs to.

4. *(Optional)* If you are using New Relic Infinite Tracing, click **Advanced options** and enter your **New Relic Trace Observer URL** in the **Trace Observer URL** field.

5. Click **Create** to create the new logging endpoint.

6. Click **Activate** to deploy your configuration changes.

Instrumenting your Compute service

Open Telemetry is a vendor-neutral, open-source Observability framework for instrumenting, generating, collecting, and exporting telemetry data such as traces, metrics, and logs. Refer to the Open Telemetry docs and the Fastly Compute documentation for additional information about using Open Telemetry in Compute.

* * *

Log streaming: OpenStack

/en/guides/log-streaming-openstack

Fastly's Real-Time Log Streaming feature can send log files to OpenStack. OpenStack is an open-source platform for cloud-computing that many companies deploy as an infrastructure-as-a-service.

> **NOTE**
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Adding OpenStack as a logging endpoint

Follow these instructions to add OpenStack as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the OpenStack area, click **Create endpoint**.
3. Fill out the **Create an OpenStack endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
    - *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.

- In the **Auth URL** field, enter the URL used for OpenStack authentication (e.g., `https://auth.api.rackspacecloud.com/v1.0`).
- In the **Bucket name** field, enter the name of the OpenStack bucket in which to store the logs.
- In the **User** field, enter your OpenStack username.
- In the **Access Key** field, enter your OpenStack access key.
- *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds.

4. Click **Advanced options** and fill out the fields as follows:
   - *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be saved in the bucket's root path. Our guide on changing where log files are written provides more information.
   - *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.
   - In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
   - *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.
5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

Example format

The following is an example format string for sending data to OpenStack. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.start)
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Orig-H
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V",
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(resp.r
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0, "tru
}

```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.

2. In the OpenStack area, click **Create endpoint**.

3. Fill out the **Create an OpenStack endpoint** fields as follows:
   - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
   - *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.
   - In the **Auth URL** field, enter the URL used for OpenStack authentication (e.g., `https://auth.api.rackspacecloud.com/v1.0`).
   - In the **Bucket name** field, enter the name of the OpenStack bucket in which to store the logs.

- In the **User** field, enter your OpenStack username.
- In the **Access Key** field, enter your OpenStack access key.
- *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds.

4. Click **Advanced options** and fill out the fields as follows:
   - *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be saved in the bucket's root path. Our guide on changing where log files are written provides more information.
   - *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.
   - In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
   - *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.
5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

---

* * *

Log streaming: Oracle Cloud Storage

/en/guides/log-streaming-oracle-cloud-storage

Fastly's Real-Time Log Streaming feature can send log files to Oracle Cloud Storage using Oracle Cloud's S3-compatible API connectivity option. Oracle Cloud Storage is a static file


storage service used by developers and IT teams.

> **NOTE**
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

Before adding Oracle Cloud Storage as a logging endpoint for Fastly services, you need an Oracle **Customer Secret Key**, which consists of an **Access Key** and **Secret Key**. These need read and write permissions on the bucket.

You will also need to know the namespace identifier assigned to your bucket. You can find your namespace by clicking on the bucket and examining the **Bucket Information** tab (`decafbaddeadbeef` in this case).



Adding Oracle Cloud Storage as a logging endpoints

> **NOTE**
>
> This logging endpoint is only available for Fastly's Deliver (VCL-based) services, not for Compute services.

After you've registered for an Oracle Cloud Storage account and created an Access Key, follow these instructions to add Oracle Cloud Storage as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. Click the Amazon Web Services S3 logo.

3. Fill out the **Create an Amazon S3 endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
    - *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.
    - In the **Access method** area, select **User Credentials**.
    - In the **Bucket name** field, enter the name of the Oracle Cloud Storage bucket in which to store the logs.
    - In the **Access key** field, enter the access key associated with the Oracle account.
    - In the **Secret key** field, enter the secret key associated with the Oracle account.
    - *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds.
4. In the **Create a new S3 endpoint** area, click **Advanced options**.
5. Fill out the rest of the **Advanced options** as follows:
    - *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be saved in the bucket's root path. Our guide on changing where log files are written provides more information.
    - In the **Domain** field, enter `<namespace>.compat.objectstorage.<region>.oraclecloud.com`.
    - *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able

to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.

- In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
- *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.
- From the **Redundancy level** menu, select a setting. Valid values are **Standard** and **Infrequent Access**. This value defaults to **Standard**.
- *(Optional)* In the **Server side encryption** area, select an encryption method to protect files that Fastly writes to your Oracle Cloud Storage bucket. Valid values are **None** and **AES-256**. Check out Oracle's guide to this feature, which is functionally identical to Amazon's implementation except for lack of support for a key management service.

6. Click **Create** to create the new logging endpoint.
7. Click **Activate** to deploy your configuration changes.

> **NOTE**
>
> Although Fastly continuously streams logs into Oracle Cloud, the Oracle Cloud website and API do not make files available for access until after their upload is complete.

Example format

The following is an example format string for sending data to Oracle Cloud Storage. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.sta
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Ori
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
```

```
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(res
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0,
}
```

* * *

Log streaming: Papertrail

/en/guides/log-streaming-papertrail

Fastly's Real-Time Log Streaming feature can send log files to Papertrail. Papertrail is a web-based log aggregation application used by developers and IT teams. Instructions for setting up remote log streaming via Papertrail are detailed in the Papertrail setup and configuration documentation.

If you're setting up Papertrail for a Compute service, review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.

NOTE

Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

* * *

Log streaming: Scalyr

/en/guides/log-streaming-scalyr

Fastly's Real-Time Log Streaming feature can send log files to Scalyr (now known as DataSet). Scalyr pulls all your server logs and metrics into a centralized, searchable system in real time.

> NOTE
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

If you don't already have a Scalyr account, you'll need to register for one. Follow the signup instructions on the Scalyr website.

Once you've signed up, navigate to the **API Keys** area in the **Settings** on your Scalyr dashboard and make note of your Scalyr Write Token. Scalyr uses this to associate data you send them with your account. You'll need this token when you set up your endpoint with Fastly.

If you're adding the Scalyr endpoint via the command line, instead of the web interface, you should also have your Fastly API token and the service ID and version number of the Fastly service for which you'll be enabling Scalyr logging.

Adding Scalyr as a logging endpoint

Follow these instructions to add Scalyr as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the Scalyr area, click **Create endpoint**.
3. Fill out the **Create a Scalyr endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our

guide on changing log placement for more information.

- In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
- *(Optional)* In the **Logfile** field, specify the log file name under which your logs will appear on Scalyr's Overview page. Defaults to `logplex`.
- In the **Token** field, enter the Scalyr Write Token provided in the Scalyr dashboard.
- From the **Region** menu, select the region to stream logs to.

4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

Example format

The following is an example format string for sending data to Scalyr. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.sta
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Ori
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(res
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0,
```

```
}
```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.
2. In the Scalyr area, click **Create endpoint** button.
3. Fill out the **Create a Scalyr endpoint** fields as follows:
   - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
   - *(Optional)* In the **Logfile** field, specify the log file name under which your logs will appear on Scalyr's Overview page. Defaults to `logplex`.
   - In the **Token** field, enter the Scalyr Write Token provided in the Scalyr dashboard.
   - From the **Region** menu, select the region to stream logs to.
4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

---

* * *

Log streaming: SFTP

/en/guides/log-streaming-sftp

Fastly's Real-Time Log Streaming feature can send log files to SFTP, a secure file transfer subsystem for the Secure Shell (SSH) protocol. Our SFTP endpoint supports both password-based authentication and SSH public-key authentication, with SSH public-key authentication being preferred. To learn more about SSH public-key authentication, or to learn how to generate public and private key pairs, see this guide.

NOTE

Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Adding SFTP as a logging endpoint

Follow these instructions to add SFTP as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the SFTP area, click **Create endpoint**.
3. Fill out the **Create an SSH File Transfer Protocol (SFTP) endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
    - *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.
    - In the **Address** field, enter the hostname or IP address of the SFTP server. In the port field after the colon, enter the port number you're using for SFTP (the default is `22`).
    - In the **Path** field, enter the path to use for storing log files. Leaving the default `/` in this field means the files will be saved in the root path. We describe this variable in more detail in our guide on changing where log files are written.

> TIP
>
> If you save logs on the SFTP server, make sure the directory already exists.

    - In the **User** field, enter the username used to authenticate to the SFTP server.
    - In the **Known hosts** field, enter a Host key for each Host you can connect to over SFTP. Each Host key you enter must be on its own line. Known hosts entries should match what's stored in your `known_hosts` file located in your

home directory (or the local account settings if you're working with macOS or a Windows operating system). A known hosts entry looks like this:

```
1.2.3.4 ecdsa-sha2-nistp256 aBc123xYz…
```

where the `1.2.3.4` is the SFTP IP address, `ecdsa-sha2-nistp256` is your Host key algorithm, and `aBc123xYz…` is your public key.

- In the **Secret key** field, enter the SSH secret key used to connect to the server. If both Secret key and Password are entered, the Secret key will be used in preference.
- In the **Password** field, enter the password used to authenticate to the SFTP server. If both Password and Secret key are entered, the Secret key will be used in preference.
- *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds.

4. Click **Advanced options** and fill out the fields as follows:
   - In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
   - *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.
   - *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.
5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

Example format

The following is an example format string for sending data to an SFTP logging endpoint. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.start)
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Orig-H
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V",
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(resp.r
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0, "tru
}

```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.
2. In the SFTP area, click **Create endpoint**.
3. Fill out the **Create an SSH File Transfer Protocol (SFTP) endpoint** fields as follows:
    - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
    - *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.
    - In the **Address** field, enter the hostname or IP address of the SFTP server. In the port field after the colon, enter the port number you're using for SFTP (the default is `22`).

- In the **Path** field, enter the path to use for storing log files. Leaving the default `/` in this field means the files will be saved in the root path. We describe this variable in more detail in our guide on changing where log files are written.

> **TIP**
>
> If you save logs on the SFTP server, make sure the directory already exists.

- In the **User** field, enter the username used to authenticate to the SFTP server.
- In the **Known hosts** field, enter a Host key for each Host you can connect to over SFTP. Each Host key you enter must be on its own line. Known hosts entries should match what's stored in your `known_hosts` file located in your home directory (or the local account settings if you're working with macOS or a Windows operating system). A known hosts entry looks like this:

  ```
  1.2.3.4 ecdsa-sha2-nistp256 aBc123xYz…
  ```

  where the `1.2.3.4` is the SFTP IP address, `ecdsa-sha2-nistp256` is your Host key algorithm, and `aBc123xYz…` is your public key.
- In the **Secret key** field, enter the SSH secret key used to connect to the server. If both Secret key and Password are entered, the Secret key will be used in preference.
- In the **Password** field, enter the password used to authenticate to the SFTP server. If both Password and Secret key are entered, the Secret key will be used in preference.
- *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds.

4. Click **Advanced options** and fill out the fields as follows:

- *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.
- In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.

- *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.

5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

---

* * *

	Log streaming: Shape Log Analysis
🔗	/en/guides/log-streaming-shape-log-analysis

Fastly's Real-Time Log Streaming feature can send log files to Shape Security. Shape Log Analysis uses anonymized attack data to analyze HTTP and application logs for insight into fraudulent activity and various types of attack that attempt to bypass security measures protecting origin servers.

> **NOTE**
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

Before adding Shape Log Analysis as a logging endpoint, send an email to fastly@f5.com with the subject line "Fastly Log Streaming Setup" to request a secure S3 bucket from Shape. In return, you will receive an email with details to help you complete the configuration of the logging endpoint including:

1. a note about the Log format value
2. a Bucket name
3. an Access key
4. a Secret key
5. a Path

6. a Domain

Each item will be specifically numbered in the email and the images in the configuration details below reflect those numbers.

Adding Shape Log Analysis as a logging endpoint

> **NOTE**
>
> This logging endpoint is only available for Fastly's Deliver (VCL-based) services, not for Compute services.

> **IMPORTANT**
>
> Shape Log Analysis setup and configuration uses Fastly's Amazon S3 log streaming endpoint to enable logs for storage and analysis. It places them in a secure S3 bucket managed by Shape that only accepts traffic from Fastly IP addresses.

After you've contacted fastly@f5.com and received the prerequisite information email, complete the following steps:

1. Review the information in our guide to setting up remote log streaming.
2. In the Amazon Web Services S3 area, click **Create endpoint**.
3. Fill out the **Create an Amazon S3 endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, copy and paste the following log format value to send log data to Shape's secure S3 bucket:

```
{
  "timestamp": "%{begin:%Y-%m-%dT%H:%M:%S%z}t",
  "ts": "%{time.start.sec}V",
  "id.orig_h": "%h", "status_code": "%>s",
  "method": "%m",
  "host": "%{Host}i",
  "uri": "%U%q",
```

```
    "accept_encoding": "%{Accept-Encoding}i",
    "request_body_len": "%{req.body_bytes_read}V",
    "response_body_len": "%{resp.body_bytes_written}V",
    "location": "%{Location}i",
    "x_forwarded_for": "%{X-Forwarded-For}i",
    "user_agent": "%{User-Agent}i",
    "referer": "%{Referer}i",
    "accept": "%{Accept}i",
    "accept_language": "%{Accept-Language}i",
    "content_type": "%{Content-Type}o",
    "geo_city": "%{client.geo.city}V",
    "geo_country_code": "%{client.geo.country_code}V",
    "is_tls": %{if(req.is_ssl, "true", "false")}V,
    "tls_version": "%{tls.client.protocol}V",
    "tls_cipher_request": "%{tls.client.cipher}V",
    "tls_cipher_req_hash": "%{tls.client.ciphers_sha}V"
    "tls_extension_identifiers_hash": "%{tls.client.tls
  }
```

- In the **Access method** area, select **User Credentials**.
- In the **Bucket name** field, enter the name of value #2 “Bucket Name” received in the Shape email response.
- In the **Access key** field, enter the name of value #3 “Access Key” received in the Shape email response.
- In the **Secret key** field, enter the name of value #4 “Secret Key” received in the Shape email response.

> **NOTE**
>
> Password management software may mistakenly treat the **Secret Key** field as a password field because of the way your web browser works. As such, that software may try to auto-fill this field with your Fastly account password. If this happens to you, the integration with Fastly services won't work and you will need to enter **Secret Key** manually instead.


4. Click **Advanced options** and fill out the fields as follows:

- In the **Path** field, enter the name of value #5 “Path” received in the email response.
- In the **Domain** field, enter the name of value #6 “Domain” received in the email response.
- In the **Select a log line format** area, select `Blank` to prevent prefixes from being added to log line messages and only report details in JSON log format. Our guide on changing log line formats provides more information.

5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

Shape data analysis

Once Fastly logging configuration is complete, logs will be sent to Shape's secure S3 bucket for analysis. Typically, Shape collects approximately two weeks worth of log data to provide an analysis of attack traffic. After analysis is complete, Shape will send you a report with data on topics like Malicious Automation, Attack Surface (URLs), Account Takeover Bots, Suspicious Manual Fraud, and Top Bot Campaigns.



* * *

Log streaming: Splunk

/en/guides/log-streaming-splunk

Fastly's Real-Time Log Streaming feature can send log files to Splunk. Splunk is a web-based log analytics platform used by developers and IT teams.

> **NOTE**
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

To use Splunk as a logging endpoint, you'll need to enable the HTTP Event Collector (HEC), create a token, and enable it. Follow the instructions on Splunk's website:

1. Enable HEC.
2. Create an HEC token.
3. Enable the HEC token.
4. Disable indexer acknowledgment for tokens used by Fastly to stream logs.

You'll need to remember the HEC token and find the URL for your collector. The URL structure depends on the type of Splunk instance you're using. Use the table below to find the URL structure for your Splunk instance.

Type	URL
Self hosted	`https://<hostname>:8088/services/collector/event`
Self-service Splunk Cloud plans	`https://input-<hostname>:8088/services/collector/event`
All other Splunk Cloud plans	`https://http-inputs-<hostname>:8088/services/collector/event`

While logged in to Splunk, you can find the hostname for the URL in your web browser's address bar.

Adding Splunk as a logging endpoint

After you've created a Splunk account and obtained your customer token, follow these instructions to add Splunk as a logging endpoint for Fastly services:

1. Review the information in our guide to setting up remote log streaming.
2. In the Splunk area, click **Create endpoint**.
3. Fill out the **Create a Splunk endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.

- In the **Log format** field, enter an Apache-style string or VCL variables to use for log formatting. You can use our recommended log format.
- In the **URL** field, enter the URL to send data to (e.g., `https://<splunk_host>:8088/services/collector/event/1.0`).
- In the **Token** field, enter the token for the HEC.
- *(Optional)* From the **Use TLS** controls, select whether or not to enable TLS. When you select Yes, additional TLS fields appear.
- In the **TLS hostname** field, optionally enter a hostname to verify the logging destination server's certificate. This should be one of the Subject Alternative Name (SAN) fields for the certificate. Common Names (CN) are not supported. If you are using Splunk Enterprise see the Splunk Enterprise section below for more information.
- In the **TLS CA certificate** field, enter the CA certificate used to verify that the origin's certificate is valid. It must be in PEM format. This is not required if your origin-side TLS certificate is signed by a well-known CA. See the using TLS CA certificates section for more information.
- *(Optional)* In the **TLS client certificate** field, copy and paste the TLS client certificate used to authenticate to the origin server. The TLS client certificate you upload must be in PEM format and must be accompanied by a client certificate. A TLS client certificate allows your server to authenticate that Fastly is performing the connection. This field only appears when you select Yes from the Use TLS menu.
- *(Optional)* In the **TLS client key** field, copy and paste the TLS client key used to authenticate to the backend server. The TLS client key you upload must be in PEM format and must be accompanied by a TLS client certificate. A TLS client key allows your server to authenticate that Fastly is performing the connection.
- *(Optional)* In the **Maximum logs** field, enter the maximum number of logs to append to a batch, if non-zero.
- *(Optional)* In the **Maximum bytes** field, enter the maximum size of the log batch, if non-zero.

4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

Recommended log format

We recommend using the following log format to send data to Splunk.

> **NOTE**
>
> All JSON sent to the Splunk HEC must have an event field. The event field can be text or nested JSON. There can also be other meta data in the payload. See the Splunk documentation for more information.

```
{
  "time":%{time.start.sec}V,
  "host":"%{Fastly-Orig-Host}i",
  "event":  {
    "service_id":"%{req.service_id}V",
    "time_start":"%{begin:%Y-%m-%dT%H:%M:%S%Z}t",
    "time_end":"%{end:%Y-%m-%dT%H:%M:%S%Z}t",
    "time_elapsed":%D,
    "client_ip":"%h",
    "client_as_name":"%{client.as.name}V",
    "client_as_number":"%{client.as.number}V",
    "client_connection_speed":"%{client.geo.conn_speed}V",
    "request":"%m",
    "protocol":"%H",
    "origin_host":"%v",
    "url":"%{json.escape(req.url)}V",
    "is_ipv6":%{if(req.is_ipv6, "true", "false")}V,
    "is_tls":%{if(req.is_ssl, "true", "false")}V,
    "tls_client_protocol":"%{json.escape(tls.client.protocol)
    "tls_client_servername":"%{json.escape(tls.client.serverna
    "tls_client_cipher":"%{json.escape(tls.client.cipher)}V",
    "tls_client_cipher_sha":"%{json.escape(tls.client.ciphers_
    "tls_client_tlsexts_sha":"%{json.escape(tls.client.tlsexts
    "is_h2":%{if(fastly_info.is_h2, "true", "false")}V,
    "is_h2_push":%{if(fastly_info.h2.is_push, "true", "false"
    "h2_stream_id":"%{fastly_info.h2.stream_id}V",
    "request_referer":"%{Referer}i",
    "request_user_agent":"%{User-Agent}i",
    "request_accept_content":"%{Accept}i",
    "request_accept_language":"%{Accept-Language}i",
```

```
      "request_accept_encoding":"%{Accept-Encoding}i",
      "request_accept_charset":"%{Accept-Charset}i",
      "request_connection":"%{Connection}i",
      "request_dnt":"%{DNT}i",
      "request_forwarded":"%{Forwarded}i",
      "request_via":"%{Via}i",
      "request_cache_control":"%{Cache-Control}i",
      "request_x_requested_with":"%{X-Requested-With}i",
      "request_x_att_device_id":"%{X-ATT-Device-Id}i",
      "request_x_forwarded_for":"%{X-Forwarded-For}i",
      "status":"%s",
      "content_type":"%{Content-Type}o",
      "response_state":"%{fastly_info.state}V",
      "response_age":"%{Age}o",
      "response_cache_control":"%{Cache-Control}o",
      "response_expires":"%{Expires}o",
      "response_last_modified":"%{Last-Modified}o",
      "response_tsv":"%{TSV}o",
      "server_datacenter":"%{server.datacenter}V",
      "server_ip":"%A",
      "geo_city":"%{client.geo.city.utf8}V",
      "geo_country_code":"%{client.geo.country_code}V",
      "geo_continent_code":"%{client.geo.continent_code}V",
      "geo_region":"%{client.geo.region}V",
      "req_header_size":%{req.header_bytes_read}V,
      "req_body_size":%{req.body_bytes_read}V,
      "resp_header_size":%{resp.header_bytes_written}V,
      "resp_body_size":%B,
      "socket_cwnd":%{client.socket.cwnd}V,
      "socket_nexthop":"%{client.socket.nexthop}V",
      "socket_tcpi_rcv_mss":%{client.socket.tcpi_rcv_mss}V,
      "socket_tcpi_snd_mss":%{client.socket.tcpi_snd_mss}V,
      "socket_tcpi_rtt":%{client.socket.tcpi_rtt}V,
      "socket_tcpi_rttvar":%{client.socket.tcpi_rttvar}V,
      "socket_tcpi_rcv_rtt":%{client.socket.tcpi_rcv_rtt}V,
      "socket_tcpi_rcv_space":%{client.socket.tcpi_rcv_space}V,
      "socket_tcpi_last_data_sent":%{client.socket.tcpi_last_da
      "socket_tcpi_total_retrans":%{client.socket.tcpi_total_re
      "socket_tcpi_delta_retrans":%{client.socket.tcpi_delta_re
      "socket_ploss":%{client.socket.ploss}V
```

```
    }
}

```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.

2. In the Splunk area, click **Create endpoint**.

3. Fill out the **Create a Splunk endpoint** fields as follows:
    - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
    - In the **URL** field, enter the URL to send data to (e.g., `https://<splunk_host>:8088/services/collector/event/1.0`).
    - In the **Token** field, enter the token for the HEC.
    - *(Optional)* From the **Use TLS** controls, select whether or not to enable TLS. When you select Yes, additional TLS fields appear.
    - In the **TLS hostname** field, optionally enter a hostname to verify the logging destination server's certificate. This should be one of the Subject Alternative Name (SAN) fields for the certificate. Common Names (CN) are not supported. If you are using Splunk Enterprise check out the Splunk Enterprise section below for more information.
    - In the **TLS CA certificate** field, enter the CA certificate used to verify that the Splunk server's certificate is valid. It must be in PEM format. This is not required if your Splunk-side TLS certificate is signed by a well-known CA. Check out the using TLS CA certificates section for more information.
    - *(Optional)* In the **TLS client certificate** field, copy and paste the TLS client certificate used to authenticate Fastly to the Splunk server. The TLS client certificate you upload must be in PEM format and must be accompanied by a client key. A TLS client certificate allows your Splunk server to authenticate that Fastly is performing the connection. This field only appears when you select Yes from the Use TLS menu.

- *(Optional)* In the **TLS client key** field, copy and paste the TLS client key used to authenticate Fastly to the Splunk server. The TLS client key you upload must be in PEM format and must be accompanied by a TLS client certificate. A TLS client key allows your Splunk server to authenticate that Fastly is performing the connection.
- *(Optional)* In the **Maximum logs** field, enter the maximum number of logs to append to a batch.
- *(Optional)* In the **Maximum bytes** field, enter the maximum size of the log batch.

4. Click **Create** to create the new logging endpoint.
5. Click **Activate** to deploy your configuration changes.

Recommended log format

Data sent to Splunk HEC must be serialized in a way conforming to Splunk's expectations.

If your logs are not formatted properly, attempts at processing your logs by your Splunk endpoint may fail. Here's an example format string for sending data to Splunk:

```
{
    "time": 1652331824.730,
    "source": "fastly",
    "index": "main",
    "event": {
        "message": "Something happened",
        "severity": "INFO"
    }
}

```

Using TLS CA certificates

If you've installed your own TLS certificate in Splunk Enterprise or Splunk Cloud, you'll need to provide the corresponding CA certificate.

Splunk Cloud

For Splunk Cloud, the default set up has the following CA certificate:

```
-----BEGIN CERTIFICATE-----
MIIB/DCCAaGgAwIBAgIBADAKBggqhkjOPQQDAjB+MSswKQYDVQQDEyJTcGx1bmsg
Q2xvdWQgQ2VydGlmaWNhdGUgQXV0aG9yaXR5MRYwFAYDVQQHEw1TYW4gRnJhbmNp
c2NvMRMwEQYDVQQKEwpTcGx1bmsgSW5jMQswCQYDVQQIEwJDQTEVMBMGA1UECxMM
U3BsdW5rIENsb3VkMB4XDTE0MTExMDA3MDAxOFoXDTM0MTEwNTA3MDAxOFowfjEr
MCkGA1UEAxMiU3BsdW5rIENsb3VkIENlcnRpZmljYXRlIEF1dGhvcml0eTEWMBQG
A1UEBxMNU2FuIEZyYW5jaXNjbzETMBEGA1UEChMKU3BsdW5rIEluYzELMAkGA1UE
CBMCQ0ExFTATBgNVBAsTDFNwbHVuayBDbG91ZDBZMBMGByqGSM49AgEGCCqGSM49
AwEHA0IABPRRy9i3yQcxgMpvCSsI7Qe6YZMimUHOecPZWaGz5jEfB4+p5wT7dF3e
QrgjDWshVJZvK6KGO7nDh97GnbVXrTCjEDAOMAwGA1UdEwQFMAMBAf8wCgYIKoZI
zj0EAwIDSQAwRgIhALMUgLYPtICN9ci/ZOoXeZxUhn3i4wIo2mPKEWX0IcfpAiEA
8Jid6bzwUqAdDZPSOtaEBXV9uRIrNua0Qxl1S55TlWY=
-----END CERTIFICATE-----
```

Splunk Enterprise

Splunk Enterprise provides a set of default certificates, but we strongly recommend you configure your own certificates for your Fastly logging endpoint rather than relying on the default certificates. The certificates provided by Splunk Enterprise only specify a Common Name (CN), which cannot be used to properly verify the identity of the Splunk host presenting the certificate. Additionally, these certificates are less secure because the same root certificate is available in every Splunk Enterprise download. We encourage you to maintain the best possible security posture by configuring your own certificates rather than relying on the default certificates. The Splunk documentation provides a guide for configuring your own certificates.

* * *

Log streaming: Storj DCS

/en/guides/log-streaming-storj-dcs

Fastly's Real-Time Log Streaming feature can send log files to Storj DCS, a decentralized object storage service that is S3 compatible and end-to-end encrypted by default.

> NOTE
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

Before adding Storj DCS as a logging endpoint for Fastly services, you will need to create a Storj DCS account, project and access credentials, and a bucket that will store the log output.

Adding Storj DCS as a logging endpoint

> NOTE
>
> This logging endpoint is only available for Fastly's Deliver (VCL-based) services, not for Compute services.

Follow these instructions to add Storj DCS as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. Click the Amazon Web Services S3 logo.
3. Fill out the **Create an Amazon S3 endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
    - *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.

- In the **Bucket name** field, enter the name of the Storj DCS bucket in which to store the logs.
- In the **Access method** area, select **User Credentials**.
- In the **Access key** field, enter the access key associated with the Storj DCS bucket.
- In the **Secret key** field, enter the secret key associated with the Storj DCS bucket.
- *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. This value defaults to `3600` seconds.

4. Click **Advanced options** and fill out the fields as follows:
   - *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be saved in the bucket's root path. Our guide on changing where log files are written provides more information.
   - In the **Domain** field, enter the fully qualified hostname of any Storj DCS Gateway.
   - *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.
   - In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
   - *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.
   - From the **Redundancy level** menu, select a setting. This value defaults to **Standard**.
   - *(Optional)* In the **Server side encryption** area, select an encryption method to protect files that Fastly writes to your Storj DCS bucket. Valid values are **None** and **AES-256**.
5. Click **Create** to create the new logging endpoint.

6. Click **Activate** to deploy your configuration changes.

Example format

The following is an example format string for sending data to Storj DCS. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.start)
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Orig-H
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V",
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(resp.r
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0, "tru
}
```

* * *

Log streaming: Sumo Logic

/en/guides/log-streaming-sumologic

Fastly's Real-Time Log Streaming feature can send log files to Sumo Logic. Sumo Logic is a web-based log analytics platform used by developers and IT teams.


NOTE

Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.


Setting up Sumo Logic

To use Sumo Logic as a logging endpoint, you'll need to create a Sumo Logic account, add a new source, and save the HTTP Source URL. Follow these instructions to add a new source in the Sumo Logic website:


1. The process starts with the Sumo Logic Setup Wizard, which appears immediately after you create your Sumo Logic account. If you already have an account, you can access the wizard by selecting **Setup Wizard** from the **Manage** menu at the top of the Sumo Logic application.




2. Click **Set Up Streaming Data**.



3. Click **All Other Sources**.




4. Click **HTTP Source**.



5. In the **Source Category** field, enter a human-readable name for the category (e.g., `fastly_cdn`) and select a time zone for your log file.

6. Click **Continue**. The HTTP Source URL appears.



7. Copy the HTTP Source URL. You will enter this value in the Fastly control panel.

8. Click **Continue**. Sumo Logic will add the new source.

Adding Sumo Logic as a logging endpoint

After you've created a Sumo Logic account and obtained the HTTP Source URL, follow these instructions to add Sumo Logic as a logging endpoint for Fastly services:

1. Review the information in our guide to setting up remote log streaming.
2. In the Sumo Logic area, click **Create endpoint**.
3. Fill out the **Create a Sumo Logic endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
    - In the **Collector URL** field, enter the address of the HTTP Source URL you found in the Sumo Logic website.
4. *(Optional)* To change the log line format, click **Advanced options**. In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

Example format

The following is an example format string for sending data to Sumo Logic. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.sta
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Or
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
```

```
    "request_referer": "%{json.escape(req.http.referer)}V",
    "request_user_agent": "%{json.escape(req.http.User-Agent)}V"
    "response_state": "%{json.escape(fastly_info.state)}V",
    "response_status": %{resp.status}V,
    "response_reason": %{if(resp.response, "%22"+json.escape(res
    "response_body_size": %{resp.body_bytes_written}V,
    "fastly_server": "%{json.escape(server.identity)}V",
    "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0, "
}
```

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.

2. In the Sumo Logic area, click **Create endpoint**. The Create a Sumo Logic endpoint page appears.

3. Fill out the **Create a Sumo Logic endpoint** fields as follows:
   - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
   - In the **Collector URL** field, enter the address of the HTTP Source URL you found in the Sumo Logic website.

4. *(Optional)* To change the log line format, click **Advanced options**. In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.

5. Click **Create** to create the new logging endpoint.

6. Click **Activate** to deploy your configuration changes.

Troubleshooting

The Sumo Logic logging endpoint is designed for services with sustained levels of traffic. If you aren't seeing any logs in Sumo Logic, try waiting a bit.

* * *

Log streaming: Syslog

/en/guides/log-streaming-syslog

Fastly's Real-Time Log Streaming feature can send log files to syslog-based logging software. Syslog is a widely used standard for message logging.

> NOTE
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Adding syslog as a logging endpoint

Follow these instructions to add syslog as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. In the Syslog area, click **Create endpoint**.
3. Fill out the **Create a Syslog endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.
    - In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
    - In the **Syslog address** field, enter the domain name or IP address and port to which logs should be sent. Be sure this port can receive incoming TCP traffic from Fastly. See the firewall considerations section for more information.
    - *(Optional)* In the **Token** field, enter a string prefix (line prefix) to send in front of each log line.

> **IMPORTANT**
>
> To send a token, be sure the log line format is set to a format other than **Blank**.

- From the **TLS** menu, select **No** to disable encryption for the syslog endpoint, or **Yes** to enable it. When you select Yes, additional TLS fields appear.
- In the **TLS hostname** field, optionally enter a hostname to verify the logging destination server's certificate. This should be one of the Subject Alternative Name (SAN) fields for the certificate. Common Names (CN) are not supported. This field only appears when you select Yes from the Use TLS menu.
- *(Optional)* In the **TLS CA certificate** field, copy and paste the certification authority (CA) certificate used to verify that the origin server's certificate is valid. The certificate you upload must be in PEM format. Consider uploading the certificate if it's not signed by a well-known certification authority. This value is not required if your TLS certificate is signed by a well-known authority. This field only appears when you select Yes from the Use TLS menu.
- *(Optional)* In the **TLS client certificate** field, copy and paste the TLS client certificate used to authenticate to the origin server. The TLS client certificate you upload must be in PEM format and must be accompanied by a client certificate. A TLS client certificate allows your server to authenticate that Fastly is performing the connection. This field only appears when you select Yes from the Use TLS menu.
- *(Optional)* In the **TLS client key** field, copy and paste the TLS client key used to authenticate to the backend server. The TLS client key you upload must be in PEM format and must be accompanied by a TLS client certificate. A TLS client key allows your server to authenticate that Fastly is performing the connection. This field only appears when you select Yes from the Use TLS menu.

4. *(Optional)* To change the log line format, click **Advanced options**. In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information. This must be compatible with your Syslog configuration.
5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

Example format

The following is an example format string for sending data to syslog. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.start)
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Orig-H
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V",
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(resp.r
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0, "tru
}
```

Adding separators or static strings

To insert a separator or other arbitrary string into the syslog endpoint format:

1. Create a new header with the following fields:
   - From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
   - In the **Destination** field, enter any suitable header name (for example, `http.X-Separator`).
   - In the **Source** field, enter any special character or string you want (for example, `"|"`).
2. Reference the new header variable in the log format box for your specific provider (for example, `req.http.X-Separator`).

1. Review the information in our guide to setting up remote log streaming for Compute. Additionally, our developer documentation provides more information about logging with Compute code written in our supported languages.

2. In the Syslog area, click **Create endpoint**.

3. Fill out the **Create a Syslog endpoint** fields as follows:
    - In the **Name** field, enter the endpoint name you specified in your Compute code. For example, in our Rust code example, the name is `my_endpoint_name`.
    - In the **Syslog address** field, enter the domain name or IP address and port to which logs should be sent. Be sure this port can receive incoming TCP traffic from Fastly. Check out the firewall considerations section for more information.
    - *(Optional)* In the **Token** field, enter a string prefix (line prefix) to send in front of each log line.

      > IMPORTANT
      >
      > To send a token, be sure the log line format is set to a format other than **Blank**.

    - From the **TLS** menu, select **No** to disable encryption for the syslog endpoint, or **Yes** to enable it. When you select Yes, additional TLS fields appear.
    - In the **TLS hostname** field, optionally enter a hostname to verify the logging destination server's certificate. This should be one of the Subject Alternative Name (SAN) fields for the certificate. Common Names (CN) are not supported. This field only appears when you select Yes from the Use TLS menu.
    - *(Optional)* In the **TLS CA certificate** field, copy and paste the certification authority (CA) certificate used to verify that the Syslog server's certificate is valid. The certificate you upload must be in PEM format. Consider uploading the certificate if it's not signed by a well-known certification authority. This value is not required if your TLS certificate is signed by a well-known authority. This field only appears when you select Yes from the Use TLS menu.
    - *(Optional)* In the **TLS client certificate** field, copy and paste the TLS client certificate used to authenticate Fastly to the Syslog server. The TLS client certificate you upload must be in PEM format and must be accompanied by a client key. A TLS client certificate allows your Syslog server to authenticate

that Fastly is performing the connection. This field only appears when you select Yes from the Use TLS menu.

- *(Optional)* In the **TLS client key** field, copy and paste the TLS client key used to authenticate Fastly to the Syslog server. The TLS client key you upload must be in PEM format and must be accompanied by a TLS client certificate. A TLS client key allows your Syslog server to authenticate that Fastly is performing the connection. This field only appears when you select Yes from the Use TLS menu.

4. *(Optional)* To change the log line format, click **Advanced options**. In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information. This must be compatible with your Syslog configuration.
5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

Recommended log format

Log messages can take on any format you choose because the log line format selected above will affect the overall line sent to and parsed by Syslog.

Syslog facility and severity

The syslog output includes the following facility and severity values:

```
facility: local0
severity: info
```

Firewall considerations

Syslog has limited security features. For this reason, it's best to create a firewall for your syslog server and only accept TCP traffic on your configured port from our address blocks. Our list of IP address blocks is dynamic, so we recommend programmatically obtaining the list whenever possible.

---

* * *

Log streaming: Wasabi Hot Cloud Storage

/en/guides/log-streaming-wasabi-hot-cloud-storage

Fastly's Real-Time Log Streaming feature can send log files to Wasabi Hot Cloud Storage using Wasabi's S3-compatible API connectivity option. Wasabi Hot Cloud Storage is a static file storage service used by developers and IT teams.

> NOTE
>
> Fastly does not provide direct support for third-party services. Read Fastly's Terms of Service for more information.

Prerequisites

Before adding Wasabi Hot Cloud Storage as a logging endpoint for Fastly services, we recommend creating an Access Key to which you've given read and write permissions on the bucket.

Adding Wasabi Hot Cloud Storage as a logging endpoint

> NOTE
>
> This logging endpoint is only available for Fastly's Deliver (VCL-based) services, not for Compute services.

After you've registered for an Wasabi Hot Cloud Storage account and created an Access Key, follow these instructions to add Wasabi Hot Cloud Storage as a logging endpoint:

1. Review the information in our guide to setting up remote log streaming.
2. Click the Amazon Web Services S3 logo.
3. Fill out the **Create an Amazon S3 endpoint** fields as follows:
    - In the **Name** field, enter a human-readable name for the endpoint.
    - In the **Placement** area, select where the logging call should be placed in the generated VCL. Valid values are **Format Version Default** and **None**. Read our guide on changing log placement for more information.

- In the **Log format** field, optionally enter an Apache-style string or VCL variables to use for log formatting. Consult the example format section for details.
- *(Optional)* In the **Timestamp format** field, enter a timestamp format for log files. The default is an `strftime` compatible string. Our guide on changing where log files are written provides more information.
- In the **Bucket name** field, enter the name of the Wasabi Hot Cloud Storage bucket in which to store the logs.
- In the **Access method** area, select **User Credentials**.
- In the **Access key** field, enter the access key associated with the Wasabi account. See Wasabi's Access Key Guide for more information.
- In the **Secret key** field, enter the secret key associated with the Wasabi account. See Wasabi's Access Key Guide for more information.
- *(Optional)* In the **Period** field, enter an interval (in seconds) to control how frequently your log files are rotated. Rotation entails the finalization of one file object and the start of a new one, never removing any previously created file object. This value defaults to `3600` seconds.

4. Click **Advanced options** and fill out the fields as follows:
   - *(Optional)* In the **Path** field, enter the path within the bucket to store the files. The path ends with a trailing slash. If this field is left empty, the files will be saved in the bucket's root path. Our guide on changing where log files are written provides more information.
   - In the **Domain** field, enter `s3.wasabisys.com`.
   - *(Optional)* In the **PGP public key** field, enter a PGP public key that Fastly will use to encrypt your log files before writing them to disk. You will only be able to read the contents by decrypting them with your private key. The PGP key should be in PEM (Privacy-Enhanced Mail) format. Read our guide on log encryption for more information.
   - In the **Select a log line format** area, select the log line format for your log messages. Our guide on changing log line formats provides more information.
   - *(Optional)* In the **Compression** field, select the compression format you want applied to the log files. Our guide on changing log compression options provides more information.

- The **Redundancy level** option is not useful as Wasabi only provides a single storage class which is most like the standard AWS S3 storage class. Wasabi's Object Storage Class documentation provides more information on using reduced redundancy storage.
- *(Optional)* In the **Server side encryption** area, select an encryption method to protect files that Fastly writes to your Wasabi Hot Cloud Storage bucket. Valid values are **None** and **AES-256**. See Wasabi's guide to this feature which is functionally identical to Amazon's implementation except for lack of support for a key management service.

5. Click **Create** to create the new logging endpoint.
6. Click **Activate** to deploy your configuration changes.

> **NOTE**
>
> Although Fastly continuously streams logs into Wasabi, the Wasabi website and API do not make files available for access until after their upload is complete.

Example format

The following is an example format string for sending data to Wasabi. Our discussion of format strings provides more information.

```
{
  "timestamp": "%{strftime(\{"%Y-%m-%dT%H:%M:%S%z"\}, time.sta
  "client_ip": "%{req.http.Fastly-Client-IP}V",
  "geo_country": "%{client.geo.country_name}V",
  "geo_city": "%{client.geo.city}V",
  "host": "%{if(req.http.Fastly-Orig-Host, req.http.Fastly-Ori
  "url": "%{json.escape(req.url)}V",
  "request_method": "%{json.escape(req.method)}V",
  "request_protocol": "%{json.escape(req.proto)}V",
  "request_referer": "%{json.escape(req.http.referer)}V",
  "request_user_agent": "%{json.escape(req.http.User-Agent)}V
  "response_state": "%{json.escape(fastly_info.state)}V",
  "response_status": %{resp.status}V,
  "response_reason": %{if(resp.response, "%22"+json.escape(res
  "response_body_size": %{resp.body_bytes_written}V,
  "fastly_server": "%{json.escape(server.identity)}V",
  "fastly_is_edge": %{if(fastly.ff.visits_this_service == 0,
```

```
17  }
18
```

* * *

Category: Non-Fastly services

These articles describe how non-Fastly services interoperate with Fastly.

Alibaba Object Storage Service

/en/guides/alibaba-object-storage-service


Alibaba Object Storage Service (OSS) can be used as an origin for Fastly for both public and private content.

Using OSS as an origin

To use OSS as an origin, follow the steps below.

Setting up and configuring your OSS account

1. Sign up for Alibaba Object Storage Service.
2. Create a bucket to store your origin's data.


Create Bucket
Create a bucket
Note: Storage Class and Region cannot be changed after the bucket is created.
Bucket Name
0/63
Region
China (Beijing)
Alibaba Cloud services in the same region can communicate with each other over an internal network. The region cannot be changed after the purchase. Exercise caution when you select a region.
Endpoint
oss-cn-beijing.aliyuncs.com
Storage Class
Standard
IA
Archive
Standard: high reliability, high availability, and high performance. Data of this type is frequently accessed.
How to Choose a Suitable Storage Class
Zone-redundant Storage
Hot
Enable
Disable
OSS can back up your data to three zones within the same region to provide data center disaster recovery. Learn more.
Zone-redundant storage improves the availability of data. This feature incurs extra costs. For more information about the pricing of this feature, visit price details. This feature cannot be disabled after it is enabled.
Versioning
Hot
Enable
Disable
After versioning is enabled for a bucket, data that is overwritten or deleted is saved as a previous version. Learn more.
Access Control List (ACL)
Private
Public Read
Public Read/Write
Private: Only the owner or authorized users of this bucket can read
OK
Cancel


3. Fill out the **Create Bucket** fields as follows:

    - In the **Bucket Name** field, enter a name for your bucket. Remember the name you enter. You'll need it to connect your bucket to your Fastly service.
    - From the **Region** menu, select a location to store your content. Most customers select a region close to the POP they specify for shielding.
    - From the **Storage Class** options, select **Standard**.
    - From the **Access Control List (ACL)** options, select **Public Read**.
    - *(Optional)* Select other options, such as **Server-side Encryption** and **Scheduled Backup**.

4. Click **OK**.

Uploading files to your bucket

Once you've created your bucket, select it and then navigate to the Files tab to add files to it by clicking **Upload**.



You can make the files externally accessible by selecting the **Public Read** option for the bucket or you can use the **Inherited from Bucket** option next to each of the files.

Setting up Fastly to use OSS as an origin

To add your OSS bucket as an origin, follow the instructions for working with hosts. You'll add specific details about your origin server.

1. On the **Origins** page, click **Create Host** and enter the appropriate address for your Host using the format `<BUCKET>.<REGION>.aliyuncs.com`. For example, if your bucket name is `test123` and your region is Beijing (e.g., `oss-cn-beijing`) your hostname would be `test123.oss-cn-beijing.aliyuncs.com`. You can also find the hostname on the Bucket Overview page in the **Bucket Domain Name** area.
2. Click on the newly created Host to edit it.
3. In the **Name** field, enter a descriptive name for your service (e.g., `Alibaba Object Storage`).
4. If the **Address** field doesn't contain the `<BUCKET>.<REGION>.aliyuncs.com` hostname you provided in the first step, enter it now.
5. Fill out the **Transport Layer Security (TLS)** area fields as follows:
   - Leave the **Enable TLS?** default set to **Yes** to secure the connection between Fastly and your origin.
   - Leave the **Verify certificate?** default set to **Yes**.
   - Set the **Certificate hostname** field to the same address that appears in the Address field (e.g., `test123.oss-cn-beijing.aliyuncs.com`).
   - In the **SNI hostname** field, select the checkbox to **Match the SNI hostname to the Certificate hostname**. The hostname address you entered during Host creation appears.
6. From the **Shielding** menu below the TLS area, select a Fastly POP near the Alibaba region from the list of shielding locations.
7. In the **Override host** field, enter an appropriate address for your Host (e.g., `test123.oss-cn-beijing.aliyuncs.com`). You entered this information during Host creation.

Review our caveats of shielding and select a shield POP accordingly.

Using OSS with private objects


To use Fastly with OSS private objects, be sure you've already made your OSS data available to Fastly by pointing to the right OSS bucket, then follow the steps below.

Setting up a private bucket and sub user

Setting up a private bucket is the same as setting up a public bucket, except you select the **Private** option in the **Access Control List (ACL)** area of the OSS bucket settings.

You'll need an **AccessKey ID** and **Access Key Secret**. These can be linked to your account by clicking on your avatar in the top right corner of the Alibaba Cloud Console, selecting **Access Key**, and then creating a new key. Since this key has full access to the account, we recommend following Alibaba's procedure for creating a sub user. Follow the steps below.

1. Navigate to the Resource Access Management (RAM) page.
2. Click **Users**.
3. Click **Create User**.
4. Enter an appropriate **Logon Name** and **Display Name**.
5. Select the **Programmatic Access** checkbox to enable access through the Alibaba API.



6. Click **OK**.
7. Copy the **AccessKeyId** and **AccessKeySecret**. You'll need these later when you're creating an Authorization header.
8. Go back to the bucket overview, click **Files** and then click **Authorize**. You should see a list of authorized users. If this is a new bucket it should be empty.
9. Click **Authorize**, filling out the fields as follows:
    - From the **Applied To** menu, select the **Whole Bucket** option. You can select **Specified Resources**, but this may lead to unexpected errors later if you don't update the permissions with new files.


- From the **Accounts** menu, select **RAM Users** and then use the menu to select your newly created RAM user.
- From the **Authorized Operation** menu, select **Read Only**.
- You can leave **Condition** blank or customize it using **IP =**, Fastly's IP ranges, or setting **Access Method** to **HTTPS**.

Setting up Fastly to use OSS private content

To use OSS private content with Fastly, you'll need to create two headers: a Date header (required for authorization signature) and a Host header. You'll also need to add some authorization parameters.

Creating a Date header

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click **Create header**.



6. Fill out the **Create a new header** fields as follows:
    - In the **Name** field, enter `Date`.
    - From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
    - In the **Destination** field, enter `http.Date`.

- In the **Source** field, enter `var.ali_expires`.
- From the **Ignore if set** menu, select **No**.
- In the **Priority** field, enter `19`.


7. Click **Create**. A new Date header appears on the Content page. You will use this later within the signature of the Authorization header.

Creating a Host header

1. Click **Create header**.
2. Fill out the **Create a new header** fields as follows:
   - In the **Name** field, enter `Date`.
   - From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
   - In the **Destination** field, enter `http.Host`.
   - In the **Source** field, enter `"<your OSS domain>"`.
   - From the **Ignore if set** menu, select **No**.
   - In the **Priority** field, enter `19`.
3. Click **Create**. A new Host header appears on the Content page.

Creating the Authorization header

1. Click **Create header** again to create another new header.



2. Fill out the **Create a header** fields as follows:
    - In the **Name** field, enter `Authorization`.
    - From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
    - In the **Destination** field, enter `url`.
    - From the **Ignore if set** menu, select **No**.
    - In the **Priority** field, enter `20`.
3. In the **Source** field, enter the Authorization header information using the following format:

```
req.url.path "?" "OSSAccessKeyId=<AccessKeyId>" "&" "Signature= ig
```

Replace `<AccessKeyId>`, `<AccessKeySecret>`, and `<OSS bucket name>` with the information you gathered before you began. For example:

```
req.url.path "?" "OSSAccessKeyId=AOSSdecafbad" "&" "Signature=" le
```

4. Click **Create**. A new Authorization header appears on the Content page.
5. Click **Activate** to deploy your configuration changes.

Setting up Fastly to use OSS private content using VCL Snippets

You can also put the configuration in a VCL Snippet with a priority of `20`.

```
declare local var.ali_bucket STRING;
declare local var.ali_region STRING;
declare local var.ali_access_key_id STRING;
declare local var.ali_access_key_secret STRING;
declare local var.ali_expires INTEGER;
declare local var.ali_canon STRING;
declare local var.ali_sig STRING;_

set var.ali_bucket = "test123";
set var.ali_region = "oss-cn-beijing";
set var.ali_access_key_id = "decafbad";
set var.ali_access_key_secret = "deadbeef";
set var.ali_expires  = std.atoi(now.sec);
set var.ali_expires += 60;


set req.http.Host = var.ali_bucket "." + var.ali_region + ".aliy
set req.http.Date = var.ali_expires;
set var.ali_canon = if(req.method == "HEAD", "GET", req.method)
                    req.http.Date LF "/" var.ali_bucket req.url.
set var.ali_sig   = digest.hmac_sha1_base64(var.alibaba_access_k

```

```
set req.url       = req.url.path;
set req.url       = querystring.set(req.url, "OSSAccessKeyId", v
set req.url       = querystring.set(req.url, "Signature",  var.a
set req.url       = querystring.set(req.url, "Expires",  var.ali

```

> **NOTE**
>
> This article describes how to configure an integration with a service provided by a third party. As stated in our Terms of Service, we do not provide direct support for non-Fastly services.

* * *

	Amazon S3
🔗	/en/guides/amazon-s3

Amazon S3 public and private buckets can be used as origins with Fastly.

Using Amazon S3 as an origin

To make your S3 data buckets available through Fastly, follow the steps below.

Creating a new service

Follow the instructions for creating a new service.

1. When you create the new domain and the new Host:
    - In the **Domain Name** field on the **Create a domain** page, enter the hostname you want to use as the URL (e.g., `cdn.example.com`).
    - In the **Hosts** field on the **Origins** page, enter the appropriate address for your Host using the format `<BUCKET>.s3.<REGION>.amazonaws.com`. Use the table in the Amazon S3 endpoints of the AWS general reference documentation as a guide. For example, if your bucket name is `fastlytestbucket` and your region is

`us-east-2`, your hostname would be `fastlytestbucket.s3.us-east-2.amazonaws.com`.

> **TIP**
>
> Most customers select a region close to the interconnect location they specify for shielding.

2. When you edit the Host details on the **Edit this host page**:
    - In the **Name** field, enter any descriptive name for your service if you haven't already done so.
    - In the **Address** field, ensure you've entered the appropriate address for your region (e.g., `fastlytestbucket.s3.us-east-2.amazonaws.com`). You entered this information during Host creation.
3. When you edit the Transport Layer Security (TLS) area information for your Host:
    - Leave the **Enable TLS?** default set to **Yes** to secure the connection between Fastly and your origin.

      > **TIP**
      >
      > If you're using Amazon S3 to host a static website, **Enable TLS?** should be set to **No** instead of relying on the default. Amazon doesn't support TLS connections to S3 buckets with the static website hosting feature enabled. You can still use one of Fastly's TLS service options to secure connections between Fastly and clients.

    - Under the **SNI hostname** field, select the checkbox to **Match the SNI hostname to the Certificate hostname**. The address you entered during Host creation appears.
    - In the **Certificate hostname** field, enter `fastlytestbucket.s3.us-east-2.amazonaws.com`.
4. In the **Override host** field, enter an appropriate address for your Host (e.g., `fastlytestbucket.s3.us-east-2.amazonaws.com`). You entered this information during Host creation. If you're using an Amazon S3 private bucket leave this field blank.

Validating the DNS mapping

By default, we create a DNS mapping called **yourdomain.global.prod.fastly.net**. In the example above, it would be `cdn.example.com.global.prod.fastly.net`. Enter this URL

in a browser to confirm it's working.

Creating a DNS alias

Create a DNS alias for the domain name you specified (e.g., CNAME `cdn.example.com` to `global-nossl.fastly.net`).

Verifying your results

Fastly will cache any content without an explicit `Cache-Control` header for 1 hour. You can verify whether you are sending any cache headers using curl. For example:

```
$ curl -I opscode-full-stack.s3.amazonaws.com

HTTP/1.1 200 OK
x-amz-id-2: ZpzRp7IWc6MJ8NtDEFGH12QBdk2CM1+RzVOngQbhMp2f2ZyalkFsZd4qPaLM
x-amz-request-id: ABV5032583242618
Date: Fri, 18 Mar 2012 17:15:38 GMT
Content-Type: application/xml
Transfer-Encoding: chunked
Server: AmazonS3
```

In this example, no Cache-Control headers are set so the default Time to Live (TTL) will be applied.

Enhanced cache control

If you need more control over how different types of assets are cached (e.g., JavaScript files, images), check out our documentation on cache freshness.

Using an Amazon S3 private bucket

To use an Amazon S3 private bucket with Fastly, you must implement version 4 of Amazon's header-based authentication. You can do this using custom VCL. Start by obtaining the following information from AWS:

Item	Description
Bucket name	The name of your AWS S3 bucket. When you download items from your bucket, this is the string listed in the URL path or hostname of each object.
Region	The AWS region code of the location where your bucket resides (e.g., `us-east-1`).
Access key	The AWS access key string for an IAM account that has at least read permission on the bucket.
Secret key	The AWS secret access key paired with the access key above.

Once you have this information, you can configure your Fastly service to authenticate against your S3 bucket using header authentication by calculating the appropriate header value in VCL.

IMPORTANT

Consider leaving the **Override host** field for the origin blank in your service settings. This setting will override the Host header from the snippets shown here and may invalidate the signature that authenticates the information being sent.

Start by creating a regular VCL snippet. Give it a meaningful name, such as `AWS protected origin`. When you create the snippet, select **within subroutine** to specify its placement and choose **miss** as the subroutine type. Then, populate the **VCL** field with the following code (be sure to change specific values as noted to ones relevant to your own AWS bucket):

```
declare local var.awsAccessKey STRING;
declare local var.awsSecretKey STRING;
declare local var.awsS3Bucket STRING;
declare local var.awsRegion STRING;
declare local var.awsS3Host STRING;
declare local var.canonicalHeaders STRING;
declare local var.signedHeaders STRING;
declare local var.canonicalRequest STRING;
declare local var.canonicalQuery STRING;
declare local var.stringToSign STRING;
declare local var.dateStamp STRING;
```

```
declare local var.signature STRING;
declare local var.scope STRING;

set var.awsAccessKey = "YOUR_AWS_ACCESS_KEY";   # Change this va
set var.awsSecretKey = "YOUR_AWS_SECRET_KEY";   # Change this va
set var.awsS3Bucket = "YOUR_AWS_BUCKET_NAME";   # Change this va
set var.awsRegion = "YOUR_AWS_BUCKET_REGION";   # Change this va
set var.awsS3Host = var.awsS3Bucket ".s3." var.awsRegion ".amazo

if (req.method == "GET" && !req.backend.is_shield) {

  set bereq.http.x-amz-content-sha256 = digest.hash_sha256("");
  set bereq.http.x-amz-date = strftime({"%Y%m%dT%H%M%SZ"}, now);
  set bereq.http.host = var.awsS3Host;
  set bereq.url = querystring.remove(bereq.url);
  set bereq.url = regsuball(urlencode(urldecode(bereq.url.path))
  set var.dateStamp = strftime({"%Y%m%d"}, now);
  set var.canonicalHeaders = ""
    "host:" bereq.http.host LF
    "x-amz-content-sha256:" bereq.http.x-amz-content-sha256 LF
    "x-amz-date:" bereq.http.x-amz-date LF
  ;
  set var.canonicalQuery = "";
  set var.signedHeaders = "host;x-amz-content-sha256;x-amz-date"
  set var.canonicalRequest = ""
    "GET" LF
    bereq.url.path LF
    var.canonicalQuery LF
    var.canonicalHeaders LF
    var.signedHeaders LF
    digest.hash_sha256("")
  ;

  set var.scope = var.dateStamp "/" var.awsRegion "/s3/aws4_requ

  set var.stringToSign = ""
    "AWS4-HMAC-SHA256" LF
    bereq.http.x-amz-date LF
    var.scope LF
    regsub(digest.hash_sha256(var.canonicalRequest),"^0x", "")
```

```
  ;

  set var.signature = digest.awsv4_hmac(
    var.awsSecretKey,
    var.dateStamp,
    var.awsRegion,
    "s3",
    var.stringToSign
  );

  set bereq.http.Authorization = "AWS4-HMAC-SHA256 "
    "Credential=" var.awsAccessKey "/" var.scope ", "
    "SignedHeaders=" var.signedHeaders ", "
    "Signature=" + regsub(var.signature,"^0x", "")
  ;
  unset bereq.http.Accept;
  unset bereq.http.Accept-Language;
  unset bereq.http.User-Agent;
  unset bereq.http.Fastly-Client-IP;
}

```

You may also remove the headers that AWS adds to the response. Do this by creating another VCL snippet. Give it a meaningful name, such as `Strip AWS response headers`. When you create the snippet, select **within subroutine** to specify its placement and choose **fetch** as the subroutine type. Then, place the following code in the **VCL** field:

```
unset beresp.http.x-amz-id-2;
unset beresp.http.x-amz-request-id;
unset beresp.http.x-amz-delete-marker;
unset beresp.http.x-amz-version-id;


```

Following redirects to S3 objects and caching S3 responses

Using VCL Snippets, Fastly can follow redirects to S3 objects and cache the response.

To configure Fastly to follow redirects to S3 objects, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **VCL Snippets**.
5. Click **Create snippet**.



6. In the **Name** field, enter an appropriate name (e.g., `S3 redirect - recv`).
7. From the **Type (placement of the snippet)** controls, select **within subroutine**.

8. From the **Select subroutine** menu, select **recv (`vcl_recv`)**.


9. In the **VCL** field, add the following condition:

```
if (req.http.redir != "true") {
  set req.backend = Main_Origin;
} else {
  set req.backend = s3_backend;
  set req.http.host = "s3.amazonaws.com";
}
```

> **IMPORTANT**
>
> In the condition above, be sure to replace the `Main_Origin` and `s3_backend` placeholders with the actual names of your backends in the service to which you're applying these redirects. You can find the exact names by navigating to the **Deliver** page and clicking **Show VCL**, which appears just beneath your service name while viewing that service.

10. Click **Create** to create the snippet.

11. Click **Create snippet** again.



12. In the **Name** field, enter an appropriate name (e.g., `S3 redirect - deliver`).
13. From the **Type (placement of the snippet)** controls, select **within subroutine**.
14. From the **Select subroutine** menu, select **deliver (`vcl_deliver`)**.
15. In the **VCL** field, add the following condition:

```
if (resp.status == 302 || resp.status == 301) {
  set req.http.redir = "true";
  set req.url = regsub(resp.http.Location, "http://s3.amazor
  set req.http.Fastly-Force-Shield = "yes";
  restart;

```

```
6 }
```

16. Click **Create** to create the snippet.
17. Click **Activate** to deploy your configuration changes.

> **NOTE**
>
> This article describes how to configure an integration with a service provided by a third party. As stated in our Terms of Service, we do not provide direct support for non-Fastly services.

* * *

	AWS CLI for Fastly Object Storage
🔗	/en/guides/aws-cli-for-fastly-object-storage

The Amazon Web Services (AWS) CLI can be configured to use Fastly Object Storage as an S3 backend.

Prerequisites

1. Install AWS CLI v2. Refer to the AWS documentation for more information.
2. If you haven't already, purchase Fastly Object Storage.
3. Create an Access Key and Secret Key for Fastly Object Storage.

Configure AWS CLI for Fastly Object Storage

1. Create or update the AWS CLI config file for your platform.

```
~/.aws/config
```

```
C:\Users\USERNAME\.aws\config
```

The config file contains AWS CLI Profiles.

Each Fastly Object Storage region should be added as an individual profile for AWS CLI. These profiles can be named whatever you would like, but below we include the Fastly Object Storage region in the profile name to make it clear which region is associated with which profile.

The config file for your system should have the following added to it:

```
[profile fastly-us-east]
region = us-east
endpoint_url = https://us-east.object.fastlystorage.app
request_checksum_calculation = when_required

[profile fastly-us-west]
region = us-west
endpoint_url = https://us-west.object.fastlystorage.app
request_checksum_calculation = when_required

[profile fastly-eu-central]
region = eu-central
endpoint_url = https://eu-central.object.fastlystorage.app
request_checksum_calculation = when_required
```

2. Create or update the *credentials* file for your platform

```
~/.aws/credentials
```

```
C:\Users\USERNAME\.aws\credentials
```

The credentials file contains the Fastly Object Storage access credentials associated with a like-named profile in the config file.

WARNING

The following steps will store your Fastly Object Storage credentials in plaintext in a file on disk. This is not recommended in a production environment.

For production environments, AWS CLI supports other methods of providing credentials such as through environment variables or from external tooling such as a password manager.

To do this for the example profiles above, we must edit the credentials file and add the following:

```
[fastly-us-east]
aws_access_key_id = <YOUR FASTLY OBJECT STORAGE ACCESS KEY ID HERE>
aws_secret_access_key = <YOUR FASTLY OBJECT STORAGE SECRET KEY HERE>

[fastly-us-west]
aws_access_key_id = <YOUR FASTLY OBJECT STORAGE ACCESS KEY ID HERE>
aws_secret_access_key = <YOUR FASTLY OBJECT STORAGE SECRET KEY HERE>

[fastly-eu-central]
aws_access_key_id = <YOUR FASTLY OBJECT STORAGE ACCESS KEY ID HERE>
aws_secret_access_key = <YOUR FASTLY OBJECT STORAGE SECRET KEY HERE>
```

The AWS CLI is now ready to be used with Fastly Object Storage.

Basic AWS CLI Commands

The following provides a sample of common commands to interact with Fastly Object Storage via the AWS CLI.

TIP

Note the use of the `--profile` flag to choose which Fastly Object Storage region to perform commands against.

Create a bucket named `photos` in the `us-east` region:

```
$ aws s3 mb s3://photos --profile fastly-us-east
```

Upload a local file called `sunset.png` to the `photos` bucket:

```
$ aws s3 cp sunset.png s3://photos/sunset.png --profile fastly-us-ea
```

Download the object named `sunset.png` from the `photos` bucket to a local file called `sunset-copy.png`:

```
$ aws s3 cp s3://photos/sunset.png sunset-copy.png --profile fastly-e
```

Delete an object named `sunset.png` from the `photos` bucket:

```
$ aws s3 rm s3://photos/sunset.png --profile fastly-us-east
```

Delete the photos bucket (the bucket must be empty before being deleted):

```
$ aws s3 rb s3://photos --profile fastly-us-east
```

Refer to the AWS CLI Documentation for more commands. Refer to Fastly Object Storage's documentation for additional limitations and considerations.

---

* * *

Backblaze B2 Cloud Storage

/en/guides/backblaze-b2-cloud-storage

Backblaze B2 Cloud Storage (B2) public and private buckets can be used as origins with Fastly.

TIP

Backblaze offers an integration discount that eliminates egress costs to Fastly when using Backblaze B2 Cloud Storage as an origin. In addition, Backblaze also offers a migration program designed to offset many of the data transfer costs associated

with switching from another cloud provider to Backblaze. To ensure your migration has minimal downtime, contact support.

Before you begin

Before you begin the setup and configuration steps required to use B2 as an origin, keep in mind the following:

- **You must have a valid Backblaze account.** Before you can create a new bucket and upload files to it for Fastly to use, you must first create a Backblaze account at the Backblaze website.
- **Backblaze provides two ways to set up and configure B2.** B2 can be set up and configured using either the Backblaze web interface or the B2 command line tool. Either creation method works for *public* buckets. To use *private* buckets, however, you must use the B2 command line tool. For additional details, including instructions on how to install the command line tool, read Backblaze's B2 documentation.
- **Backblaze provides two APIs for integrating with Backblaze B2 Cloud Storage.** You can use the B2 Cloud Storage API or the S3 Compatible API to make your B2 data buckets available through Fastly. The S3 Compatible API allows existing S3 integrations and SDKs to integrate with B2. Buckets and their specific application keys created prior to May 4th, 2020, however, cannot be used with the S3 Compatible API. For more information, read Backblaze's article on Getting Started with the S3 Compatible API.

Using Backblaze B2 as an origin

To use B2 as an origin, follow the steps below.

Creating a new bucket

Data in B2 is stored in buckets. Follow these steps to create a new bucket via the B2 web interface.


TIP

The Backblaze Guide provides details on how to create a bucket using the command line tool.

1. Log in to your Backblaze account. Your Backblaze account settings page appears.

2. Click **Buckets**.

3. Click **Create a Bucket**.



4. In the **Bucket Unique Name** field, enter a unique bucket name. Each bucket name must be at least 6 alphanumeric characters and can only use hyphens (`-`) as separators, not spaces.

5. Click **Create a Bucket**. The new bucket appears in the list of buckets on the B2 Cloud Storage Buckets page.

6. Upload a file to the new bucket you just created.

> **NOTE**
>
> Buckets created prior to May 4th, 2020 cannot be used with the S3 Compatible API. If you do not have any S3 Compatible buckets, Backblaze recommends creating a new bucket.

Uploading files to a new bucket

Once you've created a new bucket in which to store your data, follow these steps to upload files to it via the B2 web interface.

> **TIP**

The Backblaze Guide provides details on how to upload files using the command line tool.


1. Click **Buckets** in the B2 web interface. The B2 Cloud Storage Buckets page appears.
2. Find the bucket details for the bucket you just created.
3. Click **Upload/Download**.
4. Click **Upload**.
5. Either drag and drop any file into the window or click to use the file selection tools to find a file to be uploaded. The name and type of file at this stage doesn't matter. Any file will work. Once uploaded, the name of the file appears in the list of files for the bucket.
6. Find your bucket's assigned hostname so you can set up a Fastly service that interacts with B2.

Finding your bucket's assigned hostname

To set up a Fastly service that interacts with your B2, you will need to know the hostname Backblaze assigned to the bucket you created and uploaded files to.


Find your hostname in one of the following ways:

- **Via the B2 web interface when you're using the standard B2 Cloud Storage API.** Click the name of the file you just uploaded and examine the **Friendly URL** and **Native URL** fields in the Details window that appears. The hostname is the text after the `https://` designator in each line that matches exactly.



- **Via the command line and the B2 Cloud Storage API.** Run the `b2 get-account-info` command on the command line and use the hostname from the `downloadUrl` attribute.

- **Via the B2 web interface when you're using the S3 Compatible API.** Click **Buckets** and find the bucket details for the bucket you just created. The hostname is the text in the Endpoint field.



Creating a Backblaze application key for private buckets


Your Backblaze master application key controls access to all buckets and files on your Backblaze account. If you plan to use a Backblaze B2 *private* bucket with Fastly, you should create an application key specific to the bucket.

> NOTE
>
> The Backblaze documentation provides more information about application keys. When creating application keys for your private bucket, we recommend using the least amount of privileges possible. You can optionally set the key to expire after a certain number of seconds (up to a maximum of 1000 days or 86,400,000 seconds). If you choose an expiration, however, you'll need to periodically create a new application key and then update your Fastly configuration accordingly each time.

Via the web interface

To create an application key via the B2 web interface:

1. Click **App Keys**.
2. Click **Add a New Application Key**.




3. Fill out the fields of the **Add Application Key** controls as follows:

    - In the **Name of Key** field, enter the name of your private bucket key. Key names are alphanumeric and can only use hyphens (`-`) as separators, not spaces.
    - From the **Allow access to Bucket(s)** menu, select the name of your private bucket.
    - From the **Type of Access** controls, select **Read Only**.

- Leave the remaining optional controls and fields blank.

4. Click **Create New Key**.



5. Immediately note the **keyID** and the **applicationKey** from the success message. You'll use this information when you implement header-based authentication with private objects.

Via the command line

To create an application key from the command line, run the `create-key` command as follows:

```
$ b2 create-key --bucket <bucketName> <keyName> shareFiles,listBuck
```

where `<bucketName> <keyName>` represents the name of the bucket and key you created. For example:

```
$ b2 create-key --bucket this-is-an-example-bucket Fastly-Private-B et
```

The **keyID** and the **applicationKey** are the two values returned.

> **NOTE**
>
> Application keys created prior to May 4th, 2020 cannot be used with the S3 Compatible API.

Creating a new service

To create a new Fastly service, you must first create a new domain and then create a new host and edit it to accept traffic for B2. Instructions to do this appear in our guide to creating a new service. While completing these instructions, keep the following in mind:

1. When you create the new host, enter the B2 bucket's hostname in the **Hosts** field on the **Origins** page.
2. When you edit the host details on the **Edit this host page**, confirm the Transport Layer Security (TLS) area information for your host. Specifically, make sure you:
    - secure the connection between Fastly and your origin.
    - enter your bucket's hostname in the **Certificate hostname** field.
    - select the checkbox to match the SNI hostname to the Certificate hostname (it appears under the SNI hostname field).
3. *(Optional)* Also when you edit the host, enable shielding by choosing the appropriate shielding location from the **Shielding** menu. When using B2 Cloud Storage, this means you must choose a shielding location closest to the most appropriate Backblaze data center. For the data centers closest to:
    - Sacramento, California (in the US West region), choose **San Jose (SJC)** from the **Shielding** menu.
    - Phoenix, Arizona (in the US West region), choose **Palo Alto (PAO)** from the **Shielding** menu.
    - Amsterdam, Netherlands (in the EU central region), choose **Amsterdam (AMS)** from the **Shielding** menu.
4. Decide whether or not you should specify an override host:
    - If you're using the S3 Compatible API, skip this step and don't specify an override host.
    - If you're not using the S3 Compatible API, in the **Override host** field, enter an appropriate address for your host (e.g., `s3-uswest-000.backblazeb2.com` or `f000.backblazeb2.com`).

Using the S3 Compatible API

Using the S3 Compatible API with public objects

To use the S3 Compatible API with public objects, you will need to make sure the `Host` header contains the name of your B2 Bucket. There are two ways to do this, both of which require you to get your region name which will be the 2nd part of your S3 Endpoint. So if your S3 Endpoint is `s3.us-west-000.backblazeb2.com`, this means your region will be `us-west-000`.

1. In the **Origin** you created set the **Override host** field to `<bucket>.s3.<region>.backblazeb2.com` (e.g., `testing.s3.uswest-000.backblazeb2.com`).

2. Create a VCL Snippet. When you create the snippet, select **within subroutine** to specify its placement and choose **miss** as the subroutine type. Then, populate the **VCL** field with the following code. Be sure to change specific values as noted to ones relevant to your own B2 bucket - in this case `var.b2Bucket` would be `"testing"` and `var.b2Region` would be `"uswest-000"`.

```
declare local var.b2Bucket STRING;
declare local var.b2Region STRING;
set var.b2Bucket = "YOUR_B2_BUCKET_NAME";   # Change this value
set var.b2Region = "YOUR_B2_BUCKET_REGION"; # Change this value

if (req.method == "GET" && !req.backend.is_shield) {
  set bereq.http.host = var.b2Bucket ".s3." var.b2Region ".back
}

```

Using the S3 Compatible API with private objects

To use a Backblaze B2 private bucket with Fastly, you must implement version 4 of Amazon's header-based authentication. You can do this using custom VCL.

Start by obtaining the following information from Backblaze (see Creating a Backblaze application key for private buckets):

Item	Description
Bucket name	The name of your Backblaze B2 bucket. When you download items from your bucket, this is the string listed in the URL path or hostname of each object.

Item	Description
Region	The Backblaze region code of the location where your bucket resides (e.g., `uswest-000`).
Access key	The Backblaze keyID for the App Key that has at least read permission on the bucket.
Secret key	The Backblaze applicationKey paired with the access key above.

Once you have this information, you can configure your Fastly service to authenticate against your B2 bucket using header authentication by calculating the appropriate header value in VCL.

Start by creating a regular VCL snippet. Give it a meaningful name, such as `AWS protected origin`. When you create the snippet, select **within subroutine** to specify its placement and choose **miss** as the subroutine type. Then, populate the **VCL** field with the following code (be sure to change specific values as noted to ones relevant to your own AWS bucket):

```
declare local var.b2AccessKey STRING;
declare local var.b2SecretKey STRING;
declare local var.b2Bucket STRING;
declare local var.b2Region STRING;
declare local var.canonicalHeaders STRING;
declare local var.signedHeaders STRING;
declare local var.canonicalRequest STRING;
declare local var.canonicalQuery STRING;
declare local var.stringToSign STRING;
declare local var.dateStamp STRING;
declare local var.signature STRING;
declare local var.scope STRING;

set var.b2AccessKey = "YOUR_B2_ACCESS_KEY";   # Change this valu
set var.b2SecretKey = "YOUR_B2_SECRET_KEY";   # Change this valu
set var.b2Bucket = "YOUR_B2_BUCKET_NAME";     # Change this valu
set var.b2Region = "YOUR_B2_BUCKET_REGION";   # Change this valu

if (req.method == "GET" && !req.backend.is_shield) {

  set bereq.http.x-amz-content-sha256 = digest.hash_sha256("");
```

```
    set bereq.http.x-amz-date = strftime({"%Y%m%dT%H%M%SZ"}, now);
    set bereq.http.host = var.b2Bucket ".s3." var.b2Region ".backb
    set bereq.url = querystring.remove(bereq.url);
    set bereq.url = regsuball(urlencode(urldecode(bereq.url.path))
    set var.dateStamp = strftime({"%Y%m%d"}, now);
    set var.canonicalHeaders = ""
      "host:" bereq.http.host LF
      "x-amz-content-sha256:" bereq.http.x-amz-content-sha256 LF
      "x-amz-date:" bereq.http.x-amz-date LF
    ;
    set var.canonicalQuery = "";
    set var.signedHeaders = "host;x-amz-content-sha256;x-amz-date"
    set var.canonicalRequest = ""
      "GET" LF
      bereq.url.path LF
      var.canonicalQuery LF
      var.canonicalHeaders LF
      var.signedHeaders LF
      digest.hash_sha256("")
    ;

    set var.scope = var.dateStamp "/" var.b2Region "/s3/aws4_reque

    set var.stringToSign = ""
      "AWS4-HMAC-SHA256" LF
      bereq.http.x-amz-date LF
      var.scope LF
      regsub(digest.hash_sha256(var.canonicalRequest),"^0x", "")
    ;

    set var.signature = digest.awsv4_hmac(
      var.b2SecretKey,
      var.dateStamp,
      var.b2Region,
      "s3",
      var.stringToSign
    );

    set bereq.http.Authorization = "AWS4-HMAC-SHA256 "
      "Credential=" var.b2AccessKey "/" var.scope ", "
```

```
    "SignedHeaders=" var.signedHeaders ", "
    "Signature=" + regsub(var.signature,"^0x", "")
  ;
  unset bereq.http.Accept;
  unset bereq.http.Accept-Language;
  unset bereq.http.User-Agent;
  unset bereq.http.Fastly-Client-IP;
}


```

Using the B2 API

Public Objects

You'll need to make sure the URL contains your bucket name. You can do this using a **Header** object as follows:

1. Click **Create header** again to create another new header.



2. Fill out the **Create a header** fields as follows:
    - In the **Name** field, enter `Rewrite B2 URL`.
    - From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
    - In the **Destination** field, enter `url`.
    - From the **Ignore if set** menu, select **No**.
    - In the **Priority** field, enter `20`.
3. In the **Source** field, enter `"/file/<Bucket Name>" req.url`.
4. Click **Create**. A new Authorization header appears on the Content page.
5. Click **Activate** to deploy your configuration changes.

Alternatively create a VCL Snippet. When you create the snippet, select **within subroutine** to specify its placement and choose **miss** as the subroutine type. Then, populate the **VCL** field with the following code. Be sure to change the variable to the name of your own B2 bucket.

```
declare local var.b2Bucket STRING;
set var.b2Bucket = "YOUR_B2_BUCKET_NAME";   # Change this value to

if (req.method == "GET" && !req.backend.is_shield) {
  set bereq.url = "/file/" var.b2Bucket bereq.url;
}

```

Private Objects

1. To use a Backblaze B2 private bucket with Fastly, you must obtain an `Authorization Token`. This must be obtained via the command line.
2. You'll now need to authorize the command line tool with the application key you obtained.

```
$ b2 authorize-account <keyID> <applicationKey>
```

3. You will now need to get an authorization token for the private bucket.

```
$ b2 get-download-auth <bucket>
```

e.g.,

```
$ b2 get-download-auth testing
```

This will create a token that is valid for 86400 seconds (i.e 1 day), the default. You can optionally change the expiration time from anywhere between 1s and 604,800 seconds (i.e 1 week).

```
$ b2 get-download-auth --duration 604800 testing
```


Take note of the generated token.

> **NOTE**
>
> You will need to regenerate an authorization token and update your Fastly configuration before the end of the expiration time. A good way to do this would be through Fastly's versionless dictionaries.

Passing a generated token to Backblaze

There are two ways you can pass the generated token to Backblaze. The first is using an `Authorization` header. This is the recommended method.


1. Click **Create header** again to create another new header.



2. Fill out the **Create a header** fields as follows:
    - In the **Name** field, enter `Authorization`.
    - From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
    - In the **Destination** field, enter `http.Authorization`.
    - From the **Ignore if set** menu, select **No**.
    - In the **Priority** field, enter `20`.
3. In the **Source** field, enter the **Authorization Token** generated in the command line tool, surrounded by quotes. For example, if the token generated was `DEC0DEC0C0A`, then the **Source** field would be `"DEC0DEC0C0A"`
4. Click **Create**. A new Authorization header appears on the Content page.
5. Click **Activate** to deploy your configuration changes.

Alternatively, the second way is to pass an `Authorization` query parameter.

1. Click **Create header** again to create another new header.



2. Fill out the **Create a header** fields as follows:
    - In the **Name** field, enter `Authorization`.
    - From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
    - In the **Destination** field, enter `url`.
    - From the **Ignore if set** menu, select **No**.
    - In the **Priority** field, enter `20`.
3. In the **Source** field, enter the header authorization information using the following format:

```
querystring.set(req.url, "Authorization", "<Authorization Token
```

Using the previous example, that would be:

```
querystring.set(req.url, "Authorization", "DEC0DEC0C0A")
```

4. Click **Create**. A new Authorization header appears on the Content page.
5. Click **Activate** to deploy your configuration changes.

> **NOTE**
>
> This article describes how to configure an integration with a service provided by a third party. As stated in our Terms of Service, we do not provide direct support for non-Fastly services.

---

* * *

Data transfer with Backblaze B2

/en/guides/data-transfer-with-backblaze-b2

Fastly has partnered with Backblaze to provide an integration between Fastly and Backblaze B2 Cloud Storage services. Specifically, there are no egress costs from Backblaze to Fastly when you configure a Backblaze B2 service as your Fastly origin.

To offset many of the data transfer costs associated with switching from another cloud provider, Backblaze offers a migration program. Backblaze will cover migration fees for customers migrating over 50 TB of data from the US, Canada, and Europe regions of other Cloud Providers, and storing it with them for at least 12 months. For customers migrating less than 50 TB of data, Backblaze offers discounted transfer rates.

Read more about the migration program and review estimated cost saving calculations in their guide to Migrate to B2 Cloud Storage. To ensure your migration has minimal downtime, contact support.

NOTE

This article describes how to configure an integration with a service provided by a third party. As stated in our Terms of Service, we do not provide direct support for non-Fastly services.

* * *

Developer guide: Backends

/en/guides/developer-guide-backends

* * *

Developer guide: CI plugins

/en/guides/developer-guide-ci-plugins

* * *

Developer guide: CMS plugins

/en/guides/developer-guide-cms-plugins

* * *

Developer guide: Terraform

/en/guides/developer-guide-terraform

---

* * *

Developer guide: Third-party logging

/en/guides/developer-guide-third-party-logging

---

* * *

DigitalOcean Spaces

/en/guides/digitalocean-spaces

DigitalOcean Spaces public and private Spaces can be used as origins with Fastly.

Using DigitalOcean Spaces as an origin

To make your DigitalOcean Spaces available through Fastly, follow the steps below.

Creating a new service

Follow the instructions for creating a new service.

1. When you create the new domain and the new host:
    - In the **Domain Name** field on the **Create a domain** page, enter the hostname you want to use as the URL (e.g., `cdn.example.com`).
    - In the **Hosts** field on the **Origins** page, enter the appropriate address for your Host using the format `<SPACE>.<REGION>.digitaloceanspaces.com`. For

example, if your space name is `test123` and your region is `nyc3`, your hostname would be `test123.nyc3.digitaloceanspaces.com`.

2. When you edit the host details on the **Edit this host page**:
   - In the **Name** field, enter any descriptive name for your service if you haven't already done so.
   - In the **Address** field, ensure you've entered the appropriate address for your Host (e.g., `test123.nyc3.digitaloceanspaces.com`). You entered this information during Host creation.
3. When you edit the Transport Layer Security (TLS) area information for your host:
   - Leave the **Enable TLS?** default set to **Yes** to secure the connection between Fastly and your origin.
   - In the **Certificate hostname** field, enter the same address that appears in the Address field (e.g., `test123.nyc3.digitaloceanspaces.com`).
   - Under the **SNI hostname** field, select the checkbox to **Match the SNI hostname to the Certificate hostname**. The address you entered during Host creation appears.
4. In the **Override host** field, enter an appropriate address for your Host (e.g., `test123.nyc3.digitaloceanspaces.com`). You entered this information during Host creation.

Testing your results

By default, we create DNS mapping called `yourdomain.global.prod.fastly.net`. In the example above, it would be `cdn.example.com.global.prod.fastly.net`. Create a DNS alias for the domain name you specified (e.g., CNAME `cdn.example.com` to `global-nossl.fastly.net`).

Fastly will cache any content without an explicit `Cache-Control` header for 1 hour. You can verify whether you are sending any cache headers using curl. For example:

```
$ curl -I opscode-full-stack.nyc3.digitaloceanspaces.com

HTTP/1.1 200 OK
x-amz-id-2: ZpzRp7IWc6MJ8NtDEFGH12QBdk2CM1+RzVOngQbhMp2f2ZyalkFsZd4qF
x-amz-request-id: ABV5032583242618
Date: Fri, 18 Mar 2012 17:15:38 GMT
Content-Type: application/xml
```

```
Transfer-Encoding: chunked
```

In this example, no Cache-Control headers are set so default TTL will be applied.

Enhanced cache control

If you need more control over how different types of assets are cached (e.g., JavaScript files, images), refer to our cache freshness documentation.

Using private DigitalOcean Spaces

To use a private DigitalOcean Space with Fastly, follow the instructions below.

Before you begin

Be sure you've already made your Spaces data available to Fastly by pointing to the right Space and setting your origin to port 443. This needs to be done before authenticating.

Be sure you've got the access key, secret key, and Space name on hand. The DigitalOcean Spaces Authorization header takes the following form:

```
Authorization: AWS `AWSAccessKeyId`:`Signature`
```

From the DigitalOcean website you will need the following information:

- the **access key** and **secret key**
- your **Space** name

Setting up Fastly to use a private DigitalOcean Space

In order to use a private DigitalOcean Space with Fastly, create two headers, a Date header (for use with the authorization Signature) and an Authorization header.


Create a Date header

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.

3. Click **Edit configuration** and then select the option to clone the active version.

4. Click **Content**.

5. Click **Create header**.



6. Fill out the **Create a header** fields as follows:


- In the **Name** field, enter `Date`.
- From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
- In the **Destination** field, enter `http.Date`.
- In the **Source** field, enter `now`.
- From the **Ignore if set** menu, select **No**.
- In the **Priority** field, enter `10`.

7. Click **Create**. A new Date header appears on the Content page. You will use this later within the Signature of the Authorization header.

Create an Authorization header

Next, create the Authorization header with the specifications listed below.

1. Click **Create header** again to create another new header.



2. Fill out the **Create a header** fields as follows:

- In the **Name** field, enter `Spaces Authorization`.
- From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
- In the **Destination** field, enter `http.Authorization`.
- From the **Ignore if set** menu, select **No**.
- In the **Priority** field, enter `20`.

3. In the **Source** field, enter the header authorization information using the following format:

```
"AWS <DigitalOcean access key>:" digest.hmac_sha1_base64("<Digi
```

replacing `<DigitalOcean access key>`, `<DigitalOcean secret key ID>`, and `<Space name>` with the information you gathered before you began. For example:

```
"AWS JKCAUEFV2ONFFOFMSSLA:" digest.hmac_sha1_base64("P2WPSu68Bf
```

4. Click **Create**. The new Authorization header appears on the Content page.

A detailed look at the Source field

So what's going on in the Source field of the Authorization header? Here's the basic format:

`AWS<Access Key><Signature Function><key><message>`

It tells us the following:

Element	Description
`AWS`	A constant placed before the access key. It's always AWS.
`access key`	The access key from your DigitalOcean account. We used `JKCAUEFV2ONFFOFMSSLA` in this example.
`signature function`	The algorithm used to validate the key and message of the signature. We used `digest.hmac_sha1_base64(<key>, <message>)` in this example.

Element	Description
`key`	The secret key from your DigitalOcean account. We used `P2WPSu68BfI89j72vT+bXYZB7SjIOwhT4whqt27` in this example.
`message`	The UTF-8 encoding of the StringToSign. Check out the table below for a break down of each portion of the message.

The message that's part of the Source field in the Authorization header takes on this basic format:

```
<HTTP-verb></n><Content-MD5>/n<Content-Type></n><Date></n>
<CanonicalizedAmzHeader></n><CanonicalizedResource>
```

It tells us the following:

Element	Description
`HTTP-verb`	The REST verb. We use `req.method` in this example. We rewrite HEAD to GET because Varnish does this internally before sending requests to origin.
`/n`	A newline indicator constant. It's always /n.
`Content-MD5`	The content-md5 header value, used as a message integrity check. It's often left blank. We use `LF` (line feed) in this example.
`Content-Type`	The content-type header value, used to specify the MIME-type. It's often left blank. We use `LF` in this example.
`Date`	The date and time stamp. We use `req.http.Date` (which we created first as a separate header in the steps above).
`CanonicalizedAmzHeader`	The x-amz headers, which customize your Spaces implementation. It's often left blank. We use `LF` in this example.
`CanonicalizedResource`	Your DigitalOcean Space name. We use `"/test123"` in this example.

Following redirects to Spaces objects and caching Spaces responses

With custom VCL, Fastly can follow redirects to Spaces objects and cache the Spaces response as well as the 301 or 302 response separately.

Be sure to read our instructions about mixing and matching Fastly VCL with custom VCL. It's important to include the entire VCL boilerplate if you do not intend to override the Fastly default settings.

To configure Fastly to follow redirects to Spaces objects, insert the following VCL in your custom VCL:

Within `vcl_recv`

```
sub vcl_recv {

  if (req.http.redir != "true") {
    set req.backend = Main_Origin;
  } else {
    set req.backend = spaces_backend;
    set req.http.host = "nyc3.digitaloceanspaces.com";
  }

#FASTLY recv

  if (req.method != "HEAD" && req.method != "GET" && req.method !=
    return(pass);
  }

  return(lookup);

}
```

Within `vcl_deliver`

```
sub vcl_deliver {
```

```
  if (resp.status == 302 || resp.status == 301) {
    set req.http.redir = "true";
    set req.url = regsub(resp.http.Location, "http://nyc3.digita
    set req.http.Fastly-Force-Shield = "yes";
    restart;
  }

#FASTLY deliver

  return(deliver);
}
```

Be sure to set the `Main_Origin` and `spaces_backend` to the actual name of your backends in the service to which you're applying these redirects. You can find the exact names by reviewing your VCL. Simply click on the VCL button at the top of the page while viewing the service.

Once you added these VCL snippets to your custom VCL, upload the VCL file and then activate the new version of your service to apply the changes.

> **NOTE**
>
> This article describes how to configure an integration with a service provided by a third party. As stated in our Terms of Service, we do not provide direct support for non-Fastly services.

---

* * *

Discounted egress from Google

/en/guides/discounted-egress-from-google

Fastly has partnered with Google to provide an integration between Fastly and Google services. Specifically, the integration allows you to connect Google's Cloud Platform service

directly to Fastly's content delivery network services via private network interconnections (direct PNIs), thus speeding up your content delivery and optimizing backend workload.

When you sign up for Fastly services and configure a Google Cloud Platform service as your origin server, you designate a specific point of presence (POP) to serve as an Origin Shield that handles cached content from their servers.

Requests from Fastly POPs to these specific interconnect locations are routed over Fastly's network, leveraging optimized TCP connection handling, quick-start, and opened connections to enable fast response times between POPs and through to the end-user. Fastly ensures requests go directly to the Origin Shield instead of the origin servers. Only requests that the entire network has never handled will go back to the Google Cloud Platform service.

WARNING

We encourage you to read Google's CDN interconnect pricing. Despite this connection to Fastly's services being in place, in certain circumstances your data may egress from Google over the public internet rather than via the private network interconnection. In such cases, your traffic to the public internet will be metered according to your commercial arrangement with Google.

NOTE

This article describes how to configure an integration with a service provided by a third party. As stated in our Terms of Service, we do not provide direct support for non-Fastly services.

---

* * *

Google Cloud Storage

/en/guides/google-cloud-storage


Google Cloud Storage (GCS) can be used as an origin with your Fastly services once you set up and configure your GCS account and link it to a Fastly service. It can also be configured to use private content. This speeds up your content delivery and reduces your origin's workload and response times with the dedicated links between Google and Fastly's POPs.

Using GCS as an origin server

To make your GCS data available through Fastly, follow the steps below.

Setting up and configuring your GCS account

1. Sign up for Google Cloud Storage.
2. Create a bucket to store your origin's data.



3. Fill out the **Create a bucket** fields as follows:
    - In the **Name** field, enter a name for your bucket (e.g., `mybucket`). You can also create a domain-named bucket (e.g., `images.example.com`), but you'll be required to verify your domain ownership using Google's Search Console, if you

have not already done so. See the instructions on Google's website. Remember the name you type. You'll need it to connect your GCS bucket to your Fastly service.

- In the **Default storage class** area, select **Regional**.
- From the **Regional location** menu, select a location to store your content. Most customers select a region close to the interconnect location they specify for shielding.

4. Click **Create**.

You should now add objects to your bucket and make them externally accessible by selecting the **Public link** checkbox next to each of the objects.

Adding your GCS bucket as an origin server

To add your GCS bucket as an origin server, follow the instructions for working with hosts. You'll add specific details about your origin server.

1. In the **Hosts** field on the **Origins** page, enter the appropriate address for your Host using the format `<BUCKET>.storage.googleapis.com`. For example, if your bucket name is `test123`, your hostname would be `test123.storage.googleapis.com`.
2. For the initial **Edit this host** fields:
   - In the **Name** field, enter any descriptive name for your service (e.g., `Google Cloud Storage`).
   - In the **Address** field, enter the appropriate address for your Host using the format `<BUCKET>.storage.googleapis.com`. For example, if your bucket name is `mybucket`, your hostname would be `mybucket.storage.googleapis.com`.
3. When you edit the Transport Layer Security (TLS) area information for your host:
   - Leave the **Enable TLS?** default set to **Yes** to secure the connection between Fastly and your origin.
   - In the **Certificate hostname** field, enter `storage.googleapis.com`.
   - Under the **SNI hostname** field, select the checkbox to **Match the SNI hostname to the Certificate hostname**. The hostname address you entered during Host creation appears.
4. From the **Shielding** menu below the TLS area, select an interconnect location from the list of shielding locations.

5. In the **Override host** field, enter an appropriate address for your Host (e.g., `test123.storage.googleapis.com`). You entered this information during Host creation.

Interconnect locations

Interconnect locations allow you to establish direct links with Google's network edge when you choose your shielding location. By selecting one of the locations listed in our documentation, your traffic will be carried across our interconnections with Google and you will be eligible to receive Google's CDN partner pricing discount. Most customers select the interconnect closest to their GCS bucket's region. Review our caveats of shielding and select an interconnect accordingly.

Setting the Cache-Control header for your GCS bucket

By default, GCS performs its own caching for publicly readable objects, which may complicate efforts to purge cache. To avoid potential problems, we recommend using the gsutil command line utility to set the Cache-Control header for one or more objects in your GCS bucket:

```
$ gsutil setmeta -h "Cache-Control: no-store, max-age=86400" gs://<
```

Replace `<bucket>` in the example above with your GCS bucket's name. Note that `no-store` instructs GCS not to cache your content, while `max-age=86400` instructs Fastly to cache your content for one day. See Google's documentation on the `setmeta` command for more information.

Changing the default TTL for your GCS bucket

If you want to change the default TTL for your GCS bucket, if at all, keep the following in mind:

- Your GCS account controls the default TTL for your GCS content. GCS currently sets the default TTL to 3600 seconds. Changing the default TTL will not override the default setting in your GCS account.
- To override the default TTL set by GCS from within the Fastly control panel, create a new cache setting and enter the TTL there.

- To override the default TTL in GCS, download the gsutil tool and then change the Cache-Control headers to delete the default TTL or change it to an appropriate setting.

X-Http-Method-Override header behavior

GCS provides a unique functionality that allows clients to add a `X-Http-Method-Override` request header to override the request method being sent in the HTTP messages. For instance, a GET request with the `X-Http-Method-Override: HEAD` request header is treated as a HEAD request by GCS and returns a HEAD response (200 status code with an empty body).

This can cause unintended caching behavior, which is a security risk. For example, if an `X-Http-Method-Override` request header is received and an unexpected response is cached. In order to minimize this risk, we strongly recommend you unset the `X-Http-Method-Override` header in the `vcl_recv` subroutine as shown below:

```
unset req.http.X-Http-Method-Override;
```

Using GCS with private objects

To use Fastly with GCS private objects, be sure you've already made your GCS data available to Fastly by pointing to the right GCS bucket, then follow the steps below.


Setting up interoperable access

By default, GCS authenticates requests using OAuth2, which Fastly does not support. To access private objects on GCS, your project must have HMAC authentication enabled and interoperable storage access keys (an *Access Key* and *Secret* pair) created. Do this by following the steps below.


> **TIP**
>
> To limit access to your Google Cloud account, consider creating a service account and then creating HMAC keys for that service account. For more information, see Google's documentation on managing HMAC keys for service accounts.

1. Open the Google Cloud Platform console and select the appropriate project.
2. Click **Settings**.
3. Click **Interoperability**.
4. If you have not set up interoperability before, click **Enable interoperability access**.

5. Click **Make** `<PROJECT-ID>` **your default project** for interoperable access. If that project already serves as the default project, that information appears instead.



6. Click **Create a new key**. An access key and secret code appear.



7. Save the access key and secret code that appear. You'll need these later when you're creating an authorization header.

Setting up Fastly to use GCS private content


To use GCS private content with Fastly, create two headers, a Date header (required Authorization Signature) and an Authorization header.

Creating a Date header

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.

4. Click **Content**.

5. Click **Create header**.



6. Fill out the **Create a new header** fields as follows:


   - In the **Name** field, enter `Date`.

- From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
- In the **Destination** field, enter `http.Date`.
- In the **Source** field, enter `now`.
- From the **Ignore if set** menu, select **No**.
- In the **Priority** field, enter `10`.

7. Click **Create**. A new Date header appears on the Content page. You will use this later within the Signature of the Authorization header.

Creating an Authorization header

1. Click **Create header** again to create another new header.



2. Fill out the **Create a header** fields as follows:
    - In the **Name** field, enter `Authorization`.
    - From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
    - In the **Destination** field, enter `http.Authorization`.

- From the **Ignore if set** menu, select **No**.
- In the **Priority** field, enter `20`.

3. In the **Source** field, enter the header authorization information using the following format:

```
"AWS <access key>:" digest.hmac_sha1_base64("<GCS secret>", if(
```

replacing `<access key>`, `<GCS secret>`, and `<GCS bucket name>` with the information you gathered before you began. For example:

```
"AWS GOOGQORE5WOJJHLXH6OD:" digest.hmac_sha1_base64("oQb0hdmaxF
```

4. Click **Create**. A new Authorization header appears on the Content page.
5. Click **Activate** to deploy your configuration changes.

A detailed look at the Source field

So what's going on in the Source field of the Authorization header? Here's the basic format:

`AWS<access key><signature function><key><message>`

It tells us the following:

Element	Description
`AWS`	A constant placed before the access key. It's always AWS.
`access key`	The access key ID from your GCS developer's account. We used `GOOGQORE5WOJJHLXH6OD` in this example.
`signature function`	The algorithm used to validate the key and message of the signature. We used `digest.hmac_sha1_base64(<key>, <message>)` in this example.
`key`	The secret key ID from your GCS developer's account. We used `oQb0hdmaxFOc5UmC6F833Cde0+ghRSgsr7CCnX62` in this example.

Element	Description
`message`	The UTF-8 encoding of the StringToSign. See the table below for a break down of each portion of the message.

The message that's part of the Source field in the Authorization header takes on this basic format:

```
<HTTP-verb><\n><Content-MD5>\n<Content-Type><\n><Date><\n>
<CanonicalExtensionHeaders><\n><CanonicalizedResource>
```

It tells us the following:

Element	Description
`HTTP-verb`	The REST verb. We use `req.method` in this example.
`\n`	A newline indicator constant. It's always \n.
`Content-MD5`	The content-md5 header value, used as a message integrity check. It's often left blank. We use `LF` (line feed) in this example.
`Content-Type`	The content-type header value, used to specify the MIME-type. It's often left blank. We use `LF` in this example.
`Date`	The date and time stamp. We use `req.http.Date` (which we created first as a separate header in the steps above).
`CanonicalExtensionHeaders`	The x-amz- or x-goog- headers, which customize your GCS implementation. It's often left blank. We use `LF` in this example.
`CanonicalizedResource`	Your GCS resource path name. We're concatenating GCS bucket name `"/test123"` with object path `req.url.path` in this example.

NOTE

> This article describes how to configure an integration with a service provided by a third party. As stated in our Terms of Service, we do not provide direct support for non-Fastly services.


* * *

📄	**Google Compute Engine**
🔗	/en/guides/google-compute-engine


Google Compute Engine (GCE) lets you create and run a virtual machine (VM) on the Google infrastructure. The VM can be used as an origin with your Fastly service once you set up and configure your VM instance and link your instance to a Fastly service.

Creating and setting up your GCE instance


1. Sign up for Google Compute Engine and start the basic set up. If you are already signed up and at your dashboard, click the **Get started** link in the Try Compute Engine area.
2. Create or select a project to hold your origin's data.



3. Click **Create instance** to set up your VM. You can set up your instance using either Windows or Linux.



4. Fill in the necessary fields and click **Create**. When making your firewall selection, select either **Allow HTTPS traffic** (port 443) or **Allow HTTP traffic** (port 80); you will use one of those ports when you create your new origin in your Fastly service. If you select HTTPS traffic, you need to configure the VM to respond on port 443 with a valid TLS certificate.



5. Make note of the following information for when you create your new origin in your Fastly service:

    - The instance's IP address (located in the External IP column at the bottom of the page). You'll use this in the **Address** field when you create your new origin.
    - The zone you are using (located in the Zone column at the bottom of the page). You'll use this to guide your selection of an appropriate shielding location for your origin.

Creating a new origin in your Fastly service for your GCE account

Link your GCE account to a Fastly service following the steps below.

1. Log in to the Fastly control panel.
2. Create a new service if you don't already have one set up.


3. Follow the instructions for working with hosts. You'll add specific details about your origin server when you fill out the **Create a host** fields:
    - In the **Name** field, enter the name of your server (for example, `Google Compute Engine`).
    - In the **Address** field, enter the IP address of your server. This should match the port that you selected in the GCE interface.
    - From the **Shielding** menu, select an interconnect location from the list of shielding locations.

Interconnect locations

Interconnect locations allow you to establish direct links with Google's network edge when you choose your shielding location. By selecting one of the locations listed in our documentation, you will be eligible to receive discounted pricing from Google CDN Interconnect for traffic traveling from Google Cloud Platform to Fastly's network. Most customers select the interconnect closest to their origin. Review our caveats of shielding and select an interconnect accordingly.

Creating new domains for GCE to respond to

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Create domain**.



5. In the **Domain Name** field, enter the name that users will enter in their browsers to access your site.
6. *(Optional)* In the **Comment** field, enter a comment that describes your domain.
7. Click **Create**. The new domain appears on the Domains page.
8. Click **Activate** to deploy your configuration changes.

Creating a CNAME record

You can now test your configuration. In the example above, your domain would appear as `www.example.com.global-nossl.fastly.net`. After you test and you're satisfied with the results, create a CNAME record for your domain (e.g., `www.example.com`) pointing to `global-nossl.fastly.net`.

> **NOTE**
>
> This article describes how to configure an integration with a service provided by a third party. As stated in our Terms of Service, we do not provide direct support for non-Fastly services.

* * *

HUMAN Bot Defender

/en/guides/human-bot-defender

IMPORTANT

This information is part of a limited availability release. For additional details, read our product and feature lifecycle descriptions.

Fastly provides direct integration between HUMAN Bot Defender (formerly PerimeterX Bot Defender) and Fastly edge servers. By placing a snippet of JavaScript (or HTML5) on your site and custom VCL directly into your Fastly service configuration, this integration allows you to gather behavioral data and statistics that may help you do things like detect invalid traffic and mitigate automated web attacks.

How to get started

Integration with HUMAN Bot Defender requires an account with HUMAN. Once you have this account set up, contact your Fastly account manager or email sales@fastly.com to begin the integration process with Fastly. We'll work with you to configure your service to include the required code to enforce bot mitigation policies.

NOTE

This article describes how to configure an integration with a service provided by a third party. As stated in our Terms of Service, we do not provide direct support for non-Fastly services.

---

* * *

Microsoft Azure Blob Storage

/en/guides/microsoft-azure-blob-storage

Microsoft Azure Blob Storage public and private containers can be used as origins with Fastly.

> **TIP**
>
> With properly configured services in place, shared Fastly and Microsoft customers will benefit from Fastly's integration with Azure's ExpressRoute Direct Local, which results in Fastly including your outbound data transfer costs from Azure in your standard Fastly pricing. See our guide to outbound data transfers from Azure for more details.

Using Azure Blob Storage as an origin

When using Azure Blob Storage as an origin, we recommend using the most recent version of Azure storage services. Certain incompatibilities may occur if using too old a version or if the version is not specified by the request header. To enforce a version to use when not specified by the header, set the `DefaultServiceVersion` in your Blob storage service.

Alternatively, place a VCL snippet to `vcl_miss` and `vcl_pass` to set or enforce the version. For example, if the version is `2020-06-12`, the VCL snippet would look like the following:

```
{{if (req.backend.is_origin) { }}
{{ set bereq.http.x-ms-version = "2020-06-12"; }}
}
```

Once you've configured your Azure Blob Storage stores are ready to make them available through Fastly, follow the steps below.

Creating a new service

Follow the instructions for creating a new service. You'll add specific details about your origin when you fill out the **Create a new service** fields:


- In the **Name** field, enter any descriptive name for your service.
- In the **Domain** field, enter the hostname you want to use as the URL (e.g., `cdn.example.com`).

- In the **Address** field, enter `<storage account name>.blob.core.windows.net`.
- In the **Transport Layer Security (TLS)** area, leave the **Enable TLS?** default set to **Yes** to secure the connection between Fastly and your origin.
- In the **Transport Layer Security (TLS)** area, enter `<storage account name>.blob.core.windows.net` in the **Certificate hostname** field.

Setting the default Host and correct path

Once the new service is created, set the default Host to `azure` and then add your container path to the URL by following the steps below:

1. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
2. Click **Edit configuration** and then select the option to clone the active version.
3. Click **Settings**.
4. Click the **Override host** switch.



5. Enter the hostname of your Azure Blob Storage account. For example, `<storage account name>.blob.core.windows.net`.
6. Click **Save**.
7. Click **Content**.
8. Click **Create header**.
9. Fill out the **Create a header** fields as follows:
    - In the **Name** field, enter `Modify URL`.
    - From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
    - In the **Destination** field, enter `url`.

- In the **Source** field, enter `"/<your container name>" req.url`.
- From the **Ignore if set** menu, select **No**.
- In the **Priority** field, enter `10`.

10. Click **Create**.
11. Click **Activate** to deploy your configuration changes.

Testing your results

By default, we create DNS mapping called **yourdomain.global.prod.fastly.net**. In the example above, it would be `cdn.example.com.global.prod.fastly.net`. Create a DNS alias for the domain name you specified (e.g., CNAME `cdn.example.com` to `global-nossl.fastly.net`).

Fastly will cache any content without an explicit `Cache-Control` header for 1 hour. You can verify whether you are sending any cache headers using curl. For example:

```
$ curl -I opscode-full-stack.blob.core.windows.net

HTTP/1.1 200 OK
Date: Fri, 04 May 2018 21:23:07 GMT
Content-Type: application/xml
Transfer-Encoding: chunked
Server: Blob Service Version 1.0 Microsoft-HTTPAPI/2.0
```

In this example, no Cache-Control headers are set so the default TTL will be applied.

Using an Azure Blob Storage private container

To use an Azure Blob Storage private container with Fastly, follow the instructions below.

Before you begin

Be sure you've already made your Azure Blob Storage containers available to Fastly by pointing to the right container and setting your origin to port 443. This needs to be done before authenticating.

To complete the setup, you'll also need your Azure Storage Account shared key and storage account name to construct the Azure Blob Storage Authorization header, which takes the

following form:

```
Authorization: SharedKey `Account name`:`Signature`
```

Finally, you'll also need to know your Blob Storage container name.

Setting up Fastly to use an Azure Blob Storage private container with a Shared Key


> **WARNING**
>
> Your account's Shared Key does not have detailed access control. Anyone with access to your Shared Key can read and write to your container. Consider using a Shared Access Signature (SAS) instead.

To access an Azure Blob Storage private container with Fastly using a Shared Key, first familiarize yourself with Microsoft's documentation on authorizing with Shared Key. Then, create two headers: a Date header (for use with the authorization Signature) and an Authorization header.

Create a Date header

Create the Date header using the steps below.

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click **Create header**.



6. Fill out the **Create a header** fields as follows:
    - In the **Name** field, enter `Date`.
    - From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
    - In the **Destination** field, enter `http.Date`.


- In the **Source** field, enter `now`.
- From the **Ignore if set** menu, select **No**.
- In the **Priority** field, enter `10`.

7. Click **Create**. A new Date header appears on the Content page. You will use this later within the Signature of the Authorization header.

Create an Authorization header

Next, create the Authorization header with the specifications listed below.

1. Click **Create header** again to create another new header.



2. Fill out the **Create a header** fields as follows:
    - In the **Name** field, enter `Azure Authorization`.
    - From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
    - In the **Destination** field, enter `http.Authorization`.

- From the **Ignore if set** menu, select **No**.
- In the **Priority** field, enter `20`.

3. In the **Source** field, enter the header authorization information using the following format:

```
"SharedKey <Storage Account name>:" digest.hmac_sha256_base64(d st
```

replacing `<Storage Account name>` and `<Azure Storage Account shared key>` with the information you gathered before you began. For example:

```
"SharedKey test123:" digest.hmac_sha256_base64(digest.base64_de e(
```

We provide a detailed look at the Source field parameters below.

4. Click **Create**. The new Authorization header appears on the Content page.
5. Click **Activate** to deploy your configuration changes.

A detailed look at the Source field

So what's going on in the Source field of the Authorization header? Here's the basic format:

```
SharedKey<storage account name><Signature Function><key><message>
```

It tells us the following:

Element	Description
`SharedKey`	A constant placed before the storage account name. It's always SharedKey.
`storage account name`	The name of your Azure Storage Account. We used `test123` in this example.

Element	Description
`signature function`	The algorithm used to validate the key and message of the signature. We used `digest.hmac_sha256_base64(<key>, <message>)` in this example.
`key`	The Azure Storage Account shared key from your Azure Storage developer's account. We used `UDJXUFN1NjhCZmw4OWo3MnZUK2JYWVpCN1NqbE93aFQ0d2hxdDI3` in this example. It must be Base64 decoded.
`message`	The UTF-8 encoding of the StringToSign. See the table below for a break down of each portion of the message.

The message that's part of the Source field in the Authorization header takes on this basic format:

```
<HTTP-verb></n><Content-MD5>/n<Content-Type></n><Date></n>
<CanonicalizedAmzHeader></n><CanonicalizedResource>
```

It tells us the following:

Element	Description
`HTTP-verb`	The REST verb. We use `req.method` in this example. We rewrite HEAD to GET because Varnish does this internally before sending requests to origin.
`\n`	A newline indicator constant. It's always \n.
`Content-MD5`	The content-md5 header value, used as a message integrity check. It's often left blank. We use `LF` (line feed) in this example.
`Content-Type`	The content-type header value, used to specify the MIME-type. It's often left blank. We use `LF` in this example.
`Date`	The date and time stamp. We use `req.http.Date` (which we created first as a separate header in the steps above).

Element	Description
`CanonicalizedHeaders`	The x-ms headers, which customize your Azure Blob Storage implementation. It's often left blank. We use `LF` in this example.
`CanonicalizedResource`	Your Storage Account Name. We use `"/test123"` in this example.

Setting up Fastly to use an Azure Blob Storage private container with a Shared Access Signature (SAS)

To access an Azure Blob Storage private container with Fastly using a Service Shared Access Signature (SAS), read Microsoft's Delegate access with a shared access signature page. Then, obtain the SAS and sign the access URL.

TIP


Using a Service Shared Access Signature gives you more detailed control over:

- The interval during which the SAS is valid, including the start time and the expiry time.
- The permissions granted by the SAS. For example, a SAS for a blob might grant read and write permissions to that blob, but not delete permissions.
- An optional IP address or range of IP addresses from which Azure Storage will accept the SAS. For example, you might specify a range of IP addresses belonging to your organization.
- The protocol over which Azure Storage will accept the SAS. You can use this optional parameter to restrict access to clients using HTTPS.

Obtaining the Shared Access Signature

Obtain the SAS using the steps below.

1. In the Azure portal, navigate to your storage account
2. Under settings navigate to **Shared access signature**.



3. From the **Allowed services** controls, select **Blob**.
4. From the **Allowed resource types** controls, select **Object**.
5. From the **Allowed permissions** controls, select **Read**.
6. Leave the **Start time** set to the current date and time.
7. Set the **End time** as far in the future as you are comfortable (see note below).
8. Ensure the **Allowed protocols** remain set to **HTTPS only**.
9. Click **Generate SAS and connection string**. The generated information appears.
10. Copy and save the contents of the **SAS token** field. It will look something like:


```
?sv=2017-11-09&ss=b&srt=o&sp=r&se=2019-10-22T15:41:23Z&st=2018-
```

We provide a detailed look at the Shared Access Signature parameters below.

Signing the URL

Next, sign the access URL by creating an authorization header following the steps below.

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Content**.
5. Click **Create header**.



6. Fill out the **Create a header** fields as follows:

- In the **Name** field, enter a meaningful name such as `Set Azure private SAS Authorization URL`.
- From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
- In the **Destination** field, enter `url`.
- In the **Source** field, enter `req.url.path {"<SAS TOKEN>"}` replacing `{"<SAS TOKEN>"}` with the token you obtained from the Azure Portal.
- From the **Ignore if set** menu, select **No**.
- In the **Priority** field, enter `10`.

7. Click **Create**.
8. Click **Activate** to deploy your configuration changes.

A detailed look at the Shared Access Signature parameters

Microsoft's Create a service SAS page provides more details on shared access signatures and how they are constructed.

Element	Description
`sv`	The `signedversion` field. This is required and should be whatever the Azure portal provided.
`ss`	The `signedservice` field. This is required and should be `b` for "blob storage."
`srt`	The `signedresourcetype` field. This is required and should be `o` for "object."
`sp`	The `signedpermissions` field. This is required and should be `r` for "read only."
`st`	The `signedstart` field. This is optional and specifies, in a UTC format compatible with ISO 8601, the time at which the shared access signature becomes valid. If omitted, the start time for this call is assumed to be the time when the storage service receives the request.

Element	Description
`se`	The `signedexpiry` field. This is required and specifies, in a UTC format compatible with ISO 8601, the time at which the shared access signature becomes invalid.
`spr`	The `signedprotocol` field. This is optional and specifies which HTTP protocol (`http` or `https`) the container should use for access. We recommend `https`.
`sig`	The `signature` field. This is required and should be whatever the Azure portal provided.

WARNING

Always keep track of the `se` expiry date. After it has passed, Fastly will not be able to access your private container.

TCP connection settings for improved performance

By default, Fastly keeps established TCP connections opened to your origin to improve performance. Azure's default behavior, however, closes idle connections. Specifically, the Azure Load Balancer's default behavior silently drops flows when the default idle timeout of a flow reaches four minutes. To ensure successful integration, we suggest tuning Azure in two ways:

- increase the Azure Load Balancer's TCP idle timeout setting
- configure Azure to send a bidirectional TCP Reset (RST packet) on idle timeout

NOTE

This article describes how to configure an integration with a service provided by a third party. As stated in our Terms of Service, we do not provide direct support for non-Fastly services.

* * *

Using Databend with Fastly Object Storage

🔗 /en/guides/object-storage-databend

Fastly Object Storage works with the S3-compatible API to store and access large files from Fastly. This same API can be used with Databend, the open-source Cloud Data Warehouse, to remotely load files from Fastly into Databend using their Cloud Bucket feature.

Prerequisites

To remotely load files from Fastly Object Storage into Databend, you will need to create an Object Storage access key used to authenticate against the S3-compatible API and create a table in Databend that matches the format of the data file you want to load.

Using Databend with Fastly Object Storage

Use the Databend `COPY INTO` command to load the data out of Fastly Object Storage, setting the `CONNECTION` parameters as follows:

- `access_key` and `secret_access_key`: enter the appropriate values generated from the Object Storage access key you created.
- `region`: enter the Fastly data storage region you want to use (e.g. `eu-central`).
- `endpoint_url`: enter `<region>.object.fastlystorage.app` where `<region>` matches the region value above.
- `enable_virtual_host_style`: enter `FALSE`

Example:

```
CONNECTION = (
    access_key_id = 'AKIAIOSFODNN7EXAMPLE',
    secret_access_key = 'wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY',
    region = 'us-west',
    endpoint_url = 'us-west.object.fastlystorage.app',
    enable_virtual_host_style = FALSE
)
```

* * *

Using DuckDB with Fastly Object Storage

/en/guides/object-storage-duckdb

Fastly Object Storage works with the S3-compatible API to store and access large files from Fastly. This same API can be used with DuckDB, the fast, portable open-source, in-process analytical database.

Prerequisites

To remotely load files from Fastly Object Storage into DuckDBextension, you must install the `httpfs` DuckDBextension by running the `INSTALL` SQL command. This only needs to be run once. DuckDB may also try to auto-install the extension.

You will also need to create an Object Storage access key used to authenticate against the S3-compatible API.

Using DuckDB with Fastly Object Storage

To use DuckDB with Fastly Object Storage, first create an `S3` secret in DuckDB, setting the `CREATE SECRET` parameters as follows:

- `KEY_ID` and `SECRET`: enter the appropriate values generated from the Object Storage access key you created.
- `URL_STYLE`: enter `path`.
- `REGION`: enter the Fastly data storage region you want to use (e.g. `eu-central`).
- `ENDPOINT`: enter `<region>.object.fastlystorage.app` where `<region>` matches the region value above.

Example:

```
CREATE SECRET my_secret (
    TYPE S3,
```

```
    KEY_ID 'AKIAIOSFODNN7EXAMPLE',
    SECRET 'wJalrXUtnFEMI/K7MDENG/bPxRfiCYEXAMPLEKEY',
    URL_STYLE 'path',
    REGION 'us-east',
    ENDPOINT 'us-east.object.fastlystorage.app' -- see note belo
);

```

After setting up the Fastly Object Storage credentials, you can query the data using DuckDB's built-in methods, such as `read_csv` or `read_parquet`:

```
SELECT * FROM 's3://{fastly_bucket_name}/{file}.csv';
SELECT * FROM read_parquet('s3://{fastly_bucket_name}/{file}.parquet');
```

* * *

Oracle Cloud Storage

/en/guides/oracle-cloud-storage

Oracle Cloud Storage public and private buckets can be used as origins with Fastly.

Before you begin

Before you begin the setup and configuration steps required to use Oracle Cloud as an origin, keep in mind the following:

- You must have a valid Oracle Cloud account. Before you can create a new bucket and upload files to it for Fastly to use, you must first create an Oracle Cloud account at the Oracle website.
- Oracle Cloud implements both its own proprietary API and an S3 Compatible API. Currently, Fastly supports private buckets only via the S3 Compatible API.

Using Oracle Cloud Storage as an origin


To use Oracle Cloud Storage as an origin, follow the steps below.

Creating a new bucket

Data in Oracle Cloud Storage is stored in buckets. Follow these steps to create a new bucket via the Oracle Cloud web interface.


> **TIP**
>
> The Oracle Guide provides more details on how to create a bucket.

1. Log in to your Oracle account.
2. Open the navigation menu in the upper left and navigate to **Object Storage**, then select **Object Storage**.



3. Select a compartment from the **Compartment** list on the left side of the page.
4. Click **Create a Bucket**.

5. In the **Bucket Name** field, enter a unique bucket name. Bucket names must be unique within the namespace and cannot be nested. The name can contain letters, numbers, dashes, and periods.



6. Click **Create a Bucket**. The new bucket appears in the list of buckets on the Oracle Cloud Storage Buckets page.


7. By default, new buckets are private. Click on three dots on the right side of the bucket and select **Edit Visibility**. Change the visibility to **Public** and deselect the **Allow users to list objects from this bucket** option.

8. Upload a file to the new bucket you just created.

Finding your bucket's namespace and hostname

To set up a Fastly service that interacts with your Oracle Cloud Storage, you will need to know the namespace identifier and hostname assigned to the bucket you created and uploaded files to.

To find your namespace, click on the bucket and examine the **Bucket Information** tab. In this example the namespace is `decafbaddeadbeef`.



To determine your bucket's hostname:

- If you're using the native Oracle API then the hostname takes the form of `objectstorage.<region>.oraclecloud.com` (e.g `objectstorage.us-ashburn-1.oraclecloud.com`).

- If you're using the S3 Compatible API then the hostname takes the form of `<namespace id>.compat.objectstorage.<region>.oraclecloud.com` (e.g `decafbaddeadbeef.compat.objectstorage.us-ashburn-1.oraclecloud.com`).

Creating a new service

To create a new Fastly service, you must first create a new domain and then create a new host and edit it to accept traffic for Oracle Cloud Storage. Instructions to do this appear in

our guide to creating a new service. While completing these instructions, keep the following in mind:

- When you create the new host, enter the Oracle bucket's hostname in the **Hosts** field on the **Origins** page. See Finding your bucket's namespace and hostname.
- When you edit the host details on the **Edit this host page**, confirm the Transport Layer Security (TLS) area information for your host. Specifically, make sure you do the following:
  - Secure the connection between Fastly and your origin.
  - Enter your bucket's hostname in the **Certificate hostname** field.
  - Select the checkbox to match the SNI hostname to the Certificate hostname (it appears under the SNI hostname field).
  - *(Optional)* Enable shielding by choosing the appropriate shielding location from the **Shielding** menu. When using Oracle Cloud Storage, this means you must choose a shielding location closest to the most appropriate Oracle region.
- Decide whether or not you should specify an override host in the **Advanced options** area which is the same as your bucket hostname.

Using the Oracle Cloud API with public objects

To use the Oracle Cloud API with public objects, you need to either create a new header, or a VCL Snippet. The purpose of the header or VCL snippet is to rewrite request URLs for your Oracle Cloud Storage instance.


Using a Header object

1. On your Fastly service's configuration page, click **Create header** to create a new header.
2. Fill out the **Create a header** fields as follows:
   - In the **Name** field, enter `Rewrite Oracle Cloud Storage URL`.
   - From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
   - In the **Destination** field, enter `url`.
   - From the **Ignore if set** menu, select **No**.
   - In the **Priority** field, enter `20`.

3. In the **Source** field, enter `"/n/<namespace id>/b/<bucket name>/o" req.url` (e.g., `"/n/decafbaddeadbeef/b/fastly-bucket/o" req.url`).
4. Click **Create**.
5. Click **Add a condition** next to the `Rewrite Oracle Cloud Storage URL` header.
6. Click **Create a new request condition**.
7. Fill out the condition fields as follows:
   - In the **Name** field, enter `Oracle Cloud Storage Shielding`.
   - In the **Apply if** field, enter `(req.method == "GET" && !req.backend.is_shield) {}`.
8. Click **Save and apply**.
9. Click **Activate** to deploy your configuration changes.

Using a VCL Snippet

1. Click **VCL Snippets** on your service's configuration page, then click **Create Snippet**.
2. In the Create a VCL Snippet page, enter a name for the snippet.
3. Select **within subroutine** to specify its placement, and **miss** as the subroutine type.



4. Add the following code to the **VCL** field. Change the values of the `oracleNamespace` and `oracleBucket` variables to match your Oracle namespace and bucket.

```
declare local var.oracleNamespace STRING;
declare local var.oracleBucket STRING;
set var.oracleNamespace = "YOUR_ORACLE_NAMESPACE_ID";   # Chang
set var.oracleBucket = "YOUR_ORACLE_BUCKET_NAME";   # Change th

if (req.method == "GET" && !req.backend.is_shield) {
  set bereq.url = "/n/" var.oracleNamespace "/b/" var.oracleBuc
}

```

Using the S3 Compatible API with public objects

To use the S3 Compatible API with public objects you must create a new header, as explained below.

1. On your Fastly service's configuration page, click **Create header** to create a new header.
2. Fill out the **Create a header** fields as follows:
   - In the **Name** field, enter `Rewrite Oracle Cloud Storage URL`.
   - From the **Type** menu, select **Request**, and from the **Action** menu, select **Set**.
   - In the **Destination** field, enter `url`.
   - From the **Ignore if set** menu, select **No**.
   - In the **Priority** field, enter `20`.
3. In the **Source** field, enter `"/<bucket name>/" req.url` (e.g., `"/fastly-bucket/o" req.url`).
4. Click **Create**.
5. Click **Activate** to deploy your configuration changes.

Private Buckets

> **IMPORTANT**
>
> Currently, Fastly can only support private objects using the S3 Compatible API.

To use an Oracle Cloud Storage private bucket with Fastly you must implement version 4 of Amazon's header-based authentication. You can do this using custom VCL. Keep in mind the following:

- You will need an Oracle **Customer Secret Key** which consists of an **Access Key** and **Secret Key**.
- You must use path-based access. Virtual host-style access (for example, accessing a bucket as `<bucketname>.<namespace>.compat.objectstorage.<region>.oraclecloud.com`) is not supported.

The following table lists the information you need to obtain from Oracle Cloud Storage before starting.

Item	Description
Namespace	The namespace identifier assigned to your bucket (see Finding your bucket's namespace and hostname.
Bucket name	The name of your OCS bucket. When you download items from your bucket, this is the string listed in the URL path or hostname of each object.
Region	The OCS region code of the location where your bucket resides (e.g., `us-east-1`).
Access key	The OCS access key string for your account that has at least read permission on the bucket.
Secret key	The OCS secret access key paired with the access key above.

Once you have this information, you can configure your Fastly service to authenticate against your S3 bucket using header authentication by calculating the appropriate header value in VCL.


IMPORTANT

Consider leaving the **Override host** field for the origin blank in your service settings. This setting will override the host header from the snippets shown here and may invalidate the signature that authenticates the information being sent.

Start by creating a regular VCL snippet. Give it a meaningful name, such as `AWS protected origin`. When you create the snippet, select **within subroutine** to specify its placement and

choose **miss** as the subroutine type. Then, populate the **VCL** field with the following code (be sure to change specific values as noted to ones relevant to your own AWS bucket):

1. Click **VCL Snippets** on your service's configuration page, then click **Create Snippet**.
2. In the Create a VCL Snippet page give the snippet a meaningful name, such as `AWS protected origin`.
3. Select **within subroutine** to specify snippet placement, and **miss** as the subroutine type.



4. Add the following code to the **VCL** field. Be sure to change the values of the variables (`ocsNamespace`, `ocsAccessKey`, etc.) to match your Oracle environment.

```
declare local var.ocsNamespace STRING;
declare local var.ocsAccessKey STRING;
declare local var.ocsSecretKey STRING;
declare local var.ocsS3Bucket STRING;
declare local var.ocsRegion STRING;
declare local var.canonicalHeaders STRING;
declare local var.signedHeaders STRING;
declare local var.canonicalRequest STRING;
declare local var.canonicalQuery STRING;
declare local var.stringToSign STRING;
declare local var.dateStamp STRING;
declare local var.signature STRING;
declare local var.scope STRING;

```

```
set var.ocsNamespace = "YOUR_OCS_NAMESPACE"; # Change this v
set var.ocsAccessKey = "YOUR_OCS_ACCESS_KEY";   # Change thi
set var.ocsSecretKey = "YOUR_OCS_SECRET_KEY";   # Change thi
set var.ocsS3Bucket = "YOUR_OCS_BUCKET_NAME";   # Change thi
set var.ocsRegion = "YOUR_OCS_REGION";   # Change this value

if (req.method == "GET" && !req.backend.is_shield) {

  set bereq.http.x-amz-content-sha256 = digest.hash_sha256("
  set bereq.http.x-amz-date = strftime({"%Y%m%dT%H%M%SZ"}, r
  set bereq.http.host = var.ocsNamespace ".compat.objectstor
  set bereq.url = querystring.remove(bereq.url);
  set bereq.url = regsuball(urlencode(urldecode(bereq.url.pa
  set var.dateStamp = strftime({"%Y%m%d"}, now);
  set var.canonicalHeaders = ""
    "host:" bereq.http.host LF
    "x-amz-content-sha256:" bereq.http.x-amz-content-sha256
    "x-amz-date:" bereq.http.x-amz-date LF
  ;
  set var.canonicalQuery = "";
  set var.signedHeaders = "host;x-amz-content-sha256;x-amz-c
  set var.canonicalRequest = ""
    "GET" LF
    bereq.url.path LF
    var.canonicalQuery LF
    var.canonicalHeaders LF
    var.signedHeaders LF
    digest.hash_sha256("")
  ;

  set var.scope = var.dateStamp "/" var.ocsRegion "/s3/aws4_

  set var.stringToSign = ""
    "AWS4-HMAC-SHA256" LF
    bereq.http.x-amz-date LF
    var.scope LF
    regsub(digest.hash_sha256(var.canonicalRequest),"^0x", "
  ;

  set var.signature = digest.awsv4_hmac(
```

```
    var.ocsSecretKey,
    var.dateStamp,
    var.ocsRegion,
    "s3",
    var.stringToSign
  );

  set bereq.http.Authorization = "AWS4-HMAC-SHA256 "
    "Credential=" var.ocsAccessKey "/" var.scope ", "
    "SignedHeaders=" var.signedHeaders ", "
    "Signature=" + regsub(var.signature,"^0x", "")
  ;
  unset bereq.http.Accept;
  unset bereq.http.Accept-Language;
  unset bereq.http.User-Agent;
  unset bereq.http.Fastly-Client-IP;
}

```

NOTE

This article describes how to configure an integration with a service provided by a third party. As stated in our Terms of Service, we do not provide direct support for non-Fastly services.

* * *

Outbound data transfer from Azure

/en/guides/outbound-data-transfer-from-azure

Fastly has integrated local circuits with Microsoft Routing Preference Unmetered to create private connections to Azure. If using Azure as your origin, you can take advantage of the improved reliability, faster speeds, lower latencies, and higher security that this private local circuit offers over typical public internet connections.

To configure your Fastly service to use direct connectivity via this local circuit, enable shielding using your Azure service region to determine the shielding location. Additionally, configure the routing preference for your storage account based on the service region and shielding location combination. Our documentation lists the available shielding locations for the routing preference you've chosen.

> **NOTE**
>
> You can configure a routing preference after the storage account is created.

Once you configure your Fastly service and Azure storage account correctly, outbound data transfers from the appropriate Azure regions to Fastly will use this local circuit. Because Fastly has purchased this local circuit from Microsoft, Microsoft does not apply outbound data transfer rates to traffic traveling over it. Use of this local circuit should work with Azure services like Container Instances, Functions, and Media Services, as well as Blob Storage.

> **WARNING**
>
> We encourage you to use Microsoft Azure's Billing Tools to monitor traffic on Microsoft Routing Preference Unmetered for the purpose of zero-rated egress. Despite this connection to Fastly's services being in place, in certain circumstances your data may egress from Azure over the public internet. In such cases, your traffic to the public internet will be metered according to your commercial arrangement with Microsoft.

> **NOTE**
>
> This article describes how to configure an integration with a service provided by a third party. As stated in our Terms of Service, we do not provide direct support for non-Fastly services.

---

* * *

Storj DCS Object Storage

/en/guides/storj-dcs-object-storage

Storj DCS can be used as an origin for public and private Storj buckets via the Storj DCS S3 Gateway. Built on the Storj Network, Storj DCS is a decentralized object storage service that is S3 compatible and end-to-end encrypted by default.

Prerequisites

Before adding Storj DCS as an origin for Fastly services, you will need to create a Storj DCS account, project and access credentials, and a bucket that will serve as your origin.

Using Storj DCS as an origin

To use Storj DCS as an origin and make your Storj bucket available through Fastly via the Storj DCS S3 Gateway, follow the steps below.

Creating a new service

Follow the instructions for creating a new service.

1. When you create the new domain and the new host:
    - In the **Domain Name** field on the **Create a domain** page, enter the hostname you want to use as the URL (e.g., `cdn.example.com`).
    - In the **Hosts** field on the **Origins** page, enter the IP address or hostname of your Storj DCS Gateway Endpoint using the format `<BUCKET>.gateway.<REGION>.storjshare.io` including your bucket (e.g., `origin.gateway.us1.storjshare.io`).
2. When you edit the host details on the **Edit this host page**:
    - In the **Name** field, enter any descriptive name for your service if you haven't already done so.
    - In the **Address** field, ensure you've entered the IP address or hostname of your Storj DCS Gateway Endpoint. You entered this information during host creation.
3. When you edit the Transport Layer Security (TLS) area information for your host:
    - If you've set up TLS for your Storj DCS S3 Gateway, leave the **Enable TLS?** default set to **Yes** to secure the connection between Fastly and your origin.
    - Under the **SNI hostname** field, select the checkbox to **Match the SNI hostname to the Certificate hostname**. The address you entered during host creation appears.
    - In the **Certificate hostname** field, enter the IP address or hostname of your Storj DCS S3 Gateway.

Testing your results

By default, we create a DNS mapping called `yourdomain.global.prod.fastly.net`. In the example above, it would be `cdn.example.com.global.prod.fastly.net`. Create a DNS alias for the domain name you specified (e.g., CNAME `cdn.example.com` to `global-nossl.fastly.net`).

Fastly will cache any content without an explicit `Cache-Control` header for 1 hour. You can verify whether you are sending any cache headers using curl. For example:

```
$ curl -I https://cdn.example.com

Accept-Ranges: bytes
Content-Length: 250
Content-Type: application/xml
Server: MinIO/DEVELOPMENT.GOGET
Vary: Origin
Date: Wed, 07 Oct 2020 02:31:27 GMT
```

In this example, no Cache-Control headers are set so the default TTL will be applied.

Enhanced cache control

If you need more control over how different types of assets are cached (e.g., JavaScript files, images), check out our documentation on cache freshness.

Using a Storj DCS bucket for origin hosting

To use a Storj DCS S3 Gateway as an origin with Fastly, you must implement version 4 of Amazon's header-based authentication. You can do this using custom VCL. Start by obtaining the following information from AWS:

Item	Description
Bucket name	The name of your private bucket. When you download items from your bucket, this is the string listed in the URL path or hostname of each object.
Access key	The access key string associated with a Storj DCS Access Grant that has at least read permissions on the bucket.

Item	Description
Secret key	The secret access key paired with the access key above.

Once you have this information, you can configure your Fastly service to authenticate against your private bucket using header authentication by calculating the appropriate header value in VCL.

IMPORTANT

Consider leaving the **Override host** field for the origin blank in your service settings. This setting will override the host header from the snippets shown here and may invalidate the signature that authenticates the information being sent.

Start by creating a regular VCL snippet. Give it a meaningful name, such as `Storj DCS Origin`. When you create the snippet, select **within subroutine** to specify its placement and choose **miss** as the subroutine type. Then, populate the **VCL** field with the following code (be sure to change specific values as noted to ones relevant to your own bucket):

```
declare local var.accessKey STRING;
declare local var.secretKey STRING;
declare local var.storjBucket STRING;
declare local var.storjGateway STRING;
declare local var.region STRING;
declare local var.canonicalHeaders STRING;
declare local var.signedHeaders STRING;
declare local var.canonicalRequest STRING;
declare local var.canonicalQuery STRING;
declare local var.stringToSign STRING;
declare local var.dateStamp STRING;
declare local var.signature STRING;
declare local var.scope STRING;


set var.accessKey = "YOUR_ACCESS_KEY";   # Change this value to
set var.secretKey = "YOUR_SECRET_KEY";   # Change this value to
set var.storjBucket = "YOUR_BUCKET_NAME";   # Change this value
set var.storjGateway = "STORJ-DCS_GATEWAY";   # Change this valu
set var.region = "decentralized";
```

```
20
21
22  if (req.method == "GET" && !req.backend.is_shield) {
23
24    set bereq.http.x-amz-content-sha256 = digest.hash_sha256("");
25    set bereq.http.x-amz-date = strftime({"%Y%m%dT%H%M%SZ"}, now);
26    set bereq.http.host = var.storjBucket "." var.storjGateway;
27    set bereq.url = querystring.remove(bereq.url);
28    set bereq.url = regsuball(urlencode(urldecode(bereq.url.path))
29    set var.dateStamp = strftime({"%Y%m%d"}, now);
30    set var.canonicalHeaders = ""
31      "host:" bereq.http.host LF
32      "x-amz-content-sha256:" bereq.http.x-amz-content-sha256 LF
33      "x-amz-date:" bereq.http.x-amz-date LF
34    ;
35    set var.canonicalQuery = "";
36    set var.signedHeaders = "host;x-amz-content-sha256;x-amz-date"
37    set var.canonicalRequest = ""
38      "GET" LF
39      bereq.url.path LF
40      var.canonicalQuery LF
41      var.canonicalHeaders LF
42      var.signedHeaders LF
43      digest.hash_sha256("")
44    ;
45
46    set var.scope = var.dateStamp "/" var.region "/s3/aws4_request
47
48
49    set var.stringToSign = ""
50      "AWS4-HMAC-SHA256" LF
51      bereq.http.x-amz-date LF
52      var.scope LF
53      regsub(digest.hash_sha256(var.canonicalRequest),"^0x", "")
54    ;
55
56    set var.signature = digest.awsv4_hmac(
57      var.secretKey,
58      var.dateStamp,
59      var.region,
```

```
      "s3",
      var.stringToSign
    );


  set bereq.http.Authorization = "AWS4-HMAC-SHA256 "
      "Credential=" var.accessKey "/" var.scope ", "
      "SignedHeaders=" var.signedHeaders ", "
      "Signature=" + regsub(var.signature,"^0x", "")
    ;

    unset bereq.http.Accept;
    unset bereq.http.Accept-Language;
    unset bereq.http.User-Agent;
    unset bereq.http.Fastly-Client-IP;
  }

```

* * *

📄	**Wasabi Hot Cloud Storage**
🔗	/en/guides/wasabi-hot-cloud-storage

Wasabi Hot Cloud Storage public and private buckets can be used as origins with Fastly.

Using Wasabi as an origin

To make your Wasabi Hot Cloud Storage bucket available through Fastly, follow the steps below.

Creating a new service

Follow the instructions for creating a new service.

1. When you create the new domain and the new backend host:

- In the **Domain Name** field on the **Create a domain** page, enter the hostname you want to use as the URL (e.g., `cdn.example.com`).
- In the **Hosts** field on the **Origins** page, enter the appropriate address for your Wasabi Hot Cloud Storage bucket's region. For the us-east-1 region, enter `<BUCKET>.s3.wasabisys.com`. For all other regions, enter `<BUCKET>.s3.<REGION>.wasabisys.com`, replacing `<REGION>` as appropriate (e.g., `<BUCKET>.s3.eu-central-1.wasabisys.com`).

2. When you edit the host details on the **Edit this host page**:
   - In the **Name** field, enter any descriptive name for your service if you haven't already done so.
   - In the **Address** field, ensure you've entered the appropriate address for your Host (e.g., `<BUCKET>.s3.wasabisys.com`). You entered this information during Host creation.
3. When you edit the Transport Layer Security (TLS) area information for your host:
   - Leave the **Enable TLS?** default set to **Yes** to secure the connection between Fastly and your origin.
   - In the **Certificate hostname** field, enter the same address that appears in the Address field (e.g., `<BUCKET>.s3.wasabisys.com`).
   - Under the **SNI hostname** field, select the checkbox to **Match the SNI hostname to the Certificate hostname**. The address you entered during Host creation appears.
4. In the **Override host** field, enter an appropriate address for your Host (e.g., `<BUCKET>.s3.wasabisys.com`). You entered this information during Host creation.
5. From the **Shielding** menu below the TLS area, select an appropriate shielding location. For more information about this setting and which locations to select, see our enabling shielding information.

Enabling shielding

We strongly encourage you to enable shielding for your origin server. Wasabi imposes soft caps on free egress. Without shielding enabled, Fastly will request the same objects from all Fastly edge POPs instead of just one, which may not follow Wasabi's free egress guidelines.

When you select a shielding location from the **Shielding** menu, choose the location appropriate for your Wasabi Hot Cloud Storage bucket as follows:

Wasabi bucket region	Shielding location
eu-central-1	Amsterdam, NL
us-east-1	Ashburn, VA
us-west-1	Seattle, WA

Read our guidance on choosing a shield location for more information.

Testing your results

By default, we create a DNS mapping called **yourdomain.global.prod.fastly.net**. In the example above, it would be `cdn.example.com.global.prod.fastly.net`. Create a DNS alias for the domain name you specified (e.g., CNAME `cdn.example.com` to `global-nossl.fastly.net`).

Fastly will cache any content without an explicit `Cache-Control` header for 1 hour. You can verify whether you are sending any cache headers using curl. For example:

```
$ curl -I opscode-full-stack.s3.wasabisys.com

HTTP/1.1 200 OK
x-amz-id-2: ZpzRp7IWc6MJ8NtDEFGH12QBdk2CM1+RzVOngQbhMp2f2ZyalkFsZd4qPaLM
x-amz-request-id: ABV5032583242618
Date: Fri, 18 Mar 2012 17:15:38 GMT
Content-Type: application/xml
Transfer-Encoding: chunked
```

In this example, no Cache-Control headers are set so the default TTL will be applied.

Enhancing cache control

If you need more control over how different types of assets are cached (e.g., JavaScript files, images), check out our documentation on cache freshness.

Using private Wasabi Hot Cloud Storage buckets

To use a Wasabi Hot Cloud Storage private bucket with Fastly, you must implement version 4 of Amazon's header-based authentication. You can do this using custom VCL and

following the instructions below.

Before you begin

Make your Wasabi Hot Cloud Storage bucket available to Fastly. Be sure you've set your origin to port 443. This needs to be done before implementing header-based authentication with the instructions below.

Gathering Wasabi information

Start by obtaining the following information from Wasabi:

Item	Description
Bucket Name	The unique name of your Wasabi Hot Cloud Storage bucket. When you download items from your bucket, this is the string listed in the URL path or hostname of each object (e.g., `widget-project`).
Region	The Wasabi region code of the location where your bucket resides (e.g., `us-east-1`).
Access Key ID	The Wasabi access key ID string for an IAM account that has at least read permission on the bucket.
Secret Access Key	The Wasabi secret access key paired with the access key above.

You should review the user access separation document to make sure you are not inadvertently exposing files you didn't intend e.g. allowing ListBucket operations etc. Alternatively you can use the VCL snippet from the bottom of the document to block bucket listing.

Once you have this information, you can configure your Fastly service to authenticate against your Wasabi bucket using header authentication by calculating the appropriate header value in VCL.

Creating a VCL snippet for authentication

Create a regular VCL snippet.

- In the **Name** field, enter `Wasabi protected origin`.

- In the **Type (placement of the snippet)** field, select **within subroutine** then choose `miss (vcl_miss)`.
- In the **VCL** field, place the following code (be sure to change specific values as noted to ones relevant to your own Wasabi bucket):

```
if ( req.request == "GET" && req.backend.is_origin) {

  declare local var.wasabiAccessKey STRING;
  declare local var.wasabiSecretKey STRING;
  declare local var.wasabiBucket STRING;
  declare local var.wasabiRegion STRING;
  declare local var.canonicalHeaders STRING;
  declare local var.signedHeaders STRING;
  declare local var.canonicalRequest STRING;
  declare local var.canonicalQuery STRING;
  declare local var.stringToSign STRING;
  declare local var.dateStamp STRING;
  declare local var.signature STRING;
  declare local var.scope STRING;

  # Supply your own credentials
  set var.wasabiAccessKey = "YOUR_BUCKET_ACCESS_KEY";   # Change
  set var.wasabiSecretKey = "YOUR_BUCKET_SECRET";       # Change
  set var.wasabiBucket = "YOUR_BUCKET_NAME";            # Change
  set var.wasabiRegion = "YOUR_BUCKET_REGION";          # Change

  set bereq.http.x-amz-content-sha256 = digest.hash_sha256("");
  set bereq.http.x-amz-date = strftime({"%Y%m%dT%H%M%SZ"}, now);
  set bereq.http.host = var.wasabiBucket ".s3." var.wasabiRegion
  set bereq.url = querystring.remove(bereq.url);
  set var.dateStamp = strftime({"%Y%m%d"}, now);
  set var.canonicalHeaders = ""
    "host:" bereq.http.host LF
    "x-amz-content-sha256:" bereq.http.x-amz-content-sha256 LF
    "x-amz-date:" bereq.http.x-amz-date LF
  ;
  set var.canonicalQuery = "";
  set var.signedHeaders = "host;x-amz-content-sha256;x-amz-date"
  set var.canonicalRequest = ""
```

```
    "GET" LF
    bereq.url.path LF
    var.canonicalQuery LF
    var.canonicalHeaders LF
    var.signedHeaders LF
    digest.hash_sha256("")
  ;

  set var.scope = var.dateStamp "/" var.wasabiRegion "/s3/aws4_r

  set var.stringToSign = ""
    "AWS4-HMAC-SHA256" LF
    bereq.http.x-amz-date LF
    var.scope LF
    regsub(digest.hash_sha256(var.canonicalRequest),"^0x", "")
  ;

  set var.signature = digest.awsv4_hmac(
    var.wasabiSecretKey,
    var.dateStamp,
    var.wasabiRegion,
    "s3",
    var.stringToSign
  );

  set bereq.http.Authorization = "AWS4-HMAC-SHA256 "
    "Credential=" var.wasabiAccessKey "/" var.scope ", "
  "SignedHeaders=" var.signedHeaders ", "
    "Signature=" + regsub(var.signature,"^0x", "")
  ;
  unset bereq.http.Accept;
  unset bereq.http.Accept-Language;
  unset bereq.http.User-Agent;
  unset bereq.http.Fastly-Client-IP;
  }
```

Creating a VCL snippet to remove added response headers

You may also remove the headers that Wasabi adds to the response. Do this by creating another VCL snippet.

- In the **Name** field, enter `Strip Wasabi response headers`.
- In the **Type (placement of the snippet)** field, select **within subroutine** then select `deliver (vcl_deliver)`.
- In the **VCL** field, place the following code:

```
if ( !req.http.Fastly-Debug ) {
  unset resp.http.x-amz-id-2;
  unset resp.http.x-amz-request-id;
  unset resp.http.server;
}

```

Blocking directory listing

If you don't set up correct IAM privileges you may allow users to list contents of your bucket folders. If you want to disallow that on Fastly please create following snippet

- In the **Name** field, enter `Disallow bucket listing`.
- In the **Type (placement of the snippet)** field, select **within subroutine** then select `recv (vcl_recv)`.
- In the **VCL** field, place the following code:

```
if ( req.url.path ~ "/$" ) {
  error 403;
}

```

> **NOTE**
>
> This article describes how to configure an integration with a service provided by a third party. As stated in our Terms of Service, we do not provide direct support for non-Fastly services.

* * *

Observability guides

Category: About Observability

These articles provide information about monitoring your services via the control panel.

About the Observability pages

/en/guides/about-the-observability-pages

You can use the Observability pages in the Fastly control panel to monitor your Fastly CDN and Compute services.

Before you begin

Be sure you know how to access the web interface controls before learning about the details you'll encounter here.

About the Observability pages

When you click **Observability** in the navigation sidebar, the Account Summary page appears by default. The Account Summary page provides a high-level overview of all your services.

To access additional Observability pages, go to **Observability** in the navigation sidebar and select one of the following options:

- **Services menu**: provides access to the Service Overview page, which displays top metrics for a Fastly service, and the All Services page, which displays aggregated metrics for all of your services.

- **Domains page:** provides real-time and historic visibility into detailed response data for traffic from your domains and subdomains to Fastly.
- **Origins page:** provides real-time and historic visibility into detailed response data for traffic from your origin servers to Fastly.
- **Insights page:** provides insights based on stored log data for your Deliver service, allowing you to proactively identify trends, optimize performance, and troubleshoot and debug issues.
- **Logs menu:** provides access to the Tailing and Explorer pages, where you can view log data for your services.
- **Alerts menu:** provides access to the Overview, Definitions, and Integrations pages, where you can view current and historical alert feeds and configure alert definitions and integrations.
- **Custom Dashboards page:** where you can view and manage custom dashboards that surface relevant metrics for a Fastly service.

The exact graphs displayed on the Observability pages depend on your access permissions and the type of service you create, as well as other products and features you may have purchased.

The data on the Observability pages may also appear grayed out or blank to some users, with no information displayed in the controls, when a service hasn't yet received enough requests for Fastly to display meaningful information about it.

About the controls on the Observability pages

Observability pages use a number of control types to best display information.

> TIP
>
> Looking to rearrange charts or change their names? Check out custom dashboards for details.

Common dashboard controls

Many Observability pages share similar controls to help you manipulate and refine the information displayed on any dashboard.

To the right of each dashboard's name, these controls may appear:

- the **Alerts** link, which opens the Alerts firing window. From this window, you can view firing alerts.
- the **Options** menu allows you to display event markers (vertical lines) on the charts to signify when a new version of a service was activated. With appropriate permissions, it also allows you to edit a dashboard name, clone a dashboard, delete it, copy a link to it, and export the data from the dashboard to a CSV file.
- the **Service configuration** link opens the service configuration page for the service selected in the dashboard.
- the **Create dashboard** button allows you to create a custom dashboard.


Immediately below a dashboard's name, these controls may appear:

- the **Service** menu allows you to specify the service that the metrics are drawn from. From the menu, you can search for a service by ID or name.
- the **Region** menu allows you to limit the displayed metrics on any dashboard to a specific region around the world.
- the **Data Resolution** menu allows you to select how the data is represented for the defined time range.
- the **Time Range** menu allows you to change the timeframe over which metrics will be displayed and to change the time zone from Coordinated Universal Time (UTC) to the time zone identified by your browser. By default, the system displays 1 days worth of static data. The selected timeframe and time zone persist as you navigate between dashboards.
- the **Live** button (which only appears on dashboards for specific services, not the Account Summary dashboard) allows you to change displayed metrics to live data that changes in real time. When viewing the live data stream, the time axis will scroll even if there is no data. You can click **Pause** to pause the live data stream.


Sorting and filtering controls on charts

Some charts, especially those that could potentially display a large number of items, contain sorting and filtering controls that allow you to prioritize which items are viewable first.

For example, the **5xx by Origin** chart on the **Origins** page could potentially display a large amount of data. To mitigate this, a filtering menu allows you to select the 5xx status codes to display.



Similarly, if you were to hover your cursor over a specific origin name in that same chart, additional controls would appear to the right that allow you to limit the displayed data in that chart to just that one origin, without having to choose the origin specifically from the **Origin** menu below the dashboard name.



Controls that provide additional details about charts and metrics

Timestamp indicators. Hovering over any part of a graph displays a timestamp indicator that updates as you move the cursor along with a service version indicator.




Chart value selection menu. A summary menu at the bottom of many charts allows you to view the total, maximum, minimum, mean, latest, and 95th percentile values of for the metrics displayed when appropriate. By default, percentile charts display the mean value while other charts display the total. The summary menu for percentile charts does not include the total metric.




Chart expansion. You can click expand in the double-headed arrow ⤢ in the upper right corner of a chart to access a **Metrics Details** page focused on specific information about the metric being tracked.

A details page typically displays:

- the expanded metrics chart.
- a summary table that automatically updates the total, maximum, minimum, mean, and 95th percentile values for a metric based on the timestamp that you're hovering over on the expanded chart.
- a table that displays the total for the metric over time.

When a **Metrics Details** page appears with a map instead of a chart, expanding that map will provide additional high-level, metrics-specific details about regions on that map (e.g., requests per second and bandwidth details for a specific region on the global POP traffic map for a service).

Links between related data. Some charts may have relevant data in other areas of Observability. For example, on a 5xx metrics chart, you can click the line segments symbol  to the right of the chart name to go directly to the Insights page related to that chart.

About the Account Summary page

The **Account Summary** page provides aggregate metrics for your account for the last two weeks:

- **Requests:** the total number of CDN and Compute requests aggregated across your account.
- **Bandwidth:** the total amount of bandwidth served across all services in your account.
- **Error ratio:** the average ratio of error responses (4xx and 5xx) to the total number of requests across your account.

Links to your latest alerts and custom dashboards are listed at the bottom of the page. Alerts and custom dashboards are disabled by default.

About data latency

When working with dashboards and the metrics they display, keep the following in mind about data:

- We do not report data for time periods that have not yet ended.
- Data with `day` resolution is bucketed based on UTC days and each day's data becomes available around 2am the following day.
- Data with `hour` resolution buckets becomes available approximately 15 minutes after the end of each hour.
- Data with `minute` resolution buckets usually becomes available two minutes after the end of the minute, but can take up to 15 minutes to appear.

If your use case requires data closer to real-time, consider using the generally available real-time API instead.

IMPORTANT

You cannot retrieve minutely historical statistics data older than 35 days from the current date. You cannot retrieve hourly historical statistics data older than 375 days

from the current date. Contact support to discuss your minutely or hourly data needs.

What's next

Dig deeper into details about all areas of the web interface before you move on to working with services.

---

* * *

Category: Alerts

These articles provide basic information about the Alerts feature.

	About alerts
🔗	/en/guides/about-alerts

The Alerts feature lets you set configuration rules, also known as *alert definitions*, that define the conditions that should trigger an alert and how notifications should be handled.

From the Alerts pages, you can view triggered and resolved alert instances and manage your alert definitions and integrations.

Before you begin

The Alerts feature is disabled by default. Anyone assigned the role of superuser can enable a 30-day trial directly in the web interface on the Trials page. After your trial expires, the Alerts feature can be purchased for an account by contacting sales@fastly.com. After your trial expires, the Alerts feature can be purchased for an account by contacting sales@fastly.com and then configured by any superuser or engineer, which will result in changes to your monthly bill.

Accessing the Alerts pages

To access the pages associated with the Alerts feature, go to **Observability** > **Alerts**.

The Alerts menu contains links to the following pages:

- **Overview:** where you can view a historical feed of alerts that are firing and that have been resolved.
- **Definitions:** where you can view and manage alert definitions. An alert definition is a configuration rule that defines when an alert should be triggered and how notifications should be handled.
- **Integrations:** where you can view and manage alert integrations. Alert integrations are external channels that receive notifications when alerts are triggered.

Viewing firing and resolved alert instances

An alert is firing when the condition set is no longer met during an evaluation period. Once triggered, an alert is considered resolved when the defined threshold is no longer being exceeded.

From the Alerts Overview page, click on a firing or resolved alert instance to access the details page for the alert. The alert details page displays a graph of the observed metric. On the graph, a horizontal black line marks the threshold, vertical red bars indicate when the metric went above or below the threshold, and vertical black lines indicate when a new service version was activated. The page also lists all firing and resolved instances of the alert.

From the details page, you can also edit the alert definition by clicking the pencil to the right of the alert definition.

What's next

Read about how alerts are triggered and resolved and then create alert definitions

* * *

	How alerting works
🔗	/en/guides/how-alerting-works

The Alerts feature displays a notification in the Fastly control panel and sends messages to your custom integrations (e.g., Slack channels and webhooks) when a metric:

- exceeds a static threshold
- is below a static threshold
- exceeds a rate-based threshold
- is below a rate-based threshold
- increases by a certain percentage
- decreases by a certain percentage
- increases or decreases by a certain percentage

Alerting when a metric exceeds a static threshold

The Alerts feature supports alerting above a threshold. When creating an alert definition, you can define an above threshold based condition by setting the **Evaluation type** menu to `Above (one minute)`. This alert will fire when the observed metric goes above the specified threshold during an evaluation period at any one minute polling interval. The alert will resolve when there are zero one minute intervals in the evaluation period that exceed the threshold.

Above a static threshold alert example

Let's say you want to be notified in your #website-alerts Slack channel when the number of 5XX responses exceed 1,000 on a single service or all your services. When configuring the alert definition, you choose whether to report on a single service or an aggregate of all services. Then, you set:

- the **Data source** menu to `Historic Stats`
- the **Metric** menu to `status_5xx`
- the **Evaluation type** menu to `Above (one minute)`
- the **Threshold** field to `1000`
- the **Evaluation period** menu to `5 minutes`
- the **Integration(s)** menu to `website-alerts`

After saving the alert definition, the system starts evaluating the observed metric in 5 minute rolling time windows (the Evaluation period). During a polling minute in one of those evaluation periods, the observed metric goes above 1,000 (the Threshold):

Evaluation period minute	Number of 5XX responses	Threshold exceeded
1	988	No
2	765	No
3	1021	Yes
4	843	No
5	1000	No

At the end of the fifth minute of that evaluation period, an alert is triggered because the observed metric went above the threshold during the third minute of the evaluation period. Notifications are also sent. Specifically, the Fastly application indicates that an alert has been triggered via the Alert bell and a message is sent to the #website-alerts Slack channel.

That alert then resolves at the end of this evaluation period because there are zero one minute intervals in the evaluation period that exceed the threshold:

Evaluation period minute	Number of 5XX responses	Threshold exceeded
1	576	No
2	674	No
3	516	No
4	577	No
5	732	No

Alerting when a metric is below a static threshold

The Alerts feature supports alerting below a threshold. When creating an alert definition, you can define a below threshold based condition by setting the **Evaluation type** menu to `Below (two minutes)`. This alert will fire when the observed metric remains below the specified threshold for two consecutive minutes in an evaluation period. The alert will

resolve when there aren't two consecutive minutes in an evaluation period that are below the threshold. We look for two consecutive minutes in an evaluation period because network latency occasionally delays metric aggregation across POPs, and we want to ensure accuracy and limit false positives.

Below a static threshold alert example

Let's say you want to be notified in your #website-alerts Slack channel when the number of 2XX responses is below 500 on a single service or all your services. When configuring the alert definition, you choose whether to report on a single service or an aggregate of all services. Then, you set:

- the **Data source** menu to `Historic Stats`
- the **Metric** menu to `status_2xx`
- the **Evaluation type** menu to `Below (two minutes)`
- the **Threshold** field to `500`
- the **Evaluation period** menu to `5 minutes`
- the **Integration(s)** menu to `website-alerts`

After saving the alert definition, the system starts evaluating the observed metric in 5 minute rolling time windows (the Evaluation period). During two consecutive polling minutes in one of those evaluation periods, the observed metric is below 500 (the Threshold):

Evaluation period minute	Number of 2XX responses	Below the threshold
1	1098	No
2	1254	No
3	372	Yes
4	415	Yes
5	500	No

At the end of the fifth minute of that evaluation period, an alert is triggered because the observed metric was below the threshold during the third and forth minutes of the evaluation period. Notifications are also sent. Specifically, the Fastly application indicates

that an alert has been triggered via the Alert bell and a message is sent to the #website-alerts Slack channel.

That alert then resolves at the end of this evaluation period because there aren't two consecutive minutes in the evaluation period that are below the threshold:

Evaluation period minute	Number of 2XX responses	Below the threshold
1	1108	No
2	285	Yes
3	1284	No
4	1065	No
5	396	Yes

Alerting when a metric exceeds a rate-based threshold

The Alerts feature supports alerting above a rate of all requests. When creating an alert definition, you can define an above rate-based condition by selecting an error rate or success rate metric to observe and setting the **Evaluation type** menu to `Above (one minute)`. This alert will fire when the observed metric goes above the specified percentage of overall requests during an evaluation period at any one minute polling interval. The alert will resolve when there are zero one minute intervals in the evaluation period that exceed the threshold.

Above a rate-based threshold alert example

Let's say you want to be notified in your #website-alerts Slack channel when the number of 4XX responses exceeds 5% of all responses sent by a single service or all your services. When configuring the alert definition, you choose whether to report on a single service or an aggregate of all services. Then, you set:

- the **Data source** menu to `Historic Stats`
- the **Metric** menu to `4XX Error Rate`
- the **Evaluation type** menu to `Above (one minute)`
- the **Threshold** menu to `5%`
- the **Evaluation period** menu to `5 minutes`

- the **Integration(s)** menu to `website-alerts`

After saving the alert definition, the system starts evaluating the observed metric in 5 minute rolling time windows (the Evaluation period). During a polling minute in one of those evaluation periods, the observed metric goes above 5% (the Threshold):

Evaluation period minute	Number of 4XX responses	Total number of requests	Percentage of overall requests	Threshold exceeded
1	0	988	0%	No
2	13	765	1.67%	No
3	64	1021	6.27%	Yes
4	14	843	1.66%	No
5	3	1000	0.3%	No

At the end of the fifth minute of that evaluation period, an alert is triggered because the observed metric went above the threshold during the third minute of the evaluation period. Notifications are also sent. Specifically, the Fastly application indicates that an alert has been triggered via the Alert bell and a message is sent to the #website-alerts Slack channel.

That alert then resolves at the end of this evaluation period because there are zero one minute intervals in the evaluation period that exceed the threshold:

Evaluation period minute	Number of 4XX responses	Total number of requests	Percentage of overall requests	Threshold exceeded
1	19	576	3.30%	No
2	30	674	4.45%	No
3	14	516	2.71%	No
4	0	577	0%	No
5	0	732	0%	No

Alerting when a metric is below a rate-based threshold

The Alerts feature supports alerting below a rate of all requests. When creating an alert definition, you can define a below rate-based condition by selecting an error rate or success rate metric to observe and setting the **Evaluation type** menu to `Below (two minutes)`. This alert will fire when the observed metric goes below the specified percentage of overall requests during an evaluation period at any one minute polling interval. The alert will resolve when there are zero one minute intervals in the evaluation period that exceed the threshold.

Below a rate-based threshold alert example

Let's say you want to be notified in your #website-alerts Slack channel when the Success Rate, that is, the percentage of responses with non-5XX codes, falls below 80% on a single service or all your services. When configuring the alert definition, you choose whether to report on a single service or an aggregate of all services. Then, you set:

- the **Data source** menu to `Historic Stats`
- the **Metric** menu to `Success Rate`
- the **Evaluation type** menu to `Below (two minutes)`
- the **Threshold** field to `80%`
- the **Evaluation period** menu to `5 minutes`
- the **Integration(s)** menu to `website-alerts`

After saving the alert definition, the system starts evaluating the observed metric in 5 minute rolling time windows (the Evaluation period). During a polling minute in one of those evaluation periods, the observed metric goes below 80% (the Threshold):

Evaluation period minute	Success Rate	Below the threshold
1	99%	No
2	79%	Yes
3	75%	Yes
4	95%	No
5	90%	No

At the end of the fifth minute of that evaluation period, an alert is triggered because the observed metric was below the threshold during two consecutive minutes in the evaluation period. Notifications are also sent. Specifically, the Fastly application indicates that an alert has been triggered via the Alert bell and a message is sent to the #website-alerts Slack channel.

That alert then resolves at the end of this evaluation period because there aren't two consecutive minutes in the evaluation period that are below the threshold:

Evaluation period minute	Success Rate	Below the threshold
1	90%	No
2	95%	No
3	99%	No
4	99%	No
5	89%	No

Alerting when a metric increases by a certain percentage

The Alerts feature supports alerting when a metric increases by a certain percentage. When creating an alert definition, you can define a percentage increase condition by selecting `Percentage change` under the **Alert type** menu and selecting `Increases by` under the **Evaluation type** menu. This alert will fire when the observed metric increases by a specified percentage and by comparing the first and last minute of the **Comparison period**. The alert will resolve when the percentage calculation in the comparison period no longer meets the percentage condition criteria.

Percentage increase alert example

Let's say you want to be notified in your #website-alerts Slack channel when the number of 4XX responses increases by 5% on a single service excluding 4XX values less than 10. When configuring the alert definition, you choose to report on a single service. Then, you set:

- the **Data source** menu to `Historic Stats`
- the **Metric** menu to `4XX`
- the **Alert type** menu to `Percentage change`

- the **Evaluation type** menu to `Increases by`
- the **Percentage** field to `5%`
- the **Comparison period** menu to `5 minutes`
- the **Excluded values** field to `10`
- the **Integration(s)** menu to `website-alerts`

After saving the alert definition, the system starts evaluating the observed metric in 5 minute rolling time windows (the Comparison period). During a comparison period, the observed metric percentage calculation increases by 5%:

Comparison period minute	Number of 4XX responses	Comparison used	Excluded?
1	9	No	Yes
2	15	Yes	No
3	14	No	No
4	13	No	No
5	12	No	No
5	25	Yes	No

At the sixth minute and the end of the five minute comparison period, an alert is triggered because the observed metric and percentage calculation increased by at least 5% (25 - 15 / 25 = 0.4 × 100 = 40% > 5%). Notifications are also sent. Specifically, the Fastly application indicates that an alert has been triggered via the Alert bell and a message is sent to the #website-alerts Slack channel.

That alert then resolves when the percentage calculation conditions are no longer met.

Alerting when a metric decreases by a certain percentage

The Alerts feature supports alerting when a metric decreases by a certain percentage. When creating an alert definition, you can define a percentage decrease condition by selecting `Percentage change` under the **Alert type** menu and selecting `Decreases by` under the **Evaluation type** menu. This alert will fire when the observed metric decreases by a specified percentage and by comparing the first and last minute of the **Comparison**

period. The alert will resolve when the percentage calculation in the comparison period no longer meets the percentage condition criteria.

Percentage decrease alert example

Let's say you want to be notified in your #website-alerts Slack channel when the number of 2XX responses decreases by 40% on a single service. When configuring the alert definition, you choose to report on a single service. Then, you set:

- the **Data source** menu to `Historic Stats`
- the **Metric** menu to `2XX`
- the **Alert Type** menu to `Percentage change`
- the **Evaluation type** menu to `Decreases by`
- the **Percentage** field to `40%`
- the **Comparison period** menu to `5 minutes`
- the **Integration(s)** menu to `website-alerts`

After saving the alert definition, the system starts evaluating the observed metric in 5 minute rolling time windows (the Comparison period). During a comparison period, the observed metric percentage calculation decreases by 40%:

Comparison period minute	Number of 2XX responses	Comparison used
1	100	No
2	90	No
3	85	No
4	70	No
5	60	Yes

At the end of the fifth minute of that comparison period, an alert is triggered because the observed metric and percentage calculation decreased by at least 40% (60 - 100 / 100 = 0.4 x 100 = 40%). Notifications are also sent. Specifically, the Fastly application indicates that an alert has been triggered via the Alert bell and a message is sent to the #website-alerts Slack channel.

That alert then resolves when the percentage calculation conditions are no longer met.

Alerting when a metric either increases or decreases by a certain percentage

The Alerts feature supports alerting when a metric increases or decreases by a certain percentage. When creating an alert definition, you can define a percentage increase or decrease condition by selecting `Percentage change` under the **Alert type** menu and selecting `Increases or decreases by` under the **Evaluation type** menu. This alert will fire when the observed metric either increases or decreases by a specified percentage and by comparing the first and last minute of the **Comparison period**. The alert will resolve when the percentage calculation in the comparison period does not meet the percentage condition criteria.

Alerting when a metric exceeds a static threshold during the entire evaluation period

The Alerts feature supports alerting when all consecutive minutes within an evaluation period exceed a threshold. When creating an alert definition, you can define an above threshold based condition by setting the **Evaluation type** menu to `Above (all minutes)`. This alert will fire when the observed metric goes above the specified threshold during the entire evaluation period. The alert will resolve when the conditions are no longer met.

Percentage decrease alert example

Let's say you want to be notified in your #website-alerts Slack channel when the number of 5XX responses exceed 1,000 on a single service or all your services over the entire evaluation period. When configuring the alert definition, you choose whether to report on a single service or an aggregate of all services. Then, you set:

- the **Data source** menu to `Historic Stats`
- the **Metric** menu to `5XX`
- the **Alert Type** menu to `Threshold`
- the **Evaluation type** menu to `Above (all minutes)`
- the **Threshold** field to `1000`
- the **Evaluation period** menu to `5 minutes`

- the **Integration(s)** menu to `website-alerts`

After saving the alert definition, the system starts evaluating the observed metric in 5 minute rolling time windows (the Evaluation period). During an evaluation period and polling every minute, the observed metric goes above 1,000 (the Threshold) at every minute:

Evaluation period minute	Number of 5XX responses	Threshold exceeded
1	1001	Yes
2	1110	Yes
3	1021	Yes
4	1050	Yes
5	1032	Yes

At the end of the fifth minute of that evaluation period, an alert is triggered because the observed metric went above the threshold during the entire evaluation period. Notifications are also sent. Specifically, the Fastly application indicates that an alert has been triggered via the Alert bell and a message is sent to the #website-alerts Slack channel.

That alert then resolves when the percentage calculation conditions are no longer met:

Evaluation period minute	Number of 5XX responses	Threshold exceeded
1	900	No
2	1001	Yes
3	516	No
4	577	No
5	732	No

* * *

Managing alert definitions

/en/guides/managing-alert-definitions

An alert definition is a configuration rule that defines when an alert should be triggered and how notifications should be handled.

Limitations and considerations

The maximum number of alert definitions that can exist at any one time per customer is 50. Contact support to discuss raising this limit.

About alert definitions

An alert definition is a configuration rule that defines when an alert should be triggered and how notifications should be handled. Specifically, it outlines:

- the observed service, data pipeline, and metric.
- the set of conditions that must be met for an alert to trigger.
- the custom destinations for alert messages (e.g., Slack channels and webhooks).


The condition set defines the threshold, the evaluation period, and whether the alert should trigger when the metric exceeds or remains below the threshold or rate. Specifically:

- A threshold is a static number or a percentage of all requests that the observed metric must either be above or below for the alert to trigger.
- The evaluation period is the number of minutes during which the observed metric is evaluated every minute to determine if the metric has gone above, remained below, or exceeded the threshold during the entire evaluation period.
- The comparison period is the length of time used to compare and evaluate the percentage condition. The first and last minutes of the period will be used to calculate the percentage.

Creating alert definitions

To create an alert definition, start by navigating to the Add alert definition page using one of these methods:

- On the **Overview** page in the **Firing** section, click **Add alert definition**.
- On the **Alert definitions** page, click **Add alert definition**.



Next, fill out the general alert fields as follows:

1. In the **Name** field, enter the name of the alert.
2. In the **Description** field, enter a description of the alert definition.
3. Leave the **All services (aggregated)** value selected if you want to monitor all your services or select **Single service** if you want to monitor a specific service.

4. If you selected **Single service**, fill out the following fields:
    - From the **Service** menu, select a service.
    - From the **Data Source** menu, select a data pipeline. Data pipeline options include Historic Stats, Origin Inspector, and Domain Inspector.

Next, define the metric that you want to monitor:

1. If you're monitoring all services or selected `Historic Stats` from the **Data source** menu then, from the **Metric** menu, select the metric that you want to monitor.
2. If you selected `Domain Inspector` from the **Data source** menu, fill out the following fields:
    - From the **Domains** menu, select the domains that you want to monitor.
    - From the **Metric** menu, select the metric that you want to monitor.
3. If you selected `Origin Inspector` from the **Data source** menu, fill out the following fields:
    - From the **Origins** menu, select the origins that you want to monitor.
    - From the **Metric** menu, select the metric that you want to monitor.

Once you've done that, define the conditions that will trigger the alert:

If you selected an error rate or success rate alert type:

1. From the **Evaluation type** menu, select whether the alert should be triggered when the metric is above or below a percentage of overall requests.
2. From the **Threshold** menu, select a percentage of overall requests that the metric must be above or below for the alert to trigger.
3. From the **Evaluation period** menu, select the number of minutes during which the observed metric is evaluated every minute to determine if the metric is above or below the specified threshold. Options include 2 minutes, 5 minutes, 15 minutes, and 30 minutes.

If you selected a threshold alert:

1. From the **Evaluation type** menu, select whether the alert should be triggered when the metric is above or below the threshold.
2. In the **Threshold field**, enter the number that the metric must be above or below for the alert to trigger. To set this field, you can also click and drag the threshold line on the

graph.

3. From the **Evaluation period** menu, select the number of minutes during which the observed metric is evaluated every minute to determine if the metric is above or below the specified threshold. Options include 2 minutes, 5 minutes, 15 minutes, and 30 minutes.

If you selected a percentage change alert:

- From the **Evaluation type** menu, select whether the alert should be triggered when the metric increases by, decreases by, or increases or decreases by.
- In the **Percent field**, enter the percent that the metric must either increase by, decrease by, or increases or decreases by for the alert to trigger.
- From the **Comparison Period** menu, select the period during which the observed percentage is evaluated. The first and last minute of the period will be used to calculate the percentage. Options include 2 minutes, 5 minutes, 15 minutes, and 30 minutes.
- *(Optional)* From the **Excluded Values** menu, select the values below this range that will be disregarded and not used to trigger an alert.

Next, optionally specify where alert notifications should be sent:

1. *(Optional)* From the **Integrations(s)** menu, select the notification channels for the alert.
2. *(Optional)* Click **Test Alert**. A test notification is sent to the notification channel you selected.

Finally, click **Save Alert** to save the alert. The Alert definitions page appears.

Editing alert definitions

To edit an alert definition, start by navigating to the Edit alert definition page using one of these methods:

- On the **Overview** page in the **Firing** section, click an instance of an alert definition that you want to edit and then click **Edit alert definition**.
- On the **Alert definitions** page, click the pencil to the right of the alert definition that you want to edit.

Next, update and save the alert definition:

1. Fill out the **Edit alert definition** fields as follows:
    - In the **Name** field, enter the name of the alert.
    - In the **Description** field, enter a description of the alert definition.
    - If the value of the **Data source** menu is `Domain Inspector` then, from the **Domains** menu, select the domains that you want to monitor.
    - If the value of the **Data source** menu is `Origin Inspector` then, from the **Origins** menu, select the origins that you want to monitor.
    - From the **Metric** menu, select the metric that you want to monitor.
    - Under the **Alert type** menu, select whether the alert will trigger from a threshold or percentage change.
    - For thresholds and from the **Evaluation type** menu, select whether the alert should be triggered when the metric is above or below the threshold.
    - For percentage change and from the **Evaluation type** menu, select whether the alert should be triggered when the metric increases by, decreases by, or increases or decreases by.
    - In the **Threshold** field, enter the number that must be above or below for the alert to trigger. To set this field, you can also click and drag the threshold line on the graph.
    - In the **Percent** field, enter the percent that the metric must either increase by, decrease by, or increases or decreases by for the alert to trigger.
    - From the **Evaluation period** menu, select the number of minutes during which the observed metric is evaluated every minute to determine if the metric is above or below the specified threshold. Options include 2 minutes, 5 minutes, 15 minutes, and 30 minutes.
    - From the **Comparison period** menu, select the period during which the observed percentage is evaluated. The first and last minute of the period will be used to calculate the percentage. Options include 2 minutes, 5 minutes, 15 minutes, and 30 minutes.
    - From the **Integration(s)** menu, optionally select or remove notification channels for the alert.
2. *(Optional)* Click **Test Alert**. A test notification is sent to the notification channel you selected.

3. Click **Save Alert** to save the alert.

Searching alert definitions

From the **Alert definitions** page, you can search for an existing alert definition by entering a name in the search field. You can also filter definitions using the service filter.

Deleting alert definitions

From the **Alert definitions** page, you can delete alert definitions by clicking the trash to the right of the alert definition that you want to delete. The alert definition is removed from the Alert definitions page.

---

* * *

	Managing alert integrations
🔗	/en/guides/managing-alert-integrations

Alert integrations are external channels that receive notifications when alerts are triggered. When creating an alert definition, you specify the alert integrations that should be used. Multiple alert definitions can use the same alert integration.


Accessing alert definitions

To view a list of your alert definitions, follow these steps:

1. Log in to the Fastly control panel.
2. Go to **Observability** > **Alerts** > **Definitions**. The Alert definitions page appears.

Creating alert integrations

To create an alert integration, follow these steps:



1. In Slack, add an incoming webhook and copy the URL for the webhook.
2. Log in to the Fastly control panel.
3. Go to **Observability** > **Alerts** > **Integrations**.
4. Click **Add alert integration**.
5. Fill out the **Add integration** controls as follows:
    - Click **Slack**.
    - In the **Name** field, enter the name of the integration.
    - In the **Webhook URL** field, enter the URL of the webhook you created in the first step.
    - In the **Description** field, enter a description of the notification channel.
6. Click **Save integration**. The integration is added to the Alert integrations page.

1. Log in to the Fastly control panel.
2. Go to **Observability** > **Alerts** > **Integrations**.
3. Click **Add alert integration**.
4. Fill out the **Add integration** controls as follows:
    - Click **Email**.
    - In the **Name** field, enter the name of the integration.
    - In the **Email** field, enter the email address that should receive the alert notifications.

- In the **Description** field, enter a description of the integration.

5. Click **Save integration**. An email asking you to confirm the address you entered in the **Email** field is sent to the email address you entered.
6. Navigate to the relevant email account and open the confirmation email from Fastly.
7. Click **Confirm email address**. Your email address is verified and the integration is added to the Alert integrations page.

1. In PagerDuty, create a new service and copy the integration key. Be sure to set the escalation policy and integration method to **Use Our API Directly**.
2. Log in to the Fastly control panel.
3. Go to **Observability** > **Alerts** > **Integrations**.
4. Click **Add alert integration**.
5. Fill out the **Add integration** controls as follows:
   - Click **PagerDuty**.
   - In the **Name** field, enter the name of the integration.
   - In the **Service API Key** field, enter the integration key you created in the first step.
   - In the **Description** field, enter a description of the notification channel.
6. Click **Save integration**. The integration is added to the Alert integrations page.

1. In Microsoft Teams, add an incoming webhook and copy the URL for the webhook.
2. Log in to the Fastly control panel.
3. Go to **Observability** > **Alerts** > **Integrations**.
4. Click **Add alert integration**.
5. Fill out the **Add integration** controls as follows:
   - Click **Microsoft Teams**.
   - In the **Name** field, enter the name of the integration.
   - In the **Webhook URL** field, enter the URL of the webhook you created in the first step.

- In the **Description** field, enter a description of the notification channel.

6. Click **Save integration**. The integration is added to the Alert integrations page.

1. In New Relic, create a new License key on the account where you want to ingest data. Make note of both the License key and Account ID.
2. Log in to the Fastly control panel.
3. Go to **Observability** > **Alerts** > **Integrations**.
4. Click **Add alert integration**.
5. Fill out the **Add integration** controls as follows:
   - Click **New Relic**.
   - In the **Name** field, enter the name of the integration.
   - In the **License key** field, enter the license key you created in the first step.
   - In the **Account ID** field, enter the account ID you obtained in the first step.
   - In the **Description** field, enter a description of the notification channel.
6. Click **Save integration**. The integration is added to the Alert integrations page.

1. Log in to the Fastly control panel.
2. Go to **Observability** > **Alerts** > **Integrations**.
3. Click **Add alert integration**.
4. Fill out the **Add integration** controls as follows:
   - Click **Custom webhook**.
   - In the **Name** field, enter the name of the integration.
   - In the **Webhook URL** field, enter the webhook URL that should receive the alert notifications.
   - In the **Description** field, enter a description of the notification channel.
5. Click **Save integration**. The integration is added to the Alert integrations page.

NOTE

Using a Slack webhook URL won't work with this integration. Use the Slack integration instead.

Editing alert integrations

To edit an alert integration, follow these steps:

1. Log in to the Fastly control panel.
2. Go to **Observability** > **Alerts** > **Integrations**.
3. Click the pencil to the right of the alert integration that you want to edit.
4. Edit the necessary fields. Override locked fields by clicking **Override** then confirming you want to edit the field.

   NOTE

   If you change the type of integration, you may need to fill out additional fields. Refer to Creating alert integrations for field descriptions for each integration.

5. Click **Save integration**.

Deleting alert integrations

To delete an alert integration, follow these steps:

1. From the **Alert integrations** page, click the trash to the right of the alert integration that you want to delete.
2. Click **Confirm and delete**. The alert integration is removed from the Alert integrations page.

* * *

Category: Observability Dashboards

These articles provide information about monitoring your services via the control panel.

About the Custom Dashboards page

/en/guides/about-the-custom-dashboards-page

The Custom Dashboards page is where you access Observability dashboards that you've customized. You can customize dashboards to include metrics for a service to make them more visible and accessible in a single location.

Before you begin


Custom dashboards are disabled by default and are only available to customers who have purchased an Observability package. To purchase and enable this feature, contact sales@fastly.com. Once enabled, only users assigned the role of superuser or engineer can edit custom dashboards, but all account users will be able to view them.

Be sure you know how to access the web interface controls before learning about the details you'll encounter here.

About the Custom Dashboards page

The Custom Dashboards page provides a list of clickable links to all custom dashboards you've created. You can view a complete list of custom dashboards associated with your account, including the name of the user who created them and the last date on which each was updated. To access this page, go to **Observability** > **Custom dashboards**.

Clicking on each column in the displayed list will sort the entire list based on that content type. You can use the search box to search for a specific dashboard by name. You can also filter dashboards based on which user created them by selecting that name from the **Created by** menu.



Clicking **Create new dashboard** above the dashboard list takes you to the Create Dashboard page.

What's next

Dig deeper into details about all areas of the web interface before you move on to working with services.

---

* * *

📄	**About the Domains page**
🔗	/en/guides/about-the-domains-page

The Domains page gives you access to the Domain Inspector dashboard, which provides real-time and historic visibility into response data for traffic from your domains and subdomains to a Fastly Deliver service. To access the Domains page, go to **Observability** > **Domains**.

Before you begin

Domain Inspector is disabled by default. Anyone assigned the role of superuser or engineer can enable a 30-day trial directly in the web interface either on the Domains page or on the

Trials page. After your trial expires, Domain Inspector can be purchased for an account by contacting sales@fastly.com and then enabled for a service by any superuser or engineer, which will result in changes to your monthly bill.

Domain Inspector is not supported on services that use IP-to-service pinning.

Be sure you know how to access the web interface controls before learning about the details you'll encounter here.

Enabling and disabling Domain Inspector

> **NOTE**
>
> To enable or disable this product via the API once you've purchased it, check out our developer documentation.

Enabling Domain Inspector

To enable Domain Inspector for a service:

1. Log in to the Fastly control panel.
2. Go to **Observability** > **Domains**.
3. Click the **Monitor domain responses** switch to the **On** position to enable Domain Inspector for the service.

Once enabled, any user on your account can start viewing real-time and historic stats metrics about your domains immediately. Historic metrics usually become available two minutes after the end of each minute, but can take up to 15 minutes to appear.

Disabling Domain Inspector

To disable Domain Inspector for a service:

1. Log in to the Fastly control panel.
2. Go to **Observability** > **Domains**.
3. Click the **Monitor domain responses** switch to the **Off** position to disable Domain Inspector for the service.

Once disabled, we stop collecting real-time and historic stats metrics about your domains.

About the Domain Inspector dashboard

The Domain Inspector dashboard displays a wide variety of metrics to help you understand ongoing activity with the domains associated with your services.

Aggregate metrics

Once Domain Inspector is enabled for your account, the **Domain Inspector** dashboard displays a series of aggregate metrics tiles below the page controls.

When you select **All domains** from the **Domain** menu, these aggregate metrics appear:

- **Total domains:** the total number of domains, active or inactive, configured for this account.
- **Monthly active domains:** the total number of domains active within the last 30 days.
- **Total responses:** the number of responses from all active domains.
- **Bandwidth:** the bandwidth, in bytes, for all active domains.
- **Average error ratio:** the average ratio of error responses for all active domains.

When you select a specific domain from the **domain** menu, these aggregate metrics appear:

- **Responses:** the number of responses for this domain.
- **Average error ratio:** the average ratio of error responses for this domain.
- **Edge Hit Ratio:** the percentage of cache hits to all cacheable content for this domain.
- **Bandwidth:** the bandwidth, in bytes, for this domain.
- **Origin offload bytes:** the average amount of content, in bytes served, from the edge for this domain.

Metrics for all domains

When you select **All domains** from the **Domain** menu, the dashboard displays the following metrics tiles below the aggregate metrics tiles:

- **5xx by Domain:** the number of 5xx type (server error) HTTP response status codes delivered by each domain.

- **4xx by Domain:** the number of 4xx type (client error) HTTP response status codes delivered by each domain.
- **Requests by Domain:** the number of requests processed at the edge by each domain.
- **Bandwidth by Domain:** total number of bytes delivered for each domain.
- **3xx by Domain:** the number of 3xx type (redirection) HTTP response status codes delivered by each domain.
- **2xx Status Codes by Domain:** the number of 2xx type (success) HTTP response codes delivered by each domain.

Metrics for specific domains

When you select any single domain from the **Domain** menu, the **Domain Inspector** dashboard displays the following metrics:

- **Edge Status 5xx Details:** the distribution of 5xx (server) status codes delivered from the edge.
- **Origin Status 5xx Details:** the distribution of 5xx (server) status codes delivered from the domain's origin.
- **Edge Status 4xx Details:** the distribution of 4xx (server) status codes delivered from the edge.
- **Origin Status 4xx Details:** the distribution of 4xx (server) status codes delivered from the domain's origin.
- **Edge Hit Ratio:** the percentage of cache hits to all cacheable content over time.
- **Edge Hit Ratio Percentage:** the percentage of cache hits to all cacheable content.
- **Origin Offload:** the average amount of content, in bytes served, from the edge.
- **Origin Offload Percentage:** the percentage of content delivered from the edge compared to what was delivered from your origin for a domain.
- **Edge Response Status Codes:** the number of response status codes delivered from the edge.
- **Origin Response Status Codes:** the number of status response codes from the domain's origin.
- **Edge Requests:** the number of requests received at the edge.

- **Origin Requests:** the number of origin requests fetched for a domain.
- **Edge Status 3xx Details:** the distribution of 3xx (server) status codes delivered from the edge.
- **Origin Status 3xx Details:** the distribution of 3xx (server) status codes delivered from the domain's origin.
- **Edge Status 2xx Details:** the distribution of 2xx (server) status codes delivered from the edge.
- **Origin Status 2xx Details:** the distribution of 2xx (server) status codes delivered from the domain's origin.
- **Bandwidth by Domain:** total number of bytes delivered for a domain.

What's next

Dig deeper into details about all areas of the web interface before you move on to working with services.

---

* * *

📄	**About the Insights page**
🔗	/en/guides/about-the-insights-page

The Insights page provides insights based on stored log data for your Deliver service, allowing you to proactively identify trends, optimize performance, and troubleshoot and debug issues. To access the Insights page, go to **Observability** > **Insights**.

Before you begin

Log Explorer & Insights is disabled by default. Anyone assigned the role of superuser can enable a 30-day trial directly in the web interface either on the Insights page or on the Trials page. After your trial expires, Log Explorer & Insights can be purchased for an account by contacting sales@fastly.com and then enabled for a service by any superuser or engineer, which will result in changes to your monthly bill.

Be sure you know how to access the web interface controls before learning about the details you'll encounter here.

Enabling and disabling Log Explorer & Insights

> **NOTE**
>
> To enable or disable Log Explorer & Insights via the API, check out our developer documentation.

Enabling Log Explorer & Insights

To enable Log Explorer & Insights for a service:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Go to **Observability** > **Insights**.
4. Click the **Enable Insights and Log Explorer** switch to the `ON` position to enable Log Explorer & Insights for the service.

Once enabled, any user on your account can start viewing log data and metrics on the Explorer and Insights pages within a few minutes if you're receiving requests to your service.

Disabling Log Explorer & Insights

To disable Log Explorer & Insights for a service:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Go to **Observability** > **Insights**.
4. Click the **Enable Insights and Log Explorer** switch to the `OFF` position to disable Log Explorer & Insights for the service.

About the Insights page

The Insights page provides insights based on stored log data for your Deliver services. For each service, the page displays the following charts:

- **Top 10 5xx Error URLs:** The top ten URLs with the highest percentage of 5xx errors.
- **Top 10 4xx Error URLs:** The top ten URLs with the highest percentage of 4xx errors.
- **Top 10 503 Error Responses:** The top ten responses with the highest percentage of 503 errors.

> **NOTE**
>
> For meaningful insights from Top 10 503 Error Responses, avoid storing values other than legitimate HTTP responses in the response reason when logging data. To change the response to something other than a legitimate HTTP response, consider creating a synthetic response to prevent response field values appearing as redacted information.

- **HTTP Request Response Status:** The percentage distribution of requests by HTTP response status codes. Clicking on a status type in the graph allows you to drill down to see more information for that particular status type. For example, if you click the bar for 2xx, you can see the percentage of status codes in the 2xx range, and if you click a specific status code, you can see the number of requests for that status code by URL.
- **5xx Errors by Type:** The 5xx error types expressed as a percentage of total request volume. Clicking on an error type allows you to see the percentage of errors by URL.
- **4xx Errors by Type:** The 4xx error types expressed as a percentage of total request volume. Clicking on an error type allows you to see the percentage of errors by URL.
- **Top 10 URLs by Misses:** The top ten URLs with the highest percentage of requests that weren't served from cache.
- **Top 10 URLs by Bandwidth:** The top ten URLs consuming the most bandwidth by percentage.
- **Top 10 URLs by Response Time:** The top ten URLs taking the most time to serve. Measures the delay between the request sent by the browser and the receiving of the last byte of the related response. Shows the p95 time to last byte.
- **Top Browsers By Requests:** The top browsers by request percentage. Clicking on a browser type in the graph allows you to see the distribution by browser version.
- **Top Devices By Requests:** The top devices by request percentage.

- **Top OS By Requests** The top operating systems by request percentage.
- **Top Content Type By Requests:** The top content types by request percentage.
- **Top 10 URLs by Request:** The top ten URLs by request percentage.
- **Requests by Client Location:** A geographical map showing the request percentage by client location. Hover the cursor over a specific location in the map to display the specific metrics for that location. The table below the map displays for each location the percentage of errors, hits, misses, synthetic responses, and passes.

About the controls on the Insights page

You can access more details for a chart by clicking the expand icon ⤢ to access the Details page, which contains detailed information about the metric being tracked. Specifically, the Details page typically displays:

- an expanded view of the chart.
- a table that displays a list of up to 100 URLs.
- a button to open the Explorer page to view logs related to the chart

In addition, you can filter the data displayed on the Insights and Details pages by:

- selecting the **Service** the request was made to.
- entering the **Domain** the request was made to.
- selecting the **Region** that received the request.
- selecting the **Point of Presence** that received the request.
- specifying a **Time Range**.

Some charts allow you to drill down into the data by clicking the drill down icon ↓. For example, you can drill down into a specific HTTP response code in the HTTP Request Response Status chart to see the top objects returning that HTTP response code. To remove the filter, click the drill up icon ↑ or **All data**.

What's next

Dig deeper into details about all areas of the web interface before you move on to working with services.

* * *

About the Logs menu

/en/guides/about-the-logs-menu

The Logs menu contains links to two pages that provide access to log data for your services:

- **Tailing:** provides access to Compute log tailing, allowing you to view custom log messages from your Compute application. Specifically, the Tailing feature streams your Compute application's logs to the Fastly control panel so you can debug your application without setting up a third-party logging tool.
- **Explorer:** allows you to view, filter, and analyze log entries for a service. All data is sampled.

Before you begin

The Explorer page is part of the Log Explorer & Insights feature, which is disabled by default. To enable this feature, refer to the About the Insights page guide.

Be sure you know how to access the web interface controls before learning about the details you'll encounter here.

About the Tailing page

The Tailing page provides a real-time live stream of the log outputs for a Compute service. Streamed outputs can include any output sent to the standard output stream (`stdout`) and the standard error stream (`stderr`), as well as any runtime errors encountered by the application. For each log, the Tailing page displays the following information:

- **Date (UTC):** a UTC timestamp of when the request occurred.
- **Request ID:** a unique identifier applied to the request.
- **Event:** the event type, either `stdout` or `stderr`.
- **Message:** the message included in the request.

A series of controls on the Tailing page allow you to interact with and refine the logs. Specifically:

- the **Service** menu allows you to specify the Compute service that the logs are from. From the menu, you can search for a service by ID or name.
- the **Events** menu allows you to limit the displayed logs to a specific stream (e.g., `stdout` and `stderr`).
- the **Pause** button allows you to pause the live stream of Compute logs. Once paused, you can resume live stream by clicking **Live**.

Accessing the Tailing page

To access the Tailing page:

1. Log in to the Fastly control panel.
2. Go to **Observability** > **Logs** > **Tailing**.

About the Explorer page

The **Explorer** page allows you to view, filter, and analyze log entries for a service.

> NOTE
>
> To support performance at scale, we sample data at a set rate determined by the requests per second (RPS) of your service. The sample is large enough to provide statistically significant insights, but it doesn't contain all of the log entries for your service.

For each log entry, the Explorer page displays the following information:

- **Date (UTC):** a UTC timestamp of when the request occurred.
- **Status Code:** the HTTP status code of the response.
- **Region:** the region from which the request originated.
- **POP:** the POP that received the request.
- **Cache Status:** the status indicating whether the request was a HIT or a MISS. A request can have multiple statuses based on clustering and shielding configurations. The last status in the list indicates the ultimate status of a request.

- **URL:** the URL of the requested asset.

You can click any log entry to reveal more data about the request. When available, the following data is provided.

Field	Description
`customer_id`	Your Fastly customer ID.
`service_id`	The Fastly service ID.
`timestamp`	The timestamp of when the request occurred.
`client_as_number`	The autonomous system (AS) number.
`client_region`	The region from which the request originated.
`client_country_code`	The country from which the request originated.
`client_os_name`	The name of the operating system installed on the client device.
`client_os_version`	The version of the operating system installed on the client device.
`client_device_type`	The type of device the client was using.
`client_browser_name`	The name of the web browser the client was using.
`client_browser_version`	The version of the web browser the client was using.
`fastly_pop`	The name of the Fastly POP that served the request.
`origin_host`	The name of the origin host that served the request.
`request_protocol`	The HTTP protocol version in use for the request.
`request_host`	The host the request was made to.
`request_path`	The path of the requested asset.
`request_method`	The HTTP method sent by the client, such as `GET` or `POST`.
`response_bytes_body`	The size of the response body in bytes.

Field	Description
`response_bytes_header`	The size of the response header in bytes.
`response_content_length`	The size of the response content in bytes.
`response_content_type`	The type of content in the response.
`response_reason`	The response phrase included with the HTTP status code.
`response_status`	The HTTP response code returned for the request.
`response_time`	The amount of time it took to respond to the request.
`response_x_cache`	Indicates whether the request was a HIT or a MISS.
`is_cache_hit`	Indicates whether this request was fulfilled from cache.
`is_edge`	Indicates whether the request was handled by a Fastly edge POP.
`is_shield`	Indicates whether the request was handled by a Fastly shield POP.

You can filter the log entries displayed on this page by:

- selecting the **Service** the request was made to.
- entering the **Domain** the request was made to.
- entering the **URL path** the request was made to.
- selecting the **Response Status** to filter by the HTTP status code of the response.
- selecting the **Point of Presence** that received the request.
- selecting the **Browser** the client was using.
- selecting the **Operating system** installed on the client device.
- selecting the **Device type** that the client was using.
- selecting the **Cache status** of the response.

- selecting the **Fastly Edge** status of the response.
- selecting the **Fastly Shield** status of the response.
- specifying the range of **Response Time** of the response.
- specifying a **Time Range** for log entries.

Accessing the Explorer page

To access the Explorer page:

1. Log in to the Fastly control panel.
2. Go to **Observability** > **Logs** > **Explorer**.

What's next

Dig deeper into details about all areas of the web interface before you move on to working with services.

---

* * *

📄	**About the Origins page**
🔗	/en/guides/about-the-origins-page

The Origins page gives you access to the Origin Inspector dashboard, which provides real-time and historic visibility into responses delivered from your origin servers to Fastly. To access the Origins page, go to **Observability** > **Origins**.

Before you begin

Origin Inspector is disabled by default. Anyone assigned the role of superuser can enable a 30-day trial directly in the web interface either on the Origins page or on the Trials page. After your trial expires, Origin Inspector can be purchased for an account by contacting sales@fastly.com and then enabled for a service by any superuser or engineer, which will result in changes to your monthly bill.

Be sure you know how to access the web interface controls before learning about the details you'll encounter here.

Enabling and disabling Origin Inspector

> **NOTE**
>
> To enable or disable this product via the API once you've purchased it, check out our developer documentation.

Enabling Origin Inspector

To enable Origin Inspector for a service:

1. Log in to the Fastly control panel.
2. Go to **Observability** > **Origins**.
3. Click the **Monitor origin responses** switch to the `ON` position to enable Origin Inspector for the service.

Once enabled, any user on your account can start viewing real-time and historic stats metrics about your origins immediately. Historic metrics usually become available two minutes after the end of each minute, but can take up to 15 minutes to appear.

Disabling Origin Inspector

To disable Origin Inspector for a service:

1. Log in to the Fastly control panel.
2. Go to **Observability** > **Origins**.
3. Click the **Monitor origin responses** switch to the `OFF` position to disable Origin Inspector for the service.

About the Origin Inspector dashboard

The Origin Inspector dashboard displays a wide variety of metrics to help you understand ongoing activity with the origins associated with your services.

Aggregate metrics

Once Origin Inspector is enabled for your account, the **Origin Inspector** dashboard displays a series of aggregate metrics tiles below the page controls.

When you select **All origins** from the **Origin** menu, these aggregate metrics appear:

- **Total origins:** the total number of origins configured for this account.
- **Monthly active origins:** the number of active origins configured for this account for the current month.
- **Total responses:** the number of responses from all active origins.
- **Bandwidth:** the bandwidth, in bytes, for all active origins.
- **Average error ratio:** the average ratio of error responses for all active origins.

When you select a specific origin from the **Origin** menu, these aggregate metrics appear:

- **Responses:** the number of responses for this origin.
- **Bandwidth:** the bandwidth, in bytes, for this origin.
- **Average error ratio:** the average ratio of error responses for this origin.

Metrics for all origins

When you select **All origins** from the **Origin** menu, the dashboard displays the following metrics tiles below the aggregate metrics tiles:

- **5xx by Origin:** the number of 5xx type (server error) HTTP response status codes returned by each origin.
- **4xx by Origin:** the number of 4xx type (client error) HTTP response status codes returned by each origin.
- **Responses by Origin:** the number of responses processed by each origin.
- **Bandwidth by Origin:** the number of bytes sent by each origin.
- **3xx by Origin:** the number of 3xx type (redirection) HTTP response status codes returned by each origin.
- **2xx by Origin:** the number of 2xx type (success) HTTP response status codes returned by each origin.

Metrics for specific origins

When you select any single origin from the **Origin** menu, the dashboard displays the following metrics tiles below the aggregate metrics tiles:

- **Status 5xx Details:** the distribution of different 5xx (server error) status response codes for the origin.
- **Status 4xx Details:** the distribution of different 4xx (client error) status response codes for the origin.
- **Origin Latency:** the distribution of origin latency times that approximate how quickly your origin is responding to Fastly. This histogram only appears when you are viewing live traffic.
- **Origin Latency Percentiles:** the origin latency percentiles that approximate how quickly your origin is responding to Fastly. Each percentile is indicated by `pn`, where `n` is the percentile number. `pn` means `n`% of all requests had an origin latency value that is less than or equal to the value on the y-axis. For example, if the value of `p95` is `8s`, 95% of all requests had an origin latency that was less than or equal to 8 seconds. This graph only appears when you are viewing live traffic.
- **Origin Latency Heatmap:** a diagram mapping out the response times from the origin.
- **Status Response Codes:** the distribution of the number of status response codes for an origin.
- **Total Responses:** the number of responses from an origin.
- **Origin Bandwidth:** the total bandwidth from an origin.
- **Status 3xx Details:** the distribution of different 3xx (redirection) status response codes for the origin.
- **Status 2xx Details:** the distribution of different 2xx (success) status response codes for the origin.

What's next

Dig deeper into details about all areas of the web interface before you move on to working with services.

---

* * *

About the Services menu

/en/guides/about-the-services-menu

The Services menu contains links to two pages that display high-level metrics for your services:

- **Service Overview:** page that contains the Service Overview dashboard, which displays different information depending on if you are viewing a Deliver or Compute service.
- **All Services:** page that contains the All Services dashboard, which displays aggregated metrics from all of your services.

To access the Services menu, go to **Observability** > **Services**.

Before you begin

Be sure you know how to access the web interface controls before learning about the details you'll encounter here.

About the Service Overview page

The **Service Overview** page gives you access to the Service Overview dashboard, which displays different information depending on if you are viewing a Deliver or Compute service.

Service Overview dashboard for a Deliver service

When a Deliver service is selected from the **Service** menu, the Service Overview dashboard displays the following metrics:

- **Global POP Traffic:** the map of Fastly's points of presence (POPs) that receive requests for your service. The map only appears when you are viewing live traffic.
- **Hit Ratio:** the percentage of cache hits to all cacheable content over time.
- **Requests:** the number of requests by cache response type.
- **Bandwidth:** the total bytes delivered.
- **All Status Codes:** the number of responses sent by status group.

- **Error ratio:** the number of cache errors.
- **Status 3XX Details:** the number of HTTP status 301s, 302s, 304s, and other 3XX requests.
- **Status 4XX Details:** the number of HTTP status 400s, 401s, 403s, 404s, 416s, 427s, and other 4XX requests.
- **Status 5XX Details:** the number of HTTP status 500s, 501s, 502s, 503s, 504s, 505s, and other 5XX requests.
- **Misses:** the number of cache misses.
- **Object Sizes:** the number of objects served by payload size.
- **Hit Time:** the average amount of time spent processing cache hits.
- **Miss Time:** the average amount of time spent processing cache misses.
- **Header & Body Bytes Transferred:** the relative values of bytes transferred when serving the body and header portions of HTTP requests.
- **Log Lines:** the number of log lines sent.
- **Log Bandwidth:** the total log bytes sent.
- **Origin Latency:** the distribution of origin latency times that approximate how quickly your origin is responding to Fastly. This histogram only appears when you are viewing live traffic.
- **Origin Latency Percentiles:** the origin latency percentiles that approximate how quickly your origin is responding to Fastly. Each percentile is indicated by `pn`, where `n` is the percentile number. `pn` means `n`% of all requests had an origin latency value that is less than or equal to the value on the y-axis. For example, if the value of `p95` is `8s`, 95% of all requests had an origin latency that was less than or equal to 8 seconds. This graph only appears when you are viewing live traffic.
- **Cache Coverage:** the percentage of your site that you are caching with Fastly.
- **HTTP Versions:** the number of requests using HTTP/1.1, HTTP/2, and HTTP/3(QUIC).
- **Error Ratio by Region:** the percentage of cache errors per region.
- **TLS versions:** the number of requests using TLS 1.0, TLS 1.1, TLS 1.2, and TLS 1.3 protocols.

The dashboard also displays collections of metrics that you can expand and collapse by clicking the collection name. The collections include:

- **Image Optimizer:** metrics for your services that relate to image optimization.
- **WebSockets:** metrics for your service that relate to WebSockets.
- **Fanout:** metrics for your service that relate to Fanout.

Service Overview dashboard for a Compute service

When a Compute service is selected from the **Service** menu, the Service Overview dashboard displays the following metrics:

- **Global POP Traffic:** a map of Fastly's points of presence (POPs) that receive requests for your service.
- **Requests:** the total number of requests that were received for your service by Fastly.
- **Response status codes:** the total number of response status codes by category delivered by Compute.
- **Total resource limits exceeded:** the number of times a guest exceeded its resource limit, includes heap, stack, globals, and code execution timeout.
- **Memory Resource Limits Exceeded:** the number of times a guest exceeded its heap, stack, and global limits.
- **Backend Requests Errors:** the number of backend request errors, including timeouts.
- **Edge Code Errors:** the number of times a service experienced an edge code error.
- **Guest Runtime Errors:** the number of times a service experienced a guest runtime error.
- **Bytes Received by Compute:** the total bytes received by Compute.
- **Bytes Transferred to Client:** the total bytes sent from Compute to end user.
- **Bytes Transferred to Backend:** the total bytes sent to backends (origins) by Compute.
- **Bytes Transferred from Backend:** the total bytes received from backends (origins) by Compute.
- **Total Wall Clock Time:** the total, actual amount of time used to process your requests, including active CPU time.

- **CPU Time:** the amount of active CPU time used to process your requests.
- **RAM Usage:** the amount of RAM used for your service by Fastly (in bytes).
- **Logs:** the number of logs sent to your endpoints from Fastly.
- **Log Bandwidth:** the total bandwidth size of the logs sent to your endpoints from Fastly.
- **Cache Operations per Request:** The average number of cache operations per request.

About the All Services page

The **All Services** page gives you access to the All Services dashboard, which displays aggregated metrics from all of your services. Specifically, it displays the following overview metrics:

- **Requests:** a graph displaying the number of requests served across your account.
- **Bandwidth:** a graph displaying the number of bytes served from Fastly's servers to your website's visitors.
- **Error Ratio:** a graph displaying the number of cache errors across your account.

The dashboard also displays collections of metrics that you can expand and collapse by clicking the collection name. The collections include:

- **Deliver:** aggregated metrics from all of your Deliver services. The metrics in this collection mirror the metrics on the Service Overview dashboard for a Deliver service.
- **Compute:** aggregated metrics from all of your Compute services. The metrics in this collection mirror the metrics on the Service Overview dashboard for a Computer service.
- **Image Optimizer:** aggregated metrics from all of your services that relate to Image Optimizer.
- **WebSockets:** aggregated metrics from all of your services that relate to WebSockets.
- **Fanout:** aggregated metrics from all of your services that relate to Fanout.
- **Media Shield:** aggregated metrics for your service that relate to Media Shield.

About the Image Optimizer metrics collection

The **Image Optimizer** metrics collection appears on the Service Overview dashboard for a Deliver service and on the All Services dashboard. The collection includes the following metrics:

- **Image Optimizer total responses:** the total number of responses that came from the Fastly Image Optimizer service.
- **Image Optimizer shield responses:** the number of responses that came from the Fastly Image Optimizer service via a shield.
- **Image Optimizer total bytes delivered:** the total bytes delivered from the Fastly Image Optimizer service, including shield traffic.
- **Image Optimizer shield bytes delivered:** the total bytes delivered via a shield from the Fastly Image Optimizer service.
- **Image Optimizer video responses:** the number of video responses that came from the Fastly Image Optimizer service.
- **Image Optimizer video frames:** the number of video frames that came from the Fastly Image Optimizer service. A video frame is an individual image within a sequence of video.
- **Image Optimizer video bytes delivered:** the total bytes of video delivered from the Fastly Image Optimizer service.
- **Image Optimizer video shield responses:** the number of video responses delivered via a shield that came from the Fastly Image Optimizer service.
- **Image Optimizer video shield bytes delivered:** the total bytes of video delivered via a shield from the Fastly Image Optimizer service.
- **Image Optimizer video shield frames:** the number of video frames delivered via a shield that came from the Fastly Image Optimizer service. A video frame is an individual image within a sequence of video.

About the WebSockets metrics collection

The **WebSockets** metrics collection appears on the Service Overview dashboard for a Deliver service and on the All Services dashboard. The collection includes the following metrics:

- **WebSockets connection time:** the total duration of passthrough WebSocket connections with end users.

- **WebSockets bytes transferred to client:** the total bandwidth transferred by Fastly for your service when using requests.
- **WebSockets bytes transferred from client:** the total bandwidth transferred by Fastly for your service when receiving requests.
- **WebSockets bytes transferred to origin:** the total bandwidth transferred by Fastly to your backend when receiving requests.
- **WebSockets bytes transferred from origin:** the total bandwidth transferred to Fastly from your backend when serving requests.

About the Fanout metrics collection

The **Fanout** metrics collection appears on the Service Overview dashboard for a Deliver service and on the All Services dashboard. The collection includes the following metrics:

- **Fanout connection time:** the total duration of Fanout connections with end users.
- **Fanout published messages:** the total number of messages received from the publish API and sent to end users.
- **Fanout bytes transferred to client:** the total bandwidth transferred by Fastly for your service when serving requests.
- **Fanout bytes transferred from client:** the total bandwidth transferred by Fastly for your service when receiving requests.
- **Fanout bytes transferred to backend:** the total bandwidth transferred by Fastly to your backend when receiving requests.
- **Fanout bytes transferred from backend:** the total bandwidth transferred to Fastly from your backend when serving requests.

About the Media Shield metrics collection

The **Media Shield** metrics collection appears on the Service Overview dashboard for a Deliver service. The collection currently includes the following metrics:

- **Media Shield Bytes:** the number of bytes sent to Media Shield.
- **Media Shield Requests:** the number of requests sent to Media Shield.
- **Origin Offload:** the ratio of bytes served to end users that were cached.

- **Request Collapsing:** the number of requests that were collapsed and either satisfied by a usable cache object or unable to be satisfied by the resulting cache object.
- **Edge Miss Requests:** the average number of requests that resulted in a miss at the edge.
- **Media Shield Hit Requests:** the average number of requests that hit the Media Shield.
- **Media Shield Miss Requests:** the average number of requests that missed at the Media Shield.
- **Media Shield Hit Ratio:** the percentage of cache hits to all cacheable content at the Media Shield over time.
- **Edge Hit Ratio:** the percentage of cache hits to all cacheable content at the edge over time.
- **Media Shield Fetches:** the number requests from one Fastly POP to another as part of Media Shield.
- **Requests by Domain Name:** the number requests broken out by domain name.

> TIP
>
> Media Shield metrics are derived from our Metrics and Stats APIs and are also available as part of custom dashboards.

What's next

Dig deeper into details about all areas of the web interface before you move on to working with services.

---

* * *

	Working with custom dashboards
🔗	/en/guides/working-with-custom-dashboards

From the Observability pages, you can access custom dashboards that you build to make relevant metrics for a service more visible and accessible in a single location. Custom

dashboards are disabled by default.

Before you begin

Be sure you know how to access the web interface controls and understand basic information about the Observability pages before learning about custom dashboards.

Limitations and considerations

Keep the following things in mind:

- Custom dashboards are disabled by default and are only available to customers who have purchased an Observability package. Once enabled, only users assigned the role of superuser or engineer can edit custom dashboards, but all account users will be able to view them.
- You are limited to 100 custom dashboards per account, once they've been enabled for you.

Accessing custom dashboards

To access and view a custom dashboard, follow these steps:

1. Log in to the Fastly control panel.
2. Go to **Observability** in the navigation sidebar.
3. Click **Custom dashboards**.
4. Click the linked name of the custom dashboard you want to view.

About the controls on Custom dashboard pages

On the each custom dashboard page, you can refine the metrics displayed and gain more information by:

- using the menu below the dashboard name to change the timeframe.
- hovering over any part of a graph to access a timestamp indicator that updates as you move the cursor.
- clicking the button at the bottom of a card to access information related to the metric.

For additional details about all the controls on the custom dashboard pages, check out our guide to the Observability controls.

Working with custom dashboards

From the Custom dashboards page, you can create, clone, share, and delete custom dashboards.

Creating a custom dashboard

To create a custom dashboard, follow these steps:

1. On the **Custom dashboards** page, click **Create dashboard**.
2. In the **Dashboard Name** field, enter the name of your custom dashboard.
3. Click **Save**. The new custom dashboard appears, empty and ready to have charts added to it.

Cloning a custom dashboard

To clone an existing custom dashboard, follow these steps:

1. On the **Custom dashboards** page, click **Create dashboard**.
2. In the **Dashboard Name** field, enter the name of your custom dashboard.
3. Click **Clone**.
4. From the **Clone from** menu, select the existing dashboard you want to clone.
5. Click **Save**. The new custom dashboard appears, duplicating all existing charts from the original dashboard.

Deleting a custom dashboard

Custom dashboards can be deleted individually and in bulk as follows:

- To delete a specific custom dashboard from the Custom Dashboards page, click the trash to the right of the dashboard name.
- To delete multiple custom dashboards from the Custom Dashboards page, select the checkbox to the left of each dashboard you plan to delete and then click the **Delete** button above the list of custom dashboards.

- To delete a custom dashboard while viewing that specific dashboard, select **Delete dashboard** from the **Options** menu and click **Delete** on the confirmation window that appears.

Sharing a custom dashboard

To share a custom dashboard, follow these steps:

1. Navigate to the dashboard that you want to share.
2. Click **Options** and then select **Copy link**. The link is saved to your computer's clipboard.
3. Manually share the link outside of the Fastly app.

To access a shared dashboard, you must have the appropriate permissions.


Working with custom dashboard charts

You can surface relevant metrics on custom dashboards by adding charts that highlight meaningful data and deleting existing charts that aren't needed anymore.

Adding a chart to a custom dashboard

To add a chart to a custom dashboard, follow these steps:

1. Navigate to the custom dashboard that you want to add a chart to.
2. Click **Options** and then select **Edit dashboard**.
3. Click **Add Chart**.



4. Fill out the Add Chart fields as follows:

    - In the **Title** field, enter the name of the chart.
    - In the **Subtitle** field, enter a brief description of the chart.
    - From the **Data Source** menu, select a data pipeline. Data pipeline options include Historic Stats, Original Inspector, and Domain Inspector.
    - From the **Metrics** menu, select the type of data the chart should report.
    - From the **Type** menu, select an option to control how the data is displayed.
    - From the **Calculation Method** menu, select the single metric the chart should report. This field only appears when the Type field is set to Donut or Number.
    - From the **Size** menu, select an option to control the width of the chart.

    A preview of the chart appears next to the form as you enter information and make selections.

5. Click **Save**. The chart is added to the dashboard.

6. Click **Exit Edit Mode** to return to view mode for the dashboard.

Rearranging charts on custom dashboards

To rearrange the charts on a custom dashboard, click and hold on any chart you want to move using your mouse, then drag it to the desired location and release the button.

Deleting a chart from a custom dashboard

To delete a chart from a custom dashboard, follow the steps below:

1. Navigate to the custom dashboard that you want to add a chart to.
2. Click **Options** and then select **Edit dashboard**.
3. Click the trash to the right of the chart that you want to delete. The chart is removed from the dashboard.
4. Click **Exit Edit Mode** to return to view mode for the dashboard.

What's next

Dig deeper into details about all areas of the web interface before you move on to working with services.

---

* * *

Security guides

Category: Access Control Lists

These articles describe how to restrict access to resources by allowing or blocking IP addresses with access control lists (ACLs).

	About ACLs
🔗	/en/guides/about-acls

Malicious actors can present themselves in a variety of ways on the internet. Automated tools can scrape information from your website, bots can probe your application for

vulnerabilities, and hackers can exploit them. Using access control lists (ACLs) at the edge can help prevent the offending IP addresses they use from ever accessing your information resources.

When ACLs can be useful

Access control lists at the edge might be useful for:

- E-commerce companies preventing scraping from certain IP ranges.
- Offices restricting access to their administrative portals.
- Advertising technology companies blocking bad-actors at the edge.
- Mobile applications accepting only calls from specific proxies or IP ranges.
- System administrators restricting access to groups of backends from an office IP address or subnet range.

How ACLs work

ACLs have two parts: an ACL container and the ACL entries within it. In combination, containers and entries allow you to store a list of permissions used to grant or restrict access to URLs within your services.

Once you attach an ACL container to a version of your service and that service is activated, the data in the container (the ACL entries) becomes *versionless*. This means that once your service is activated, any further changes to the data within that container, such as the addition of ACL entries, will become effective immediately for all service versions, including the active one.

Ways to create ACLs

To create an ACL at the edge and use it within your service, start by creating an empty ACL container and then add its entries. You can create ACLs in several ways. For most configurations that integrate websites or applications with an ACL at the edge, you can:

- use the service configuration for CDN services.
- use the Fastly API for both CDN and Compute services.
- use the Resources tab for Compute services.

- use the Fastly CLI for Compute services

For simple access control requirements in which a few IP addresses can be hardcoded, you can manually create an ACL using VCL. Manually created ACLs are only supported for use with CDN services and are versioned, meaning any changes to the ACL will require changes to your VCL.

Limitations

When working with ACL containers and entries specifically, remember the following:

- **ACL entry changes via the API don't appear in the event logs.** If you use the API to add, update, or remove an ACL entry, there will be no record of it in the audit log or event log. The only record of a change will exist when you compare service versions and view the exact point at which the ACL was associated with the service version in the first place.
- **ACL entry deletions are permanent.** ACL entries are versionless. This means that if you delete an entry within an ACL container, that entry is permanently removed from all service versions and cannot be recovered.
- **ACL containers are limited to 1000 ACL entries.** If you find your containers approaching this entry limit, contact support. We may be able to help you figure out an even more efficient way to do things with your ACLs at the edge.

---

* * *

	Manually creating access control lists
🔗	/en/guides/manually-creating-access-control-lists

IMPORTANT

This guide only applies to CDN services.

Varnish allows you to use access control lists (ACLs), a feature that enables fast matching of a client's IP address against a list of defined IP addresses. An ACL in Varnish looks like this:

```
# Who is allowed access ...
acl local {
  "localhost";
  "192.0.2.0"/24; /* and everyone on the local network */
  ! "192.0.2.1"/32; /* except for the dial-in router */
}

```

Before you begin

Be sure you understand how ACLs work in Fastly.

Limitations and considerations

Note the following limitations and considerations for ACLs manually created with custom VCL:

- **ACLs created with custom VCL are always versioned.** ACLs created with custom VCL are always tied to a service and require a new service version each time they are updated in any way. This is true for both the ACLs created using custom VCL and for any logic created to interact with those ACLs.
- **ACLs created with custom VCL cannot be manipulated using the API.** If you create an ACL using custom VCL, that ACL must always be manipulated via custom VCL and can never be manipulated using the Fastly API. ACLs created using the API, however, can be manipulated using both the API and custom VCL.

Defining an ACL

Using ACLs requires you to create and add custom VCL to Fastly's boilerplate VCL. To define an ACL in your Fastly configuration:

1. Read about how to mix and match custom VCL with Fastly VCL.
2. Create a custom VCL file with your ACL definitions included in the appropriate location. Use the example shown below as a guide. You can reference the ACL in your configuration (`vcl_recv`) using a match operation that can be located above or below `#FASTLY recv`. The placement only matters for the order of operations within Varnish's execution of your configuration.

```
# If you are using the "include" keyword
include "myACL1.vcl";

# And/or if you are using an actual ACL block
acl local {
  "localhost";
  "192.0.2.0"/24; /* and everyone on the local network */
  ! "192.0.2.1"/32; /* except for the dial-in router */
}

sub vcl_recv {
  # block any requests to Admin pages not from local IPs
  if (req.url ~ "^/admin" && req.http.Fastly-Client-IP !~ local
    error 403 "Forbidden";
  }
}
```

3. Upload the file in the Varnish Configuration area of your service.

Example ACL use

Let's suppose you've used the Fastly API to create an ACL and add ACL entries, after which the VCL for the ACLs and ACL entries will be automatically generated, as shown below. For example, this VCL shows an ACL called `office_ip_ranges` has been created:

```
# This VCL is automatically generated when you create an ACL cc ai
# using the Fastly API. In this example, the ACL name is office_ip_
acl office_ip_ranges {
  "192.0.2.0"/24;                                # internal office
  "198.51.100.4";                                # remote VPN office
  "2001:db8:ffff:ffff:ffff:ffff:ffff:ffff";      # ipv6 address remot
}
```

Once created, you can add logic to interact with your ACL at the edge by uploading custom VCL. You could use the `office_ip_ranges` ACL as an allow list by uploading the following

custom VCL:

```
sub vcl_recv {
  # block all requests to Admin pages from IP addresses not in offi
  if (req.url ~ "^/admin" && client.ip !~ office_ip_ranges) {
    error 403 "Forbidden";
  }
}

```

With this VCL, access to `/admin` is denied for everyone by default, but the IP addresses listed in the ACL are allowed to access `/admin` without restriction.

TIP

Because ACL entries have a boolean option for negation, you can specify whether or not an IP address is allowed (false or `0`) or blocked (true or `1`).

* * *

Using the IP block list

/en/guides/using-the-ip-block-list

IMPORTANT


This guide only applies to CDN services.

You can prevent specific IP addresses from accessing your service by adding them to a block list. Enabling this feature creates a condition and response that returns a 403 error to anyone trying to access the service from a blocked IP address. You can use this feature to prevent bad actors from interfering with the operation of your web application.

Enabling the IP block list

To enable the IP block list, follow the steps below:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Settings**.
5. Click the **IP block list** switch to **On**.



6. Click **Activate** to deploy your configuration changes.

1. Open a terminal application and enter the following command to create an ACL:

```
$ curl -i  -X POST "https://api.fastly.com/service/[service_i
```

2. Enter the following command to create a condition:

```
$ curl -i  -X POST "https://api.fastly.com/service/[service_i
```


3. Enter the following command create a response object:

```
$ curl -i  -X POST "https://api.fastly.com/service/[service_i
```

Blocking an IP address

To block an IP address, follow the steps below:

1. Click **Add address**.
2. In the **Address** field, enter an IP address or subnet mask (a range of IP addresses) to block for this service. To add an exception for an IP address, use an exclamation point (for example, use `!192.0.2.0` or `!192.0.2.0/24`).
3. *(Optional)* In the **Comment** field, enter a comment that describes the IP address or subnet mask.
4. Click **Add**. The IP address or subnet mask appears in the list. This addition will become effective immediately.



1. Find the ID of the IP block list ACL. Open a terminal application and enter the following command to list the ACLs on your service:

```
$ curl -i  "https://api.fastly.com/service/[service_id]/versi/[
```

Find the ID of the IP block list ACL in the output:

```
[{"updated_at":"2023-11-01T20:46:51Z","version":"3","deleted_at":
```

2. Using the ACL ID, enter the following command to block an IP address by creating a new ACL entry:

```
$ curl -i  -X POST "https://api.fastly.com/service/[service_i
```

Editing a blocked IP address

You can edit a blocked IP address or subnet mask at any time. To edit an IP address or a subnet mask, follow the steps below:

1. Find the IP block list associated with your service in which the associated IP addresses or subnet masks appear. Because these entries are versionless, the service version you choose doesn't matter. Choose the one that makes the most sense to you.
2. In the IP block list area, hover your cursor over an entry, then click the pencil that appears.
3. Edit the IP address, subnet mask, or comment as necessary.
4. Click **Save**. The changes you make will be immediately applied to your configuration. If your IP block list has already been associated with a deployed service version, those changes will happen live.

1. Find the ID of the IP block list ACL. Open a terminal application and enter the following command to list the ACLs on your service:

```
$ curl -i  "https://api.fastly.com/service/[service_id]/versi
```

Find the ID of the IP block list ACL in the output:

```
[{"updated_at":"2023-11-01T20:46:51Z","version":"3","deleted_at":
```

2. Using the ACL ID, enter the following command to list the ACL entries on your service:

```
$ curl -i  "https://api.fastly.com/service/[service_id]/acl/[
```

Find the ACL entry ID of the IP address you want to update in the output.

```
[{"acl_id":"[acl_id]","negated":"0","service_id":"[service_id]","
```

3. Using the ACL entry ID of the IP address you want to update, enter the following command to update the IP address:

```
$ curl -i  -X PATCH "https://api.fastly.com/service/[service_
```

Deleting an IP block list entry

You can delete individual entries in the IP block list at any time. To delete an IP address or subnet mask that was created via the Fastly control panel:

1. Find the IP block list associated with your service in which the associated IP addresses or subnet masks appear. Because these entries are versionless, the service version you choose doesn't matter.
2. In the IP block list area, hover your cursor over an entry, then click the trash that appears.
3. Click **Confirm and delete**.

1. Find the ID of the IP block list ACL. Open a terminal application and enter the following command to list the ACLs on your service:

```
$ curl -i  "https://api.fastly.com/service/[service_id]/versi
```

Find the ID of the IP block list ACL in the output:

```
[{"updated_at":"2023-11-01T20:46:51Z","version":"3","deleted_at":
```

2. Using the ACL ID, enter the following command to list the ACL entries on your service:

```
$ curl -i  "https://api.fastly.com/service/[service_id]/acl/[
```

Find the ACL entry ID of the IP address you want to delete in the output.

```
[{"acl_id":"[acl_id]","negated":"0","service_id":"[service_id]","
```

3. Using the ACL entry ID of the IP address you want to delete, enter the following command to update the IP address:

```
$ curl -i  -X DELETE "https://api.fastly.com/service/[service
```

Disabling the IP block list

The IP block list and its associated entries can be disabled in any unlocked service version. To disable the IP block list, follow the steps below:

1. Find the IP block list associated with an unlocked version of your service.
2. Click the **IP block list** switch to **Off**.
3. Click **Yes**. This disables the block list and deletes all associated entries.
4. Click **Activate** to deploy your configuration changes.

Creating other ACL types

If you need other types of ACLs, you'll need to create them in the Data page of the Fastly control panel.

* * *

	Working with ACLs
🔗	/en/guides/working-with-acls

Access control lists (ACLs) allow you to store a list of permissions that Fastly will use to grant or restrict access to URLs within a service. You can use the Fastly control panel to add, remove, and update ACLs.

Before you begin

Be sure to review the limitations and considerations applied to access control lists.

Creating an ACL

ACLs have two parts: an ACL container and the ACL entries within it. Once an ACL is linked to a service, the entries within it are "versionless". This means once your service is activated, any changes to add, edit, or remove ACL entries become effective immediately for all service versions, even the active one, without needing to clone a new service version.

To create an ACL:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Data**.
5. Click **Create an ACL**.
6. In the **Name of ACL** field, enter a descriptive name for the ACL (e.g., `Example ACL`).
7. Click **Add**.

8. Click **Activate** to deploy your configuration changes to the service version you're editing.

Once your ACL is created, add ACL entries into it:

1. Click **Add address**.
2. In the **Address** field, enter an IP address or subnet mask (a range of IP addresses) to allow or block for this service. To exclude or block an IP address or subnet mask, use an exclamation point (for example, use `!192.0.2.0` or `!192.0.2.0/24`).
3. *(Optional)* In the **Comment** field, enter a comment that describes the IP address or subnet mask.
4. Click **Add**. The IP address or subnet mask appears in the ACL. This addition will become effective immediately.

To create an ACL:

1. Log in to the Fastly control panel.
2. Go to **Resources** > **Access control lists**.
3. Click **Create list**.
4. Enter a name for your ACL, then click **Create**.

Once your ACL is created, add ACL entries into it:

1. Click the name of the ACL you want to add entries to.
2. From the **Items** tab, click **Add item**.
3. In the **Prefix** field, enter an IP address defined in Classless Inter-Domain Routing (CIDR) format.
4. From the **Action** field, select whether to allow or block the IP address.
5. Click **Save**.

Finally, link your ACL to a service and activate:

1. Click the name of the ACL you want to link to a service.
2. From the **Linked services** tab, click **Link service**.
3. Select the checkbox next to any services you want to link your ACL to.

4. Click **Next**.

5. Decide which version of the service to link to. By default, the system will assume you want to clone the most recently active version of your service. You can choose an existing draft version of the service instead by selecting it specifically from the Version menu.

6. Select one of the following options for linking the store to your service:

    - **Link only:** links the store to the selected service versions but leaves any cloned or draft versions un-activated so you can activate them at a later time.
    - **Link and activate:** links the store to the selected service versions and activates those versions at the same time.

    A success message appears once the ACL is linked to the service.

7. Finally, do one of the following:

    - Click **Activate versions** to activate any cloned or draft versions of services linked to the ACL.
    - Click **Finish** to leave the cloned or draft service versions un-activated so you can make additional configuration changes to them and activate them at a later time.

> NOTE
>
> Compute ACLs can also be linked from the service configuration. Go to **Service configuration** > **Resources** > **Access control lists** and use the menu to select an ACL to link to the service.

Viewing and managing ACLs

Once created, ACLs linked to CDN services can be viewed and managed by accessing the appropriate service and going to **Service configuration** > **Data** > **Access control lists**. ACLs linked to Compute services can be viewed and managed from the Resources tab or by accessing the appropriate service and going to **Service configuration** > **Resources** > **Access control lists**.

Editing ACLs

You can edit an ACL to change the name or edit the ACL entries within at any time.

To edit the name of an ACL:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Configuration** and then select **View Active**.
4. From the service version menu, select an appropriate service version.
5. Click **Data**.
6. Click the pencil next to the ACL you want to edit.
7. Change the name, then click **Save**.

To edit entries within an ACL:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Find any ACL associated with your service in which the entry you want to edit appears. Because ACL entries are versionless, the service version you choose doesn't matter. Choose the one that makes the most sense to you.
4. Hover your cursor over an ACL entry, then click the pencil that appears.
5. Edit the IP address, subnet mask, or comment as necessary.
6. Click **Save**. The changes you make will be immediately applied to your configuration. If your ACL has already been associated with a deployed service version, those changes will happen live.

To edit the name of an ACL:

1. Log in to the Fastly control panel.
2. Go to **Resources** > **Access control lists**.
3. Click the name of the ACL you want to edit.

To edit entries within an ACL:

1. Log in to the Fastly control panel.

2. Go to **Resources** > **Access control lists**.
3. Click the name of the ACL with entries you want to edit.
4. From the **Items** tab, click the pencil to the right of the store you want to rename.
5. Make necessary changes to the entry, then click **Save**.

Unlinking Compute ACLs from a service

ACLs linked to a Compute service can be unlinked from the service configuration.

To unlink an ACL:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Service configuration**.
4. From the **Resources** options in the on-page navigation, click **Access control lists**.
5. Click **Unlink from service** next to the ACL you want to unlink from your service.
6. Click **Confirm and unlink**. A new, draft version of the service is created.
7. Activate the service to finalize unlinking the ACL.

Deleting an ACL

You can delete an ACL or specific entries within an ACL at any time.

> TIP
>
> Deleted ACLs are only removed from the service version you're editing. This allows you to revert your configuration to a previous version in as few steps as possible.

To delete an ACL:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.

3. From the service version menu, select an unlocked version of your service.
4. Click the trash in the top right corner of the ACL you want to delete.
5. Click **Confirm and delete**.
6. Click **Activate** to deploy your configuration changes to the service version you're editing.

To delete ACL entries:

> **WARNING**
>
> ACL entry deletions are permanent and immediate. They cannot be recovered. Deleting an ACL entry immediately impacts all service versions associated with the ACL container holding the deleted entries, including the active service version.

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Find any ACL associated with your service in which the entry you want to delete appears. Because ACL entries are versionless, the service version you choose doesn't matter. Choose the one that makes the most sense to you.
4. Hover your cursor over an ACL entry, then click the trash that appears.
5. Click **Confirm and delete**.

To delete an ACL:

1. Log in to the Fastly control panel.
2. Go to **Resources** > **Access control lists**.
3. Click the name of the ACL you want to delete.
4. From the **Options menu**, click **Delete list**.
5. Click **Confirm and delete**.

To delete ACL entries:

1. Log in to the Fastly control panel.

2. Go to **Resources** > **Access control lists**.

3. Click the name of the ACL with entries you want to delete.

4. Click the trash to the right of the entry you want to delete.

5. Click **Confirm and delete**.

---

* * *

Category: Client-Side-Protection

These articles describe how to inventory client-side scripts that load on an end user's browser from defined areas of your website and provide a justification as to why each script is needed.

	About Client-Side Protection
🔗	/en/guides/about-client-side-protection

Fastly Client-Side Protection provides you with the ability to inventory and control the resources (e.g., scripts, images, and fonts) that load on an end user's browser from defined areas of your web applications by building and enforcing content security policies (policies). In addition, you can provide a justification as to why each client-side script is or isn't allowed. These capabilities help you guard against cross-site scripting attacks (e.g., Magecart attack) and enable you to maintain compliance with Payment Card Industry Data Security Standard (PCI DSS) 4.0.1 - Sections 6.4.3 and 11.6.1.

Prerequisites

To use Client-Side Protection, be sure you have the following prerequisites in place:

- Client-Side Protection is disabled by default. To purchase and enable the product, contact sales@fastly.com. Once enabled, all users will be able to access the Client-Side Protection menu in the Fastly control panel and the items within it, but you'll only be able to view and manage the data on linked pages if you've been assigned the role of superuser. All other user roles will see an error message indicating you're not authorized to view the information.

- For Fastly to be able to inventory the client-side scripts on your web application, the Next-Gen WAF must be monitoring that same web application.
- If you have a Core WAF deployment, verify that the Next-Gen WAF agent and module versions that you're using support Client-Side Protection.
- If you've written a custom module for integration with the Next-Gen WAF, update the module to support response header modification.

Supported Core WAF deployment options

The following Core WAF deployment variations support the Client-Side Protection product:

Deployment variation	Minimum agent version	Minimum module version	Notes
Apache module		1.10.0+	
AWS Lambda	4.64.0+		
Envoy	4.62.0+		Envoy, Istio Envoy filter, and Istio Authorization policy are supported. If you use Ambassador Edge Stack and Gloo, you must configure the agent as a reverse proxy. Those environments do not support the Envoy external authorization features that are needed to modify response headers.
Golang	4.61.0+		If you've written a custom module for integration with the Next-Gen WAF and use the Golang module, the Golang module must be at least version 1.14.0.
HAProxy	4.63.0+	1.5.0+	
Heroku	4.61.0+		
IBM Cloud	4.61.0+		
IIS module		3.5.0+	

Deployment variation	Minimum agent version	Minimum module version	Notes
Java module		2.7.0+	
.Net module		1.7.1+	
.Net Core module		1.4.1+	
NGINX Lua module		1.7.0+	
NGINX native module		1.2.0+	
Node.js module		2.3.0+	
Reverse proxy	4.61.0+		
VMware Tanzu	4.61.0+		

The following Core WAF deployment variations do not support the Client-Side Protection product:

- PHP
- Python

How it works

Client-Side Protection works alongside the Next-Gen WAF to inventory and control the resources that load on an end user's browser from defined areas of your web applications. You define the areas by creating at least one *website* and *Page*. A website is a base URL (e.g., `https://www.example.com`) and a Page is a single path (e.g., `/checkout`) or collection of paths that describe a similar component or user experience on your web application (e.g., `/checkout` and `/edit-cc`). Together, a website and Page define the full URLs (e.g., `https://www.example.com/checkout` and `https://www.example.com/cc`) of the webpages that you want to monitor and protect.

Once you've created at least one website and Page, you can:

- monitor the inventory that Fastly creates for each Page. An inventory is a collection of the client-side scripts and select response headers that Fastly observes for a Page. Reviewing changes to your inventory can help you identify security issues that should be investigated.
- build and manage a policy that tells the end user's browser from where it is allowed to load certain types of resources for the Page. Maintaining a policy helps guard against cross-site scripting attacks.

About the inventory

An inventory is a collection of the client-side scripts and security-impacting response headers that Fastly observes for a Page. Each inventory is associated with a single Page.

To create and maintain the inventory, the Next-Gen WAF inserts the `Content-Security-Policy-Report-Only` header into a sample of responses for a Page. This header makes it possible for Fastly to observe and collect the scripts and response headers for the inventory.

Type	Collection frequency
Client-side scripts	Every three days, Fastly pulls the observed scripts into the inventory and stores them. When Fastly fails to re-inventory a script for 90 days, Fastly removes the script from the inventory.
Security-impacting response headers	Fastly logs the security-impacting response headers for all responses that have the `Content-Security-Policy-Report-Only` response header.

Every three days, Fastly sends you a list of the response headers that changed to the email address you defined on the associated Page. The changes are grouped into 60-minute periods.

From the Inventory page in the Fastly control panel, you can:

- add an authorization status and comment for each observed script to help keep track of the scripts that you've reviewed and why certain scripts are or aren't approved.
- view the security-impacting response headers from the last-logged response.

If you think that a response header value is dangerous or that a script shouldn't be loading on your web application, investigate the issue and take action accordingly.

About the policy

Using the Fastly control panel, you can create a policy that applies to one Page. A policy is made up of directives, which tell the end user's browser what resources its allowed to load and from where. Each directive controls one type of resource. For example, the `script-src` directive controls the allowed sources for JavaScript.

Client-Side Protection works with the Next-Gen WAF to add your policy to responses that pass through the WAF for the associated Page. Depending on whether Client-Side Protection is in blocking or logging mode, the Next-Gen WAF adds the `Content-Security-Policy` or the `Content-Security-Policy-Report-Only` response header. These headers deliver the policy to the end user's browser, and in the case of blocking mode, tell the end user's browser to enforce the policy. For example, if Client-Side Protection is in blocking mode and the `script-src` directive doesn't list `www.example.com` as an allowed source, the end user's browser blocks all scripts from `www.example.com`.

In both blocking and logging mode, the end user's browser logs the policy violation and sends a report to Fastly. If the violation is unique, Fastly stores the report. Violation uniqueness is defined by the following properties:

- Website and Page (e.g., `www.example.com/cc`)
- Effective or violated directive (e.g., `script-src`)
- Policy

  > **NOTE**
  >
  > When you make a change to your policy and activate the change, the activated policy is considered different from the previous version of the policy.

- Disposition (i.e., blocking or logging mode)
- Blocked URI (e.g., `https://example.com/js/library.js`)
- HTTP response status code
- Sample of the script if the effective directive is `script-src`

If a policy violation is not unique, Fastly increases the count on the existing report for the identical violation by one. We store reports for 90 days.

You can access stored reports from the Reports page in the Fastly control panel. If you want to update your policy based on a report, make note of the relevant effective directive and blocked URI, go to the Policy page, and add a new value for the effective directive, being sure to adhere to fetch directive syntax.

Protection mode	Response header	Actions taken when a resource violates the policy
Blocking	`Content-Security-Policy`	1. The end user's browser blocks the resource and logs the policy violation. 2. The end user's browser sends a policy violation report to Fastly. 3. If the violation is unique, Fastly stores the report. If not, Fastly increases the count on the report for the identical violation.
Logging	`Content-Security-Policy-Report-Only`	1. The end user's browser logs the policy violation. 2. The end user's browser sends a policy violation report to Fastly. 3. If the violation is unique, Fastly stores the report. If not, Fastly increases the count on the report for the identical violation.
Off	None, the policy is not sent to the end user's browser.	None

* * *

About the Client-Side Protection controls

/en/guides/about-the-client-side-protection-controls

In the Fastly control panel, use the Client-Side Protection menu to access the pages associated with Client-Side Protection:

1. Log in to the Fastly control panel.
2. Go to **Security** > **Client-Side Protection** and then select the link to one of the following pages:
    - **Inventory**, where you can view the client-side scripts and select response headers that Fastly observes for a Page.
    - **Reports**, where you can view unique policy violation reports.
    - **Policy**, where you can manage your policy for a Page.
    - **Pages**, where you can add and edit Pages.
    - **Website**, where you can add and edit websites.
3. If you navigated to the Inventory, Reports, or Policy page, click the menu ⌄ to the right of the Page name and select the appropriate Page.

About the Inventory page

The Inventory page has two tabs: **Scripts** and **Response headers**. The Scripts tab displays the list of observed scripts for a Page. From this tab, you can:

- use the search bar and authorization status menu to filter the listed scripts.
- click the pencil to the right of a script to add an authorization status for a script.

The Response headers tab displays the last-logged values for select, security-impacting response headers that Fastly observes for a Page.

About the Reports page

The Reports page displays unique policy violations. For each report, the following information is available:

- **Directive:** the directive whose enforcement caused the violation.

- **Blocked URI:** the URI of the resource that violated the policy. Depending on the policy's protection mode, this resource was either blocked or logged.
- **Status code:** the HTTP status code of the resource that violated the policy.
- **Disposition:** whether the resource that violated the policy was blocked or logged per the policy's protection mode.
- **Count:** the number of times the exact violation was reported.
- **Last seen:** the date and time the last instance of the policy violation was reported.
- **First seen:** the date and time the first instance of the policy violation was reported.

You can use the search bar, the Date range menu, and Directives menu to filter the list of reports.

About the Policy page

From the Policy page, you can create and manage a policy that applies to one Page. A policy is made up of directives, which tell the end user's browser what resources it's allowed to load and from where.

If a policy doesn't exist for a page, click **Create policy**. Once the policy has been created, you can use the **Protection mode** menu to change the policy's protection mode and modify directive values by:

- clicking **Add value** to the right of a directive to add a value.
- clicking the pencil to the right of a value to edit the value.
- clicking the trash to the right of a value to delete the value.

When you make a change to a policy, a draft of the policy is created. You must activate the draft policy to push the change to the active policy. Once the draft policy is activated, the active policy will reflect the change and the draft policy is deleted.

About the Pages page

The Pages page displays a list of your existing Pages. From this page, you can:

- click **Add Page** to create a new Page.
- click the pencil to the right of a Page to edit the Page.

- click the trash to the right of a Page to delete the Page.

About the Website page

The Website page displays a list of your websites. From this page, you can:

- click **Add website** to add a new website.
- click the pencil to the right of a website to edit the website.
- click the trash to the right of a website to delete the website.

---

* * *

	Managing your policy
	/en/guides/managing-your-policy

A content security policy (policy) controls the resources (e.g., scripts, images, and fonts) that load on an end user's browser for a Page. A policy only applies to one Page. Maintaining a policy helps guard against cross-site scripting attacks.

IMPORTANT

Policies have an active and draft state and are versionless. When you make a change to a policy, a draft of the policy is created. You must activate the draft policy to push the change to the active policy. Once the draft policy is activated, the active policy will reflect the change and the draft policy is deleted.

Prerequisites

Before creating and managing a policy, you must set up Client-Side Protection by creating at least one website and Page.

Limitations and considerations

When working with policies, keep the following in mind:

- When an object evaluated by the Next-Gen WAF is cached, the policy attached to the object is also cached. Both the object and policy are served together for as long as the object remains in the cache. If you update the policy, cached objects won't reflect the updated policy until the object is removed from cache and passes through the WAF again.
- A policy cannot be deleted. To prevent a policy from being added to responses, set the **Protection mode** setting to **Off**.

Creating a policy

To create a policy, complete the following steps:

1. Log in to the Fastly control panel.
2. Go to **Security** > **Client-Side Protection** > **Policy**.
3. From the workspaces bar, click the menu ⌄ to the right of the Page name and select a Page.
4. Click **Create policy**. A blank policy is created in draft state.
5. Add values for the directives on the policy, being sure to use fetch directive syntax.
6. From the **Protection mode** menu, select **Blocking** or **Logging**. The Protection mode setting tells the end user's browser how to handle policy violations.
7. Click **Activate** to activate the policy.

Managing directive source values

A policy is made up of directives. Each directive controls one type of resource and has source values. The source values define where that type of resource can be loaded from. For example, the `script-src` directive controls the allowed sources for JavaScript. Potential values for `script-src` are as follows:

> **TIP**
>
> This table only covers four syntax options for values. For a complete list, read Mozilla's Fetch directive syntax.

Syntax option	Example value	Description
`none`	`none`	Blocks all JavaScript resources from loading. If you use this value, the directive can't have any other values.
`self`	`self`	Allows loading of JavaScript resources from the same origin. For example, let's say the end user makes a request to `https://example.com`. The browser would load `https://example.com/foo.js` because the resource has the same origin. However, it would prevent `https://example.org/foo.js` from loading because it has a different origin.
`<host-source>`	`https://*.example.com`	Allows loading of JavaScript resources from subdomains of `example.com`.
`nonce-<nonce_value>`	`nonce-1234-abcd-5678-efgh`	Allows loading of JavaScript resources that have a tag with the matching `nonce`: `<script nonce="1234-abcd-5678-efgh"/>`. A `nonce` is a random string that your web server creates for a webpage.

Adding directive source values

To add a directive source value, complete the following steps:

1. Log in to the Fastly control panel.
2. Go to **Security** > **Client-Side Protection** > **Policy**.

3. From the workspaces bar, click the menu ⌄ to the right of the Page name and select a Page.
4. Find the appropriate directive and click **Add value**.
5. In the **Directive source** field, enter the source that you want to allowlist. Be sure to use fetch directive syntax.
6. Click **Add source**. A draft of the policy is created and the value is added to the directive.
7. Click **Activate** to activate the policy.

Editing directive source values

To edit a directive source value, complete the following steps:

1. Log in to the Fastly control panel.
2. Go to **Security** > **Client-Side Protection** > **Policy**.
3. From the workspaces bar, click the menu ⌄ to the right of the Page name and select a Page.
4. Click the pencil ✎ to the right of the directive value that you want to edit.
5. In the **Directive source** field, update the source that you want to allowlist. Be sure to use fetch directive syntax.
6. Click **Update value**. A draft of the policy is created and the value is updated.
7. Click **Activate** to activate the policy.

Deleting directive source values

To delete a directive source value, complete the following steps:

1. Log in to the Fastly control panel.
2. Go to **Security** > **Client-Side Protection** > **Policy**.
3. From the workspaces bar, click the menu ⌄ to the right of the Page name and select a Page.
4. Click the trash 🗑 to the right of the directive value that you want to delete.

5. Click **Remove value**. A draft of the policy is created and the value is removed from the directive.

6. Click **Activate** to activate the policy.

Changing the protection mode

Protection mode is a policy setting that tells the end user's browser how to handle policy violations (i.e., block or log the resource). To change the protection mode, complete the following steps:

1. Log in to the Fastly control panel.
2. Go to **Security** > **Client-Side Protection** > **Policy**.
3. From the workspaces bar, click the menu ⌄ to the right of the Page name and select a Page.
4. From the **Protection mode** menu, select one of the following options:
    - **Blocking:** the end user's browser blocks resources that violate the policy from loading and sends a policy violation report to Fastly.
    - **Logging:** the end user's browser allows resources that violate the policy to load and sends a policy violation report to Fastly.
    - **Off:** the policy is disabled and not sent to the end user's browser.

    A draft of the policy is created.
5. Click **Activate** to activate the policy.

Monitoring policy violation reports

You can view policy violation reports from the Reports page in the Fastly control panel. If you want to update your policy based on a report, make a note of the relevant effective directive and blocked URI, go to the Policy page, and add a new value for the effective directive.

---

* * *

Monitoring your inventory

/en/guides/monitoring-your-inventory

An inventory is a collection of the client-side scripts and security-impacting response headers that Fastly observes for a Page. Each inventory is associated with a single Page. Reviewing changes to your inventory can help you identify security issues that should be investigated.

Prerequisites

Before Fastly creates an inventory for your Page, you must set up Client-Side Protection by creating at least one website and Page.

Reviewing inventoried scripts

For each observed script in the inventory, you can add an authorization status to help keep track of which scripts you've reviewed for legitimacy. If a script shouldn't be loading, investigate the issue and take action accordingly.

To add an authorization status, complete the following steps:

1. Log in to the Fastly control panel.
2. Go to **Security** > **Client-Side Protection** > **Inventory**.
3. From the Pages bar, click the menu ⌄ to the right of the Page name and select a Page.
4. Click the pencil to the right of the script you want to add an authorization status for.
5. From the **Authorized** menu, leave **Yes** selected to authorize the script. Select **No** to not authorize the script.
6. In the **Justification** field, enter the reason the script is authorized or not authorized.
7. Click **Update**.

When Fastly detects changes to a script that has an authorization status, Fastly resets the authorization status.

Monitoring response headers

Fastly logs the following security-impacting response headers for all responses that have the `Content-Security-Policy-Report-Only` response header:

- `Access-Control-Allow-Origin`
- `Content-Security-Policy`
- `Cross-Origin-Embedder-Policy`
- `Cross-Origin-Opener-Policy`
- `Cross-Origin-Resource-Policy`
- `Permissions-Policy`
- `Referrer-Policy`
- `Strict-Transport-Security`
- `X-Content-Type-Options`
- `X-Frame-Options`
- `X-XSS-Protection`

Every three days, Fastly sends you a list of the response headers that changed to the email address you defined on the associated Page. The changes are grouped into 60-minute periods. If you think that a response header value is dangerous, investigate the issue and take action accordingly.

---

* * *



Setting up Client-Side Protection



/en/guides/setting-up-client-side-protection

To get started with Client-Side Protection, create at least one website and Page. Together, a website and Page define the full URLs of the webpages that you want to monitor and protect (e.g., `https://www.example.com/checkout` and `https://www.example.com/cc`).

Limitations & considerations

When using Client-Side Protection, keep in mind the following:

- Only users assigned the role of superuser can manage websites and Pages.
- The inventory process runs on a non-configurable sampled basis. Your website's traffic volume factors into the frequency at which the inventory process runs. Creating or updating a Page does not trigger the inventory process.
- When inventorying the scripts that are observed for a Page, Client-Side Protection doesn't capture where the scripts were loaded from.
- A Page can support a maximum of 1,000 paths.

Managing websites

A website is a base URL (e.g., `https://www.example.com` or `https://www.app.example.com`).

To add a website, complete the following steps:

1. Log in to the Fastly control panel.
2. Go to **Security** > **Client-Side Protection** > **Websites**.
3. Click **Add website**.
4. In the **Website** field, enter the base URL of your website.
5. Click **Continue to add page** to create a Page that is associated with the website you just created. Alternatively, click **Add website** to create the website without any associated Pages.

To edit a website, complete the following steps:

1. Log in to the Fastly control panel.
2. Go to **Security** > **Client-Side Protection** > **Websites**.
3. Click the pencil to the right of the website you want to edit.
4. In the **Website** field, enter the base URL of your website.
5. Click **Update**.

When you delete a website, all associated Pages and inventories will be deleted. To delete a website, complete the following steps:

1. Log in to the Fastly control panel.
2. Go to **Security** > **Client-Side Protection** > **Websites**.
3. Click the trash to the right of the website you want to delete.
4. Click **Delete website**.
5. In the **Enter website** field, enter the base URL of the website that you want to delete and then click **Delete**.

Managing Pages

A Page is a single path (e.g., `/checkout`) or collection of paths that describe a similar component or user experience on a website (e.g., `/checkout` and `/edit-cc`). Multiple Pages can be associated with the same website.

To add a Page, complete the following steps:

1. Log in to the Fastly control panel.
2. Go to **Security** > **Client-Side Protection** > **Pages**.
3. Click **Add page**.
4. Fill out the Add page form as follows:
    - In the **Page name** field, enter a name for the Page.
    - In the **Page description** field, enter a description of the Page.
    - From the **Website** menu, select the appropriate website.
    - In the **Alert email** field, enter an email address that should receive notifications about your Page.
    - Leave the **Inventory all paths** checkbox selected to inventory all of the website's paths. Deselect the checkbox if you want to specify the paths that should be inventoried.
    - If you deselected the **Inventory all paths** checkbox, in the **Paths** field, enter a path that should be inventoried. For each additional path that needs inventorying, click the plus + sign next to the last path you entered.

5. Click **Add page**.

To edit a Page, complete the following steps:

> **NOTE**
>
> If you remove or update a path, the scripts that were observed at the removed or updated path will remain in the inventory until they are no longer observed for 90 days.

1. Log in to the Fastly control panel.
2. Go to **Security** > **Client-Side Protection** > **Pages**.
3. Click the pencil to the right of the Page you want to edit.
4. Fill out the Edit page form as follows:
   - In the **Page name** field, enter a name for the Page.
   - In the **Page description** field, enter a description of the Page.
   - From the **Website** menu, select the appropriate website.
   - In the **Alert email** field, enter an email address that should receive notifications about your Page.
   - Select the **Inventory all paths** checkbox selected to inventory all of the website's paths. Deselect the checkbox if you want to specify the paths that should be inventoried.
   - If you deselected the **Inventory all paths** checkbox, in the **Paths** field, enter a path that should be inventoried. For each additional path that needs inventorying, click the plus + sign next to the last path you entered.
5. Click **Update page**.

When you delete a Page, the associated inventory is also deleted. To delete a Page, complete the following steps:

1. Log in to the Fastly control panel.
2. Go to **Security** > **Client-Side Protection** > **Pages**.
3. Click the trash to the right of the Page you want to delete.
4. Click **Delete page**.

What's next

For each Page that you've created, you can monitor the associated inventory that Fastly creates and create a policy that controls the resources that the end user's browser is allowed to load.

---

* * *

Category: DDoS Protection

These articles describe the automatic DDoS Protection that keeps applications and APIs available and performant.

	About DDoS Protection
🔗	/en/guides/about-ddos-protection

Fastly DDoS Protection provides metrics that help you analyze DDoS attack traffic directed at your applications, APIs, and origin servers over time. Its controls and dashboards provide both high-level and specific details about potential DDoS events and any mitigation rules generated as a result.

Before you begin

Keep in mind the following things when working with Fastly DDoS Protection:

- Fastly DDoS Protection is disabled by default, but can be enabled directly in the Fastly control panel to immediately establish a defensive posture against attack traffic.
- Enabling Fastly DDoS Protection and then either logging or blocking potential attack traffic may result in changes to your bill if you pay using month-to-month billing.
- Once Fastly DDoS Protection is enabled, all account users will be able to access the DDoS Protection menu in the Fastly control panel.

Enabling and disabling Fastly DDoS Protection


After Fastly DDoS Protection has been purchased for your account, it can be enabled and disabled in the Fastly control panel by anyone assigned the role of superuser or engineer.

> **WARNING**
>
> Enabling, disabling, or making changes to Fastly DDoS Protection on a service immediately impacts all service versions, including the active one.

Enabling Fastly DDoS Protection

To enable Fastly DDoS Protection on a service, follow these steps:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Service configuration**.
4. In the **Security** area, click the **DDoS Protection** switch to **On** to immediately enable DDoS Protection for this service.



5. Using the **Protection mode** menu, decide what to do next for this service:
   - Leave the menu set to `Logging` to immediately begin logging potential attack traffic for observation without mitigation.
   - Select `Blocking` to immediately begin mitigating attacks that DDoS Protection detects.
   - Select `Off` to temporarily stop logging or mitigating attack traffic, but without disabling DDoS Protection.

> **NOTE**

> These instructions refer to protection mode in the context of Fastly DDoS Protection in the Fastly control panel. To enable agent mode (protection mode) on Fastly's Next-Gen WAF, check out our guide about the agent mode instead.

Disabling Fastly DDoS Protection

To immediately disable Fastly DDoS Protection on a service, follow these steps:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Service configuration**.
4. In the **Security** area, click the **DDoS Protection** switch to **Off** to immediately disable DDoS Protection for this service.

Security products note

No security product, such as a WAF or DDoS mitigation product, including those security services offered by Fastly, will detect or prevent all possible attacks or threats. As a subscriber, you should maintain appropriate security controls on all web applications and origins. The use of Fastly's security products does not relieve you of this obligation. As a subscriber, you should test and validate the effectiveness of Fastly's security services to the extent possible prior to deploying these services in production, continuously monitor their performance, and adjust these services as appropriate to address changes in your web applications, origin services, and configurations of the other aspects of your Fastly services.

---

* * *

	About the DDoS Protection controls
🔗	/en/guides/about-the-ddos-protection-controls

In the Fastly control panel, use the DDoS Protection menu to access the pages associated with DDoS Protection.


1. Log in to the Fastly control panel.

2. Go to **Security** > **DDoS Protection** and then select the link to one of the following pages:

    - **Dashboards**, where you can view metrics related to attack requests and mitigations for each of your services.
    - **Events**, where you can view the DDoS event details associated with a specific service.

About the Dashboards page

The Dashboards page displays metrics about request volumes over time for a specific service, as well as requests labeled as attacks and attack requests that were mitigated.



The controls on the Dashboards page allow you to filter the data displayed there:


- the **Service** menu allows you to specify the service that the metrics are drawn from.

- the **Region** menu allows you to limit the displayed metrics on any dashboard to a specific region around the world.
- the **Time range** menu allows you to change the timeframe over which metrics will be displayed. By default, the system displays 1 days worth of static data. The selected timeframe and time zone persist as you navigate between service dashboards.
- the **Live** button allows you to change displayed metrics to live data that changes in real time. Click **Exit Live View** to stop viewing the live data stream.

You can also learn more information by hovering over any part of the graph. This displays a timestamp indicator that updates as you move the cursor along with a service version indicator.

About the Events page

The Events page displays a list of the DDoS events associated with a service, including a basic summary of the details about it and the short-lived rules that were created to manage it. For example, if the system detects an unusual traffic spike, it may generate a temporary rule to filter or limit the impact.



Clicking on the name of any event listed on the Events page takes you to expanded information about that event including:

- **Event details** provide information about a detected DDoS event, which represents a specific potential attack. Events are associated with a timestamp, detected or blocked traffic data (depending on whether Logging or Blocking mode is active), and one or more Event Rules. Customers can view key details such as the event's name, unique ID, status, start and end times, peak traffic volume, and the list of rules applied to mitigate it.

- **Event rules** define the conditions and attributes used to filter or mitigate traffic for a DDoS event. These rules help manage traffic based on specific characteristics, such as IP addresses, Autonomous System Numbers (ASNs), countries, prefixes, and hostnames. Customers can review details including rule IDs, associated attributes, and a summary of traffic patterns by IP addresses, hostnames, user agents, and IP prefixes.

The information on the Events page can help you understand why traffic was identified as part of a potential DDoS attack and how mitigation rules were applied in response.

* * *

Category: Rate Limiting

These articles describe how to work with Fastly's rate limiting features.

About rate limiting

/en/guides/about-rate-limiting

Rate limiting is a way to control the rate at which traffic flows through Fastly's network to your origins. You might need rate limiting if you need to do things like prevent abusive bots, mitigate DDoS attacks, measure types of activity so you can meter them, and create queueing solutions like waiting rooms to prevent traffic surges.

NOTE

This page discusses basic information about using the main dashboard for our Edge Rate Limiting product. Edge Rate Limiting is designed for use cases where a faster response to large volumes of traffic is required (e.g., mitigating DDoS attacks). For details about Advanced Rate Limiting and its use in the Fastly Next-Gen WAF, refer to the advanced rate limiting rules documentation.

About the Edge rate limiting page

The Edge rate limiting page displays a summary of all rate limiting policies currently in effect across your services. Each summary includes the following details:

- **Service:** the name of the service
- **Policy name:** the name of the rate limiting policy
- **Requests per second:** the maximum number of requests per second within the detection window counted before enacting the rate limiting policy
- **Detection window:** the duration of the rate limiting window

- **Action:** the action taken once the rate limit is exceeded, either `Block` or `Log only`

Security products note

No security product, such as a WAF or DDoS mitigation product, including those security services offered by Fastly, will detect or prevent all possible attacks or threats. As a subscriber, you should maintain appropriate security controls on all web applications and origins. The use of Fastly's security products does not relieve you of this obligation. As a subscriber, you should test and validate the effectiveness of Fastly's security services to the extent possible prior to deploying these services in production, continuously monitor their performance, and adjust these services as appropriate to address changes in your web applications, origin services, and configurations of the other aspects of your Fastly services.

---

* * *

	Working with rate limiting policies
🔗	/en/guides/working-with-rate-limiting-policies

You can use the Fastly Rate Limiting feature to create rate limiting policies. When you create a rate limiting policy, you define the criteria to track requests counts and their rates over time. Accumulated counts are converted to an estimated rate computed over the time window you specify: either 1s, 10s or 60s. Rates are always measured in requests per second (RPS). If the rate limit is exceeded, Fastly logs the event and can also block additional requests for a time period you specify.

Limitations and considerations

When creating or making changes to a rate limiting policy, consider the following questions:

- Should the service be protected, or should different protection levels be configured for different endpoints? For example, authentication-related endpoints may require more strict limits.
- How should clients be identified? For example, should the client key be the client IP address, or a more complex key that identifies individual clients behind a single IP address?

- How should the rates be set? A typical client rate should be established, and rate limiting should be configured over an appropriate time window to allow normal client usage, including some overhead to prevent false positives.

When testing a rate limiting policy, keep the following things in mind:

- You can use logging to test that your rate limiting configuration is behaving as desired.
- You can identify clients or client IP addresses to be excluded. For example, remote performance monitoring, testing solutions, and penetration testing solutions could be excluded from a rate limiting policy.
- If you're using shielding, you may need to make modifications to your rate limiting policy. Refer to the developer documentation for more information.

Creating a rate limiting policy at the edge

Create a rate limiting policy at the edge by following these steps:

1. Log in to the Fastly control panel.
2. Go to **Security** > **Edge rate limiting**.
3. Click **Add rate limiting to a service**.

Edge rate limiting

Limit the number of requests to your origin (PASS) traffic. Once over the limit, requests will be blocked.
For fine-grained control visit our rate limiting documentation.

Policy name Example Rate Limit * Required

Give your rate limiting policy a name.

Service Select a service version * Required

The service and version the policy applies to.

Detect Define the detection criteria for the rate limiting policy.

Destination to protect

- (•) Protect all traffic to origin
- ( ) Protect paths specified in an Edge Dictionary

HTTP Methods

- [x] GET
- [x] PUT
- [x] TRACE
- [x] POST
- [x] HEAD
- [x] DELETE
- [x] PATCH
- [x] OPTIONS

The type of requests made to origin that Fastly will detect.

Requests per second 1000 * Required

The maximum rate of requests per second within a detection window.

Detection window

- ( ) **1 second -** fastest time to detect, lowest accuracy.
- ( ) **10 seconds -** medium accuracy.
- (•) **60 seconds -** slowest time to detect, highest accuracy.

Client keys IP

The client keys used to aggregate the requests being counted.

Respond Define how Fastly should respond to a threat if the limit is exceeded.

If the limit is exceeded

- (•) Block with custom response
- ( ) Block with response object
- ( ) Log only

Status 429

MIME type text/html


Response

```
<html>
  <head>
    <title>Too Many Requests</title>
  </head>
  <body>
    <p>Too Many Requests</p>
  </body>
</html>
```

Response duration 2 * Required

In minutes, how long the response will persist before the rate limiter resets and unblocks requests.

4. In the **Policy name** field, enter a human-readable name for your policy. This name is displayed on the rate limiting dashboard.



5. From the **Service** menu, select the service and version you want to apply the policy to. Use the search box to search by ID or name.

6. In the **Detect** section, fill out the fields to define the detection criteria for the rate limiting policy:

    - In the **Destination to protect** field, select whether to protect all traffic to origin or specific requests via a dictionary. If the service you selected doesn't have a dictionary, this option is disabled.

    - In the **HTTP Methods** field, select the check box next to the types of request to detect.

    - In the **Requests per second** field, enter the maximum number of requests per second to count within the detection window before enacting the rate limiting policy. The lowest rate limit supported by this feature to demonstrate effective behavior is 10 RPS. Using a limit below 10 RPS may result in unpredictable accuracy and detection time.

    - In the **Detection window** field, select the duration of the rate limiting window. The window size helps determine the effective time to detection (TTD) for excessive traffic to your origin. You can use a shorter window to improve the detection time for attacks at some expense of accuracy. For more information, review the limitations and caveats.

    - From the **Client keys** menu, select either **IP**, **User-Agent**, or **IP and User-Agent** to aggregate the requests being counted.

7. In the **Respond** section, select how Fastly should respond to your rate limiting policy being exceeded, then fill out the additional fields that appear.

    - **Block with custom response:** block requests once the rate limit is exceeded and display a custom response in the browser. See Block with custom response.

    - **Block with response object:** block requests once the rate limit is exceeded and display a response object in the browser. Note that you must have a response object created to use this option. See Block with response object.

    - **Log only:** log when the rate limit is exceeded but still allow requests. See Log only.

8. Click **Save policy**.

> **NOTE**
>
> You can create an advanced configuration by configuring rate limiting in VCL. Refer to the developer documentation for more information.

Using dictionaries for more specific protection


Edge Rate Limiting allows you to specify paths to protect using dictionaries. You must specify a path to protect as a key in the key-value pair within a dictionary. For example, to protect a specific API, such as `/checkout`, you would create a key-value pair where the key is `/checkout` and the value is `Checkout`.

Note the following:

- Keys must be specified using relative paths and without using a trailing `/`.
- Query strings are excluded.
- Keys using regex are not supported.

Block with custom response


Select the **Block with custom response** option to block requests once the rate limit is exceeded and display a custom response. If you select this option, the following fields become available:



- In the **Status** field, enter an HTTP status code to display in the browser.
- In the **MIME type** field, enter a media type identifier. Any MIME type can be specified as long as it's compatible with the text entered in the `Response` field.
- In the **Response** field, enter the custom response that appears in the browser when the rate limit is exceeded.
- In the **Response duration** field, enter a value between 1 and 60 to determine how long, in minutes, to display the custom response before the rate limiter resets and unblocks requests.

Block with response object

Select the **Block with response object** option to block requests once the rate limit is exceeded and display a response object. Note that you must have a response object created to use this option. If you select this option, the following fields become available:



- From the **Response object** menu, select the response object that will appear in the browser when the rate limit is exceeded.

> **NOTE**
>
> Make sure the response object selected has a condition attached or else the response will be returned for all requests.


- In the **Response duration** field, enter the number of minutes you want the custom response to appear before the rate limiter resets and unblocks requests.

Log only

Select the **Log only** option to log when the rate limit is exceeded but still allow requests. By default, the following fields are logged: `timestamp`, `policy_name`, `url`, `limit`, `window`, `entry`, and `rate`.

> **NOTE**
>
> In place of the `timestamp` field, Datadog logs `time_start` and Honeycomb logs `time`.

If you select this option, the **Logging provider** menu becomes available. Select the logging endpoint where you want to send logs. Once you click **Save policy**, an abbreviated form appears to create a logging endpoint for the provider you specified. Complete the fields and then click **Save**.



> **NOTE**
>
> You can only have one logging endpoint for all rate limiting policies. By default, the logging endpoint is named `ratelimit-debug`. You can also create this endpoint via the Fastly control panel or API.

Log formats

The following JSON log formats are used when you choose the Log only option. These schemas can be useful to understand how data is written to different logging providers.

Unless otherwise specified, the default format is used to log information about particular policies that exceed the rate limit.

```
{
  "timestamp": "%{strftime({"%Y-%m-%dT%H:%M:%S"}, time.start)}V",
  "policy_name": "%{json.escape("<rate limiter name>")}V",
  "url": "%{json.escape(req.url)}V",
  "limit": <limit>,
  "window": <window>,
  "entry": "<entry>",
  "rate":  "<rate>"
}
```

```
{
  "time_start": “%{strftime({"%Y-%m-%dT%H:%M:%S%Z"}, time.start)}
  "ddsource": "fastly",
  "service": “%{req.service_id}V",
  "policy_name": "%{json.escape(“<rate limiter name>”)}V”,
  "url": “%{json.escape(req.url)}V”,
  "limit": <limit>,
  "window": <window>,
  "entry": "<entry>",
  "rate":  “<rate>"
}
```

```
{
  "time": “%{strftime({"%Y-%m-%dT%H:%M:%SZ"}, time.start)}V”,
  "data":{
    "service_id": “%{req.service_id}V",
    "policy_name": "%{json.escape(“<rate limiter name>”)}V”,
    "url": “%{json.escape(req.url)}V”,
    "limit": <limit>,
    "window": <window>,
    "entry": "<entry>",
    "rate":  “<rate>"
  }
}
```

Editing a rate limiting policy

After you've created a rate limiting policy, you can edit the same controls specified when you created the policy. You can only edit policies attached to services in a Draft state. You cannot edit policies attached to Active or Locked services.

To edit a rate limiting policy, follow the steps below:

1. Log in to the Fastly control panel.

2. Go to **Security** > **Edge rate limiting**.
3. Locate the rate limiting policy you want to edit.
4. For policies attached to a Draft service, click the pencil to edit the rate limiting policy. For policies attached to an Active or Locked service, click **Clone version to edit**.
5. Update the values of the edge rate limiting controls you want to edit.
6. Click **Save policy**.

Deleting a rate limiting policy

To delete a rate limiting policy, follow the steps below. You can only delete policies attached to services in a Draft state. You cannot delete policies attached to Active or Locked services. To delete a policy attached to an Active or Locked service, you must first clone the service.

To delete a rate limiting policy:

1. Log in to the Fastly control panel.
2. Go to **Security** > **Edge rate limiting**.
3. Locate the rate limiting policy you want to delete.
4. For policies attached to a Draft service, click the trash and then **Confirm and delete** to delete the rate limiting policy.

Security products note

No security product, such as a WAF or DDoS mitigation product, including those security services offered by Fastly, will detect or prevent all possible attacks or threats. As a subscriber, you should maintain appropriate security controls on all web applications and origins. The use of Fastly's security products does not relieve you of this obligation. As a subscriber, you should test and validate the effectiveness of Fastly's security services to the extent possible prior to deploying these services in production, continuously monitor their performance, and adjust these services as appropriate to address changes in your web applications, origin services, and configurations of the other aspects of your Fastly services.

---

* * *

Category: TLS

These articles describe how to set up TLS certificates with Fastly services.

Enabling TLS 1.3 through Fastly

/en/guides/enabling-tls-1-3-through-fastly

IMPORTANT

TLS 1.3 is now the default TLS version. You only need to follow the instructions in this guide if you created your account on or before June 29, 2020.

This guide describes how to use Fastly TLS to enable TLS 1.3 for a domain using a TLS certificate you provide or one that Fastly provides and manages.

About TLS 1.3

To serve secure, encrypted traffic from Fastly using the Hypertext Transfer Protocol Secure (HTTPS) protocol, a website or application must provide a valid TLS certificate that is digitally signed by a trusted certification authority. Transport Layer Security (TLS) and its predecessor, Secure Sockets Layer (SSL), are the protocols that allow clients to form secure communication connections between web browsers or applications and the servers they request information from.

TLS 1.3, the newest version of the TLS protocol, was designed to improve the performance and security of traffic for HTTPS domains. Specifically, this version of the protocol was designed to help speed up encrypted connections to servers by eliminating an entire round trip from its connection establishment handshake. The Zero Round Trip Time (0-RTT) feature can reduce the latency of resumed connections by encrypting requests in the initial ClientHello, a step in the client handshake process that specifies the maximum protocol version the client wishes to support.

In addition, TLS 1.3 allows only cipher suites that offer Perfect Forward Secrecy (PFS) for securing and encrypting traffic. TLS 1.3 also specifically prohibits TLS renegotiation, a process that allows changing the details of a TLS handshake after a connection has already

been established with the server. Both restrictions make TLS 1.3 more secure than previous versions of the protocol.

When to use the Fastly control panel and when to contact Support

You can only enable TLS 1.3 via the Fastly control panel if you have purchased or are using:

- Fastly TLS,
- Concierge TLS, or
- Fastly's Legacy Customer-Provided TLS Certificate Hosting Service

and your domains have not been configured on Dedicated IP addresses that Fastly maintains and manages for you.

If you have purchased or are using Platform TLS or Dedicated IP addresses, or you have custom domain mapping in place, you must contact support and have them enable TLS 1.3 for you.

Limitations and key behaviors


Before enabling or requesting this functionality, keep the following in mind:

- Negotiation of the TLS protocol will only happen if the requesting client also supports TLS 1.3. If a request comes from an older client, Fastly's default behavior is to downgrade to TLS 1.2.
- Fastly currently only supports 0-RTT between Fastly and requesting clients. We do not support 0-RTT between Fastly and your origin servers.
- By default, Fastly only answers idempotent requests (GET and HEAD requests without query parameters) over 0-RTT. This helps protect customer applications from replay attacks.
- Requests issued with 0-RTT will include an `Early-Data:1` header per RFC 8470. This attribute can be queried and logged via VCL using `req.http.early-data`.

Setting up TLS 1.3 for a new domain

Setting up TLS for a domain requires you to secure the domain by registering it with a certification authority. To start this process through the Fastly control panel (instead of programmatically) follow these steps.

1. Log in to the Fastly control panel.
2. Go to **Security** > **TLS management** > **Domains**.
3. Click **Secure another domain**.
4. Decide what to do next:
    - If you have your own TLS certificates and private keys, click **Use certificates you've provided** and then follow the instructions in the guide to uploading and deploying your own certificates instead of this one.
    - If you want Fastly to procure and manage your TLS certificates and keys, continue with the remaining steps that follow.
5. From the selection menu that appears, select **Use certificates Fastly obtains for you**.
6. In the **Domain** field, enter one or more apex domains (e.g., `example.com`), subdomains (e.g., `www.example.com` or `api.example.com`), or a wildcard domain (e.g., `*.example.com`) and click **Add**. Domains you add appear in the Common name area of the page.



If you only have one domain, the common name will be the same as the domain name. If you add more than one domain, they will appear in a menu. By default, the first domain you add will be selected for you. Select another domain from the **Common name** menu if that's not the one you want.

7. From the **Select a certification authority** controls, choose one of the certification authorities to secure your certificate. Prices vary between certification authorities, sometimes significantly. Be sure to review the details about these differences on our pricing page.

8. If you previously enabled TLS in your Fastly account, use the **Select a TLS configuration** menu to select a TLS 1.3 configuration to apply. Your selection will specify both the IP addresses that the certificate will be deployed to and the associated TLS settings that will be applied to them.

    - Select **HTTP/3 & TLS v1.3** to apply the latest version of the protocol, but without 0-RTT.
    - Select **HTTP/3 & TLS v1.3 + 0RTT** to apply the latest version of the protocol with 0-RTT.

    However, if you are enabling TLS in your Fastly account for the first time on or after March 29, 2022, this menu will not appear. Your TLS configuration will use HTTP/3 & TLS v1.3 + 0RTT by default.

9. Click **Submit**. The Subscription details page appears displaying your domains along with detailed steps on how to verify you own them.

10. Click **View details** to view information for your domain and use it to update your DNS records with your DNS provider.

Applying TLS 1.3 to an existing domain

To migrate an existing domain to a new TLS 1.3 configuration, follow these steps:

1. Log in to the Fastly control panel.
2. Go to **Security** > **TLS management** > **Domains**.
3. Find the card for the appropriate domain.
4. Click **View/Edit Activation** next to the appropriate certificate.
5. From the list of configurations that appear, click **Activate** next to the TLS 1.3 configuration you want to apply. Your selection will specify both the IP addresses that the certificate will be deployed to and the associated TLS settings that will be applied to them.
    - Activate **HTTP/3 & TLS v1.3** to apply the latest version of the protocol, but without 0-RTT

- Activate **HTTP/3 & TLS v1.3 + 0RTT** to apply the latest version of the protocol with 0-RTT.

6. Click **Done**.
7. Watch the **TLS status** area for the certificate. Once the configuration is selected, the status for the domain will change to `Deploying`. When the TLS status area changes back to `Activated`, the TLS configuration selected will have been applied to the domain.
8. Click **View details** to view information for your domain and use it to update your DNS records with your DNS provider.
9. Confirm the new DNS records have propagated across the internet (this can take up to 48 hours), then delete the old TLS configuration by clicking the trash .

---

* * *

TLS origin configuration messages

/en/guides/tls-origin-configuration-messages

When you are connecting to origins over TLS, you may have errors.

Hostname mismatches

- `Error: Hostname mismatch`

Why the error appears

Your origin server is serving a TLS certificate with a Common Name (CN) or list of Subject Alternate Names (SAN) that does not match the origin host or the origin's SSL hostname setting.

How to fix it

You can fix this by telling Fastly what to match against in the CN or SAN field in your origin's certificate.

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Origins**.
5. Click the pencil to edit the affected host.
6. In the **Certificate Hostname** field, enter the hostname associated with your TLS certificate. This value is matched against the certificate common name (CN) or a subject alternate name (SAN) depending on the certificate you were issued. For example, if your certificate's CN field is `www.example.com`, enter that value for your hostname.
7. Click **Update**.
8. Click **Activate** to deploy your configuration changes.

When using custom VCL, you can specify the hostname to match against the certificate by using the `.ssl_cert_hostname` field of your origin's definition. For example: `.ssl_cert_hostname = www.example.com;`.

Certificate chain mismatches

- `Error: unable to verify the first certificate`
- `Error: self signed certificate`
- `Error: unable to get local issuer certificate`
- `Error: self signed certificate in certificate chain`
- `Error: unable to get issuer certificate`

Why the errors appear

Your origin server is serving a certificate chain that can not be validated using any of the certification authorities (CAs) that Fastly knows. This can happen for two reasons:

- Your certificate is self-signed or self-issued and you did not provide your generated CA certificate to Fastly for us to use for verification.

- Your certificate is issued by a CA that isn't in Fastly's CA certificates bundle.

How to fix them

In both cases, you can fix your configuration by adding the CA certificate that Fastly should use to verify the certificate to your service configuration:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Origins**.
5. Click the pencil to edit the affected host.
6. In the **TLS CA certificate** field, copy and paste a PEM-formatted CA certificate.
7. Click **Update**.
8. Click **Activate** to deploy your configuration changes.

If you are using custom VCL, you can specify the CA for Fastly to use by setting the `.ssl_ca_cert` backend parameter to a PEM encoded CA certificate.

Alternatively, you can get a new certificate issued by a CA in Fastly's CA certificate bundle (e.g., Globalsign).

Connection failures

- `Error: Gethostbyname`
- `Error: Connection timeout`
- `Error: Connection refused`

Why each error appears and how to fix it

For `Gethostbyname` failures, the configured backend Host domain is returning NXDOMAIN. Double check that the DNS settings for your backend are correct.

For `Connection time out` failures, the connection to your server is timing out. Double check that your backend is accessible and responding in a timely fashion.

For `Connection refused` failures, the connection to your server is being refused, potentially by a firewall or network ACL. Double check that you have allowlisted the Fastly IP addresses and that your backend is accessible from our network.

Certificate expirations

`Error: Certificate has expired`

Why the error appears

The certificate your backend server is presenting Fastly has expired and needs to be reissued with an updated validity period.

How to fix it

If this is a self-signed certificate you can perform this update on your own by issuing a new CSR with your private key, creating the corresponding certificate, and installing it on the server.

If this is a CA signed certificate you will need to issue a new CSR with your private key, submit it to your CA, and install the signed certificate they provide you.

SSL and old TLS protocol errors

- `Error: Unknown protocol`
- `Error: SSL handshake failure`
- `Error: TLSv1 alert internal error`

Why the errors appear

Either your origin server is not configured to use TLS or it only supports older, outdated versions of the protocol. We do not support SSLv2 or SSLv3.

How to fix them

If the origin server is configured to use TLS, use the following information to troubleshoot the problem:

- Make sure your server software is up to date and running a recent version of the TLS libraries for your platform or operating system. You may have to explicitly enable a newer protocol version. Fastly supports TLS 1.3, 1.2, 1.1, and 1.0.

- Confirm that you can connect to your origin. For example, if you're using TLS 1.3, enter a command like:

  ```
  $ echo Q | openssl s_client -connect ${IP}:443 -tls1_3
  ```

  To test other versions of TLS, you can replace `-tls1_3` with `tls1_2`, `-tls1_1`, or `-tls1_0`. If the TLS handshake is successful, you should see output showing the certificate, the subject, the issuer, and additional diagnostic information.

- Use `sslscan` to list the TLS protocols and ciphers supported by the TLS server.

If the origin server is not configured to use TLS, change your service configuration to disable TLS and communicate with it on port 80 instead of port 443:

1. Log in to the Fastly control panel.
2. From the **Home** page, select the appropriate service. You can use the search box to search by ID, name, or domain.
3. Click **Edit configuration** and then select the option to clone the active version.
4. Click **Origins**.
5. Click the pencil to edit the affected host.
6. From the **Connect to backend using TLS** menu, select **No**.
7. Click **Update**.
8. Click **Activate** to deploy your configuration changes.

RC4 cipher error

- `Error: Using RC4 Cipher`

Why the error appears

When Fastly connects to your origin server using TLS, the only cipher suite your server supports for establishing a connection is the RC4 cipher. This cipher is considered to be unsafe for general use and should be deprecated.

How to fix it

You can fix this on your origin by using the latest version of both the server and the TLS library (e.g., OpenSSL) and ensuring the cipher suites offered are tuned to best practices. You may need to explicitly blocklist the RC4 cipher.

---

* * *

	TLS termination
🔗	/en/guides/tls-termination

Identifying TLS terminated requests

To maintain optimal caching performance, Fastly uses a TLS terminator separate from the caching engine. This means, however, that the caching engine doesn't know that it was originally a TLS request. As a result, we set the `Fastly-SSL` header when fetching the content from your servers.

Because we set this header, you can check for its presence on your backend by including something like this in your `vcl_recv` subroutine:

```
if (req.http.Fastly-SSL) {
    set resp.http.X-Is-SSL = "yes";
  }

```

and that should tell you if the request was a TLS request or not.

When using WordPress

If you're using Fastly TLS services with WordPress, you'll want to add a check for the `HTTP_FASTLY_SSL` header so that WordPress can build URLs to your CSS or JS assets correctly. Do this by placing a check in your `wp-config.php` file to override the SSL flag that is checked later:

```
if (!empty( $_SERVER['HTTP_FASTLY_SSL'])) {
    $_SERVER['HTTPS'] = 'on';
  }
```

Finding the original IP when using TLS termination

Services

Pricing

Managed CDN

Developers

Network Status

Try Fastly Free

Support Plans

Resource Library

Contact Us

Network Map

Talk to an Expert

Blog

Events

Company

About Us

Careers

Customer Stories

Partners

News

Investor Relations

Trust

© Fastly 2025

Archives Changelog Translations Terms of Service Policy FAQ